
tdl Documentation

Release 9.0.0

Kyle Stewart

Feb 17, 2019

1	Status	3
2	About	5
3	Usage	7
4	Installation	9
4.1	Windows / MacOS	9
4.2	Linux	9
5	Requirements	11
6	License	13
7	Changelog	15
7.1	Unreleased	15
7.2	9.0.0 - 2019-02-17	15
7.3	8.5.0 - 2019-02-15	15
7.4	8.4.3 - 2019-02-06	16
7.5	8.4.2 - 2019-02-05	16
7.6	8.4.1 - 2019-02-01	16
7.7	8.4.0 - 2019-01-31	16
7.8	8.3.2 - 2018-12-28	17
7.9	8.3.1 - 2018-12-28	17
7.10	8.3.0 - 2018-12-08	17
7.11	8.2.0 - 2018-11-27	17
7.12	8.1.1 - 2018-11-16	18
7.13	8.1.0 - 2018-11-15	18
7.14	8.0.0 - 2018-11-02	18
7.15	7.0.1 - 2018-10-27	18
7.16	7.0.0 - 2018-10-25	18
7.17	6.0.7 - 2018-10-24	19
7.18	6.0.6 - 2018-10-01	19
7.19	6.0.5 - 2018-09-28	19
7.20	6.0.4 - 2018-09-11	19
7.21	6.0.3 - 2018-09-05	19
7.22	6.0.2 - 2018-08-28	19

7.23	6.0.1 - 2018-08-24	19
7.24	6.0.0 - 2018-08-23	20
7.25	5.0.1 - 2018-07-08	20
7.26	5.0.0 - 2018-07-05	20
7.27	4.6.1 - 2018-06-30	20
7.28	4.5.2 - 2018-06-29	20
7.29	4.5.1 - 2018-06-23	21
7.30	4.5.0 - 2018-06-12	21
7.31	4.4.0 - 2018-05-02	21
7.32	4.3.2 - 2018-03-18	21
7.33	4.3.1 - 2018-03-07	22
7.34	4.3.0 - 2018-02-01	22
7.35	4.2.3 - 2018-01-06	22
7.36	4.2.2 - 2018-01-06	22
7.37	4.2.0 - 2018-01-02	22
7.38	4.1.1 - 2017-11-02	23
7.39	4.1.0 - 2017-07-19	23
7.40	4.0.1 - 2017-07-12	23
7.41	4.0.0 - 2017-07-08	23
7.42	3.2.0 - 2017-07-04	24
7.43	3.1.0 - 2017-05-28	24
7.44	3.0.2 - 2017-04-13	24
7.45	3.0.1 - 2017-03-22	24
7.46	3.0.0 - 2017-03-21	25
7.47	2.0.1 - 2017-02-22	25
7.48	2.0.0 - 2017-02-15	25
7.49	1.6.0 - 2016-11-18	25
7.50	1.5.3 - 2016-06-04	25
7.51	1.5.2 - 2016-03-11	26
7.52	1.5.1 - 2015-12-20	26
7.53	1.5.0 - 2015-07-13	26
7.54	1.4.0 - 2015-06-22	26
7.55	1.3.1 - 2015-06-19	26
7.56	1.3.0 - 2015-06-19	26
7.57	1.2.0 - 2015-06-06	26
7.58	1.1.7 - 2015-03-19	27
7.59	1.1.6 - 2014-06-27	27
7.60	1.1.5 - 2013-11-10	27
7.61	1.1.4 - 2013-03-06	27
7.62	1.1.3 - 2012-12-17	27
7.63	1.1.2 - 2012-12-13	28
7.64	1.1.1 - 2012-12-05	28
7.65	1.1.0 - 2012-10-04	28
7.66	1.0.8 - 2010-04-07	28
7.67	1.0.5 - 2010-04-06	28
7.68	1.0.4 - 2010-04-06	29
7.69	1.0.0 - 2009-01-31	29
8	Glossary	31
9	tcod.console	33
10	tcod.map	41
11	tcod.bsp	43

12	tcod.path	47
13	tcod.image	49
14	tcod.random	53
15	tcod.noise	55
16	tcod.event	59
17	libtcodpy	67
17.1	bsp	67
17.2	color	68
17.3	console	71
17.4	Event	79
17.5	sys	81
17.6	pathfinding	84
17.7	heightmap	86
17.8	image	92
17.9	line	93
17.10	map	95
17.11	mouse	96
17.12	namegen	96
17.13	noise	97
17.14	parser	98
17.15	random	98
17.16	struct	101
17.17	other	101
18	tdl	105
18.1	Getting Started	105
18.2	Indexing Consoles	105
18.3	Drawing and Colors	105
18.4	tdl API	106
18.5	tdl.Console	108
18.6	tdl.Window	113
19	tdl.event	117
20	tdl.map	123
21	tdl.noise	127
22	Indices and tables	129
	Python Module Index	131

Contents:

Contents

- *Status*
- *About*
- *Usage*
- *Installation*
 - *Windows / MacOS*
 - *Linux*
- *Requirements*
- *License*

CHAPTER 1

Status

CHAPTER 2

About

This is a Python `ffi` port of `libtcod`.

This library is hosted on [GitHub](#).

Any issues you have with this module can be reported at the [GitHub issue tracker](#).

CHAPTER 3

Usage

This module was designed to be backward compatible with the original libtcodpy module distributed with libtcod. If you had code that runs on libtcodpy then you can use this library as a drop-in replacement. This installs a libtcodpy module so you'll only need to delete the libtcodpy/ folder that's usually bundled in an older libtcodpy project.

Guides and Tutorials for libtcodpy should work with the tcod module.

The latest documentation can be found [here](#).

The recommended way to install is by using pip. Older versions of pip will have issues installing tcod, so make sure it's up-to-date.

4.1 Windows / MacOS

To install using pip, use the following command:

```
> python -m pip install tcod
```

If you get the error “ImportError: DLL load failed: The specified module could not be found.” when trying to import tcod/tcl then you may need the latest [Microsoft Visual C runtime](#).

4.2 Linux

On Linux python-tcod will need to be built from source. Assuming you have Python, pip, and apt-get, then you'll run these commands to install python-tcod and its dependencies to your user environment:

```
$ sudo apt-get install gcc python-dev python3-dev libsdl2-dev libffi-dev libomp5  
$ pip2 install tcod  
$ pip3 install tcod
```


CHAPTER 5

Requirements

- Python 3.5+
- Windows, Linux, or MacOS X 10.9+.
- On Windows, requires the Visual C++ runtime 2015 or later.
- On Linux, requires libsd12 (2.0.5+) and libomp5 to run.

CHAPTER 6

License

python-tcod is distributed under the [Simplified 2-clause FreeBSD license](#).

Changes relevant for users of the the `tdl` and `tcod` packages are documented here.

This project adheres to [Semantic Versioning](#) since v2.0.0

7.1 Unreleased

7.2 9.0.0 - 2019-02-17

Changed - New console methods now default to an *fg* and *bg* of `None` instead of `white-on-black`.

7.3 8.5.0 - 2019-02-15

Added

- `tcod.console.Console` now supports *str* and *repr*.
- Added new Console methods which are independent from the console defaults.
- You can now give an array when initializing a `tcod.console.Console` instance.
- `Console.clear` can now take *ch*, *fg*, and *bg* parameters.

Changed

- Updated `libtcod` to 1.10.6
- Printing generates more compact layouts.

Deprecated

- Most `libtcodpy` console functions have been replaced by the `tcod.console` module.

- Deprecated the *set_key_color* functions. You can pass key colors to *Console.blit* instead.
- *Console.clear* should be given the colors to clear with as parameters, rather than by using *default_fg* or *default_bg*.
- Most functions which depend on console default values have been deprecated. The new deprecation warnings will give details on how to make default values explicit.

Fixed

- *tcod.console.Console.blit* was ignoring the key color set by *Console.set_key_color*.
- The *SDL2* and *OPENGL2* renders can now large numbers of tiles.

7.4 8.4.3 - 2019-02-06

Changed

- Updated libtcod to 1.10.5
- The *SDL2/OPENGL2* renderers will now auto-detect a custom fonts key-color.

7.5 8.4.2 - 2019-02-05

Deprecated

- The *tdl* module has been deprecated.
- The libtcodpy parser functions have been deprecated.

Fixed

- *tcod.image_is_pixel_transparent* and *tcod.image_get_alpha* now return values.
- *Console.print_frame* was clearing tiles outside if its bounds.
- The *FONT_LAYOUT_CP437* layout was incorrect.

7.6 8.4.1 - 2019-02-01

Fixed

- Window event types were not upper-case.
- Fixed regression where libtcodpy mouse wheel events unset mouse coordinates.

7.7 8.4.0 - 2019-01-31

Added

- Added *tcod.event* module, based off of the *sdlevent.py* shim.

Changed

- Updated libtcod to 1.10.3

Fixed

- Fixed libtcodpy *struct_add_value_list* function.
- Use correct math for tile-based delta in mouse events.
- New renderers now support tile-based mouse coordinates.
- SDL2 renderer will now properly refresh after the window is resized.

7.8 8.3.2 - 2018-12-28

Fixed

- Fixed rare access violations for some functions which took strings as parameters, such as *tcod.console_init_root*.

7.9 8.3.1 - 2018-12-28

Fixed

- libtcodpy key and mouse functions will no longer accept the wrong types.
- The *new_struct* method was not being called for libtcodpy's custom parsers.

7.10 8.3.0 - 2018-12-08

Added

- Added BSP traversal methods in *tcod.bsp* for parity with libtcodpy.

Deprecated

- Already deprecated bsp functions are now even more deprecated.

7.11 8.2.0 - 2018-11-27

Added

- New layout *tcod.FONT_LAYOUT_CP437*.

Changed

- Updated libtcod to 1.10.2
- *tcod.console_print_frame* and *Console.print_frame* now support Unicode strings.

Deprecated

- Deprecated using bytes strings for all printing functions.

Fixed

- Console objects are now initialized with spaces. This fixes some blit operations.
- Unicode code-points above U+FFFF will now work on all platforms.

7.12 8.1.1 - 2018-11-16

Fixed

- Printing a frame with an empty string no longer displays a title bar.

7.13 8.1.0 - 2018-11-15

Changed

- Heightmap functions now support 'F_CONTIGUOUS' arrays.
- *tcod.heightmap_new* now has an *order* parameter.
- Updated SDL to 2.0.9

Deprecated

- Deprecated heightmap functions which sample noise grids, this can be done using the *Noise.sample_ogrid* method.

7.14 8.0.0 - 2018-11-02

Changed

- The default renderer can now be anything if not set manually.
- Better error message for when a font file isn't found.

7.15 7.0.1 - 2018-10-27

Fixed

- Building from source was failing because *console_2tris.glsf** was missing from source distributions.

7.16 7.0.0 - 2018-10-25

Added

- New *RENDERER_SDL2* and *RENDERER_OPENGL2* renderers.

Changed

- Updated libtcod to 1.9.0
- Now requires SDL 2.0.5, which is not trivially installable on Ubuntu 16.04 LTS.

Removed

- Dropped support for Python versions before 3.5
- Dropped support for MacOS versions before 10.9 Mavericks.

7.17 6.0.7 - 2018-10-24

Fixed

- The root console no longer loses track of buffers and console defaults on a renderer change.

7.18 6.0.6 - 2018-10-01

Fixed

- Replaced missing wheels for older and 32-bit versions of MacOS.

7.19 6.0.5 - 2018-09-28

Fixed

- Resolved CDefError error during source installs.

7.20 6.0.4 - 2018-09-11

Fixed

- tcod.Key right-hand modifiers are now set independently at initialization, instead of mirroring the left-hand modifier value.

7.21 6.0.3 - 2018-09-05

Fixed

- tcod.Key and tcod.Mouse no longer ignore initiation parameters.

7.22 6.0.2 - 2018-08-28

Fixed

- Fixed color constants missing at build-time.

7.23 6.0.1 - 2018-08-24

Fixed

- Source distributions were missing C++ source files.

7.24 6.0.0 - 2018-08-23

Changed

- Project renamed to tcod on PyPI.

Deprecated

- Passing bytes strings to libtcodpy print functions is deprecated.

Fixed

- Fixed libtcodpy print functions not accepting bytes strings.
- libtcod constants are now generated at build-time fixing static analysis tools.

7.25 5.0.1 - 2018-07-08

Fixed

- tdl.event no longer crashes with StopIteration on Python 3.7

7.26 5.0.0 - 2018-07-05

Changed

- tcod.path: all classes now use *shape* instead of *width* and *height*.
- tcod.path now respects NumPy array shape, instead of assuming that arrays need to be transposed from C memory order. From now on *x* and *y* mean 1st and 2nd axis. This doesn't affect non-NumPy code.
- tcod.path now has full support of non-contiguous memory.

7.27 4.6.1 - 2018-06-30

Added

- New function *tcod.line_where* for indexing NumPy arrays using a Bresenham line.

Deprecated

- Python 2.7 support will be dropped in the near future.

7.28 4.5.2 - 2018-06-29

Added

- New wheels for Python3.7 on Windows.

Fixed

- Arrays from *tcod.heightmap_new* are now properly zeroed out.

7.29 4.5.1 - 2018-06-23

Deprecated

- Deprecated all libtcodpy map functions.

Fixed

- *tcod.map_copy* could break the *tcod.map.Map* class.
- *tcod.map_clear* *transparent* and *walkable* parameters were reversed.
- When multiple SDL2 headers were installed, the wrong ones would be used when the library is built.
- Fails to build via pip unless Numpy is installed first.

7.30 4.5.0 - 2018-06-12

Changed

- Updated libtcod to v1.7.0
- Updated SDL to v2.0.8
- Error messages when failing to create an SDL window should be a less vague.
- You no longer need to initialize libtcod before you can print to an off-screen console.

Fixed

- Avoid crashes if the root console has a character code higher than expected.

Removed

- No more debug output when loading fonts.

7.31 4.4.0 - 2018-05-02

Added

- Added the libtcodpy module as an alias for tcod. Actual use of it is deprecated, it exists primarily for backward compatibility.
- Adding missing libtcodpy functions *console_has_mouse_focus* and *console_is_active*.

Changed

- Updated libtcod to v1.6.6

7.32 4.3.2 - 2018-03-18

Deprecated

- Deprecated the use of falsy console parameters with libtcodpy functions.

Fixed

- Fixed libtcodpy image functions not supporting falsy console parameters.

- Fixed tdl `Window.get_char` method. (Kaczor2704)

7.33 4.3.1 - 2018-03-07

Fixed

- Fixed `ffi.api.FFIError` “unsupported expression: expected a simple numeric constant” error when building on platforms with an older `ffi` module and newer `SDL` headers.
- `tcod/tdl Map` and `Console` objects were not saving stride data when pickled.

7.34 4.3.0 - 2018-02-01

Added

- You can now set the `numpy` memory order on `tcod.console.Console`, `tcod.map.Map`, and `tdl.map.Map` objects well as from the `tcod.console_init_root` function.

Changed

- The `console_init_root title` parameter is now optional.

Fixed

- `OpenGL` renderer alpha blending is now consistent with all other render modes.

7.35 4.2.3 - 2018-01-06

Fixed

- Fixed `setup.py` regression that could prevent building outside of the `git` repository.

7.36 4.2.2 - 2018-01-06

Fixed

- The `Windows` dynamic linker will now prefer the bundled version of `SDL`. This fixes: “`ImportError: DLL load failed: The specified procedure could not be found.`”
- `key.c` is no longer set when `key.vk == KEY_TEXT`, this fixes a regression which was causing events to be heard twice in the `libtcod/Python` tutorial.

7.37 4.2.0 - 2018-01-02

Changed

- Updated `libtcod` backend to `v1.6.4`
- Updated `SDL` to `v2.0.7` for `Windows/MacOS`.

Removed

- Source distributions no longer include tests, examples, or fonts. Find these on [GitHub](#).

Fixed

- Fixed “final link failed: Nonrepresentable section on output” error when compiling for Linux.
- `tcod.console_init_root` defaults to the SDL renderer, other renderers cause issues with mouse movement events.

7.38 4.1.1 - 2017-11-02**Fixed**

- Fixed `ConsoleBuffer.blit` regression.
- Console defaults corrected, the root console’s blend mode and alignment is the default value for newly made Console’s.
- You can give a byte string as a filename to load parsers.

7.39 4.1.0 - 2017-07-19**Added**

- tdl Map class can now be pickled.

Changed

- Added protection to the `transparent`, `walkable`, and `fov` attributes in `tcod` and `tdl Map` classes, to prevent them from being accidentally overridden.
- `tcod` and `tdl Map` classes now use numpy arrays as their attributes.

7.40 4.0.1 - 2017-07-12**Fixed**

- tdl: Fixed `NameError` in `set_fps`.

7.41 4.0.0 - 2017-07-08**Changed**

- `tcod.bsp`: `BSP.split_recursive` parameter `random` is now `seed`.
- `tcod.console`: `Console.blit` parameters have been rearranged. Most of the parameters are now optional.
- `tcod.noise`: `Noise.__init__` parameter `rand` is now named `seed`.
- tdl: Changed `set_fps` paramter name to `fps`.

Fixed

- `tcod.bsp`: Corrected spelling of `max_vertical_ratio`.

7.42 3.2.0 - 2017-07-04

Changed

- Merged libtcod-ffi dependency with TDL.

Fixed

- Fixed boolean related crashes with Key 'text' events.
- tdl.noise: Fixed crash when given a negative seed. As well as cases where an instance could lose its seed being pickled.

7.43 3.1.0 - 2017-05-28

Added

- You can now pass tdl Console instances as parameters to libtcod-ffi functions expecting a tcod Console.

Changed

- Dependencies updated: *libtcod-ffi* >=2.5.0, <3
- The *Console.tcod_console* attribute is being renamed to *Console.console_c*.

Deprecated

- The tdl.noise and tdl.map modules will be deprecated in the future.

Fixed

- Resolved crash-on-exit issues for Windows platforms.

7.44 3.0.2 - 2017-04-13

Changed

- Dependencies updated: *libtcod-ffi* >=2.4.3, <3
- You can now create Console instances before a call to *tdl.init*.

Removed

- Dropped support for Python 3.3

Fixed

- Resolved issues with MacOS builds.
- 'OpenGL' and 'GLSL' renderers work again.

7.45 3.0.1 - 2017-03-22

Changed

- *KeyEvent*'s with *text* now have all their modifier keys set to False.

Fixed

- Undefined behaviour in text events caused crashes on 32-bit builds.

7.46 3.0.0 - 2017-03-21

Added

- *KeyEvent* supports libtcod text and meta keys.

Changed

- *KeyEvent* parameters have been moved.
- This version requires *libtcod-ffi* $\geq 2.3.0$.

Deprecated

- *KeyEvent* camel cased attribute names are deprecated.

Fixed

- Crashes with key-codes undefined by libtcod.
- *tdl.map* typedef issues with libtcod-ffi.

7.47 2.0.1 - 2017-02-22

Fixed

- *tdl.init* renderer was defaulted to OpenGL which is not supported in the current version of libtcod.

7.48 2.0.0 - 2017-02-15

Changed

- Dependencies updated, tdl now requires libtcod-ffi 2.x.x
- Some event behaviours have changed with SDL2, event keys might be different than what you expect.

Removed

- Key repeat functions were removed from SDL2. *set_key_repeat* is now stubbed, and does nothing.

7.49 1.6.0 - 2016-11-18

- Console.blit methods can now take *fg_alpha* and *bg_alpha* parameters.

7.50 1.5.3 - 2016-06-04

- *set_font* no longer crashes when loading a file without the implied font size in its name

7.51 1.5.2 - 2016-03-11

- Fixed non-square Map instances

7.52 1.5.1 - 2015-12-20

- Fixed errors with Unicode and non-Unicode literals on Python 2
- Fixed attribute error in compute_fov

7.53 1.5.0 - 2015-07-13

- python-tdl distributions are now universal builds
- New Map class
- map.bresenham now returns a list
- This release will require libtcod-ffi v0.2.3 or later

7.54 1.4.0 - 2015-06-22

- The DLL's have been moved into another library which you can find at <https://github.com/HexDecimal/libtcod-ffi> You can use this library to have some raw access to libtcod if you want. Plus it can be used alongside TDL.
- The libtcod console objects in Console instances have been made public.
- Added tdl.event.wait function. This function can called with a timeout and can automatically call tdl.flush.

7.55 1.3.1 - 2015-06-19

- Fixed pathfinding regressions.

7.56 1.3.0 - 2015-06-19

- Updated backend to use python-ffi instead of ctypes. This gives decent boost to speed in CPython and a drastic to boost in speed in PyPy.

7.57 1.2.0 - 2015-06-06

- The set_colors method now changes the default colors used by the draw_* methods. You can use Python's Ellipsis to explicitly select default colors this way.
- Functions and Methods renamed to match Python's style-guide PEP 8, the old function names still exist and are deprecated.

- The fgcolor and bgcolor parameters have been shortened to fg and bg.

7.58 1.1.7 - 2015-03-19

- Noise generator now seeds properly.
- The OS event queue will now be handled during a call to tdl.flush. This prevents a common newbie programmer hang where events are handled infrequently during long animations, simulations, or early development.
- Fixed a major bug that would cause a crash in later versions of Python 3

7.59 1.1.6 - 2014-06-27

- Fixed a race condition when importing on some platforms.
- Fixed a type issue with quickFOV on Linux.
- Added a bresenham function to the tdl.map module.

7.60 1.1.5 - 2013-11-10

- A for loop can iterate over all coordinates of a Console.
- drawStr can be configured to scroll or raise an error.
- You can now configure or disable key repeating with tdl.event.setKeyRepeat
- Typewriter class removed, use a Window instance for the same functionality.
- setColors method fixed.

7.61 1.1.4 - 2013-03-06

- Merged the Typewriter and MetaConsole classes, You now have a virtual cursor with Console and Window objects.
- Fixed the clear method on the Window class.
- Fixed screenshot function.
- Fixed some drawing operations with unchanging backgrounds.
- Instances of Console and Noise can be pickled and copied.
- Added KeyEvent.keychar
- Fixed event.keyWait, and now converts window closed events into Alt+F4.

7.62 1.1.3 - 2012-12-17

- Some of the setFont parameters were incorrectly labeled and documented.
- setFont can auto-detect tilesets if the font sizes are in the filenames.

- Added some X11 unicode tilesets, including unifont.

7.63 1.1.2 - 2012-12-13

- Window title now defaults to the running scripts filename.
- Fixed incorrect deltaTime for App.update
- App will no longer call tdl.flush on its own, you'll need to call this yourself.
- tdl.noise module added.
- clear method now defaults to black on black.

7.64 1.1.1 - 2012-12-05

- Map submodule added with AStar class and quickFOV function.
- New Typewriter class.
- Most console functions can use Python-style negative indexes now.
- New App.runOnce method.
- Rectangle geometry is less strict.

7.65 1.1.0 - 2012-10-04

- KeyEvent.keyname is now KeyEvent.key
- MouseButtonEvent.button now behaves like KeyEvent.keyname does.
- event.App class added.
- Drawing methods no longer have a default for the character parameter.
- KeyEvent.ctrl is now KeyEvent.control

7.66 1.0.8 - 2010-04-07

- No longer works in Python 2.5 but now works in 3.x and has been partly tested.
- Many bug fixes.

7.67 1.0.5 - 2010-04-06

- Got rid of setuptools dependency, this will make it much more compatible with Python 3.x
- Fixed a typo with the MacOS library import.

7.68 1.0.4 - 2010-04-06

- All constant colors (C_*) have been removed, they may be put back in later.
- Made some type assertion failures show the value they received to help in general debugging. Still working on it.
- Added MacOS and 64-bit Linux support.

7.69 1.0.0 - 2009-01-31

- First public release.

console defaults The default values implied by any Console print or put functions which don't explicitly ask for them as parameters.

libtcod-ffi This is the *ffi* implementation of libtcodpy, the original was made using *ctypes* which was more difficult to maintain.

libtcod-ffi is now part of *python-tcod*.

python-tcod *python-tcod* is a superset of the *libtcodpy* API. The major additions include class functionality in returned objects, no manual memory management, pickle-able objects, and *numpy* array attributes in most objects.

The *numpy* attributes in particular can be used to dramatically speed up the performance of your program compared to using *libtcodpy*.

python-tdl *tdl* is a high-level wrapper over *libtcodpy* although it now uses *python-tcod*, it doesn't do anything that you couldn't do yourself with just *libtcodpy* and Python.

Currently no new features are planned for *tdl*, instead new features are added to *libtcod* itself and then ported to *python-tcod*.

python-tdl and *libtcodpy* are included in installations of *python-tcod*.

libtcodpy *libtcodpy* is more or less a direct port of *libtcod*'s C API to Python. This caused a handful of issues including instances needing to be freed manually or a memory leak will occur and some functions performing badly in Python due to the need to call them frequently.

These issues are fixed in *python-tcod* which implements the full *libtcodpy* API. If *python-tcod* is installed then imports of *libtcodpy* are aliased to the *tcod* module. So if you come across a project using the original *libtcodpy* you can delete the *libtcodpy/* folder and then *python-tcod* will load instead.

libtcod works with a special ‘root’ console. You create this console using the `tcod.console_init_root` function. Usually after setting the font with `console_set_custom_font` first.

Example:

```
# Make sure 'arial10x10.png' is in the same directory as this script.
import tcod
import tcod.event

# Setup the font.
tcod.console_set_custom_font(
    "arial10x10.png",
    tcod.FONT_LAYOUT_TCOD | tcod.FONT_TYPE_GREYSCALE,
)
# Initialize the root console in a context.
with tcod.console_init_root(80, 60, order="F") as root_console:
    root_console.print_(x=0, y=0, string='Hello World!')
    while True:
        tcod.console_flush() # Show the console.
        for event in tcod.event.wait():
            if event.type == "QUIT":
                raise SystemExit()
# The libtcod window will be closed at the end of this with-block.
```

class `tcod.console.Console` (*width: int, height: int, order: str = 'C', buffer: Optional[numpy.array]*
= *None*)

A console object containing a grid of characters with foreground/background colors.

width and *height* are the size of the console (in tiles.)

order determines how the axes of NumPy array attributes are arranged. *order="F"* will swap the first two axes which allows for more intuitive $[x, y]$ indexing.

With *buffer* the console can be initialized from another array. The *buffer* should be compatible with the *width*, *height*, and *order* given; and should also have a dtype compatible with `Console.DTYPE`.

Changed in version 4.3: Added *order* parameter.

Changed in version 8.5: Added *buffer*, *copy*, and default parameters. Arrays are initialized as if the *clear* method was called.

console_c

A python-cffi “TCOD_Console*” object.

DTYPE

A class attribute which provides a dtype compatible with this class.

```
[("ch", np.intc), ("fg", "(3,)u1"), ("bg", "(3,)u1")]
```

Example:

```
>>> buffer = np.zeros(
...     shape=(20, 3),
...     dtype=tcod.console.Console.DTYPE,
...     order="F",
... )
>>> buffer["ch"] = ord(' ')
>>> buffer["ch"][:, 1] = ord('x')
>>> c = tcod.console.Console(20, 3, order="F", buffer=buffer)
>>> print(c)
<          |
|xxxxxxxxxxxxxxxxxxxx|
|          >
```

New in version 8.5.

__bool__() → bool

Returns False if this is the root console.

This mimics libtcodpy behaviour.

__enter__() → tcod.console.Console

Returns this console in a managed context.

When the root console is used as a context, the graphical window will close once the context is left as if *tcod.console_delete* was called on it.

This is useful for some Python IDE’s like IDLE, where the window would not be closed on its own otherwise.

__exit__(*args) → None

Closes the graphical window on exit.

Some tcod functions may have undefined behaviour after this point.

__repr__() → str

Return a string representation of this console.

__str__() → str

Return a simplified representation of this consoles contents.

blit (*dest*: tcod.console.Console, *dest_x*: int = 0, *dest_y*: int = 0, *src_x*: int = 0, *src_y*: int = 0, *width*: int = 0, *height*: int = 0, *fg_alpha*: float = 1.0, *bg_alpha*: float = 1.0, *key_color*: Optional[Tuple[int, int, int]] = None) → None

Blit from this console onto the *dest* console.

Parameters

- **dest** (Console) – The destintaion console to blit onto.
- **dest_x** (int) – Leftmost coordinate of the destintaion console.

- **dest_y** (*int*) – Topmost coordinate of the destintaion console.
- **src_x** (*int*) – X coordinate from this console to blit, from the left.
- **src_y** (*int*) – Y coordinate from this console to blit, from the top.
- **width** (*int*) – The width of the region to blit.
If this is 0 the maximum possible width will be used.
- **height** (*int*) – The height of the region to blit.
If this is 0 the maximum possible height will be used.
- **fg_alpha** (*float*) – Foreground color alpha vaule.
- **bg_alpha** (*float*) – Background color alpha vaule.
- **key_color** (*Optional[Tuple[int, int, int]]*) – None, or a (red, green, blue) tuple with values of 0-255.

Changed in version 4.0: Parameters were rearraged and made optional.

Previously they were: (*x, y, width, height, dest, dest_x, dest_y, **)

clear (*ch: int = 32, fg: Tuple[int, int, int] = Ellipsis, bg: Tuple[int, int, int] = Ellipsis*) → None
Reset all values in this console to a single value.

ch is the character to clear the console with. Defaults to the space character.

fg and *bg* are the colors to clear the console with. Defaults to white-on-black if the console defaults are untouched.

Note: If *fg/bg* are not set, they will default to *default_fg/default_bg*. However, default values other than white-on-back are deprecated.

Changed in version 8.5: Added the *ch*, *fg*, and *bg* parameters. Non-white-on-black default values are deprecated.

draw_frame (*x: int, y: int, width: int, height: int, title: str = "", clear: bool = True, fg: Optional[Tuple[int, int, int]] = None, bg: Optional[Tuple[int, int, int]] = None, bg_blend: int = 1*) → None
Draw a framed rectangle with an optional title.

x and *y* are the starting tile, with 0, 0 as the upper-left corner of the console. You can use negative numbers if you want to start printing relative to the bottom-right corner.

width and *height* determine the size of the frame.

title is a Unicode string.

If *clear* is True than the region inside of the frame will be cleared.

fg and *bg* are the foreground text color and background tile color respectfully. This is a 3-item tuple with (r, g, b) color values from 0 to 255. These parameters can also be set to *None* to leave the colors unchanged.

bg_blend is the blend type used by libtcod.

New in version 8.5.

Changed in version 9.0: *fg* and *bg* now default to *None* instead of white-on-black.

draw_rect (*x: int, y: int, width: int, height: int, ch: int, fg: Optional[Tuple[int, int, int]] = None, bg: Optional[Tuple[int, int, int]] = None, bg_blend: int = 1*) → None
Draw characters and colors over a rectangular region.

x and *y* are the starting tile, with 0, 0 as the upper-left corner of the console. You can use negative numbers if you want to start printing relative to the bottom-right corner.

width and *height* determine the size of the rectangle.

ch is a Unicode integer. You can use 0 to leave the current characters unchanged.

fg and *bg* are the foreground text color and background tile color respectfully. This is a 3-item tuple with (r, g, b) color values from 0 to 255. These parameters can also be set to *None* to leave the colors unchanged.

bg_blend is the blend type used by libtcod.

New in version 8.5.

Changed in version 9.0: *fg* and *bg* now default to *None* instead of white-on-black.

get_height_rect (*x*: int, *y*: int, *width*: int, *height*: int, *string*: str) → int

Return the height of this text word-wrapped into this rectangle.

Parameters

- **x** (int) – The x coordinate from the left.
- **y** (int) – The y coordinate from the top.
- **width** (int) – Maximum width to render the text.
- **height** (int) – Maximum lines to render the text.
- **string** (str) – A Unicode string.

Returns The number of lines of text once word-wrapped.

Return type int

hline (*x*: int, *y*: int, *width*: int, *bg_blend*: int = 13) → None

Draw a horizontal line on the console.

This always uses ord(‘-’), the horizontal line character.

Parameters

- **x** (int) – The x coordinate from the left.
- **y** (int) – The y coordinate from the top.
- **width** (int) – The horizontal length of this line.
- **bg_blend** (int) – The background blending flag.

Deprecated since version 8.5: Console methods which depend on console defaults have been deprecated. Use `Console.draw_rect` instead, calling this function will print a warning detailing which default values need to be made explicit.

print (*x*: int, *y*: int, *string*: str, *fg*: Optional[Tuple[int, int, int]] = None, *bg*: Optional[Tuple[int, int, int]] = None, *bg_blend*: int = 1, *alignment*: int = 0) → None

Print a string on a console with manual line breaks.

x and *y* are the starting tile, with 0, 0 as the upper-left corner of the console. You can use negative numbers if you want to start printing relative to the bottom-right corner.

string is a Unicode string which may include color control characters. Strings which are too long will be truncated until the next newline character “\n”.

fg and *bg* are the foreground text color and background tile color respectfully. This is a 3-item tuple with (r, g, b) color values from 0 to 255. These parameters can also be set to *None* to leave the colors unchanged.

bg_blend is the blend type used by libtcod.

alignment can be *tcod.LEFT*, *tcod.CENTER*, or *tcod.RIGHT*.

New in version 8.5.

Changed in version 9.0: *fg* and *bg* now default to *None* instead of white-on-black.

print_(*x*: int, *y*: int, *string*: str, *bg_blend*: int = 13, *alignment*: Optional[int] = None) → None
Print a color formatted string on a console.

Parameters

- **x** (*int*) – The x coordinate from the left.
- **y** (*int*) – The y coordinate from the top.
- **string** (*str*) – A Unicode string optionally using color codes.
- **bg_blend** (*int*) – Blending mode to use, defaults to BKGND_DEFAULT.
- **alignment** (*Optional[int]*) – Text alignment.

Deprecated since version 8.5: Console methods which depend on console defaults have been deprecated. Use `Console.print` instead, calling this function will print a warning detailing which default values need to be made explicit.

print_box(*x*: int, *y*: int, *width*: int, *height*: int, *string*: str, *fg*: Optional[Tuple[int, int, int]] = None, *bg*: Optional[Tuple[int, int, int]] = None, *bg_blend*: int = 13, *alignment*: int = 0) → int
Print a string constrained to a rectangle and return the height.

x and *y* are the starting tile, with 0, 0 as the upper-left corner of the console. You can use negative numbers if you want to start printing relative to the bottom-right corner.

width and *height* determine the bounds of the rectangle, the text will automatically be broken to fit within these bounds.

string is a Unicode string which may include color control characters.

fg and *bg* are the foreground text color and background tile color respectfully. This is a 3-item tuple with (r, g, b) color values from 0 to 255. These parameters can also be set to *None* to leave the colors unchanged.

bg_blend is the blend type used by libtcod.

alignment can be *tcod.LEFT*, *tcod.CENTER*, or *tcod.RIGHT*.

Returns the actual height of the printed area.

New in version 8.5.

Changed in version 9.0: *fg* and *bg* now default to *None* instead of white-on-black.

print_frame(*x*: int, *y*: int, *width*: int, *height*: int, *string*: str = "", *clear*: bool = True, *bg_blend*: int = 13) → None
Draw a framed rectangle with optional text.

This uses the default background color and blend mode to fill the rectangle and the default foreground to draw the outline.

string will be printed on the inside of the rectangle, word-wrapped. If *string* is empty then no title will be drawn.

Parameters

- **x** (*int*) – The x coordinate from the left.
- **y** (*int*) – The y coordinate from the top.
- **width** (*int*) – The width of the frame.

- **height** (*int*) – The height of the frame.
- **string** (*str*) – A Unicode string to print.
- **clear** (*bool*) – If True all text in the affected area will be removed.
- **bg_blend** (*int*) – The background blending flag.

Changed in version 8.2: Now supports Unicode strings.

Deprecated since version 8.5: Console methods which depend on console defaults have been deprecated. Use `Console.draw_frame` instead, calling this function will print a warning detailing which default values need to be made explicit.

print_rect (*x: int, y: int, width: int, height: int, string: str, bg_blend: int = 13, alignment: Optional[int] = None*) → *int*

Print a string constrained to a rectangle.

If *h* > 0 and the bottom of the rectangle is reached, the string is truncated. If *h* = 0, the string is only truncated if it reaches the bottom of the console.

Parameters

- **x** (*int*) – The x coordinate from the left.
- **y** (*int*) – The y coordinate from the top.
- **width** (*int*) – Maximum width to render the text.
- **height** (*int*) – Maximum lines to render the text.
- **string** (*str*) – A Unicode string.
- **bg_blend** (*int*) – Background blending flag.
- **alignment** (*Optional[int]*) – Alignment flag.

Returns The number of lines of text once word-wrapped.

Return type *int*

Deprecated since version 8.5: Console methods which depend on console defaults have been deprecated. Use `Console.print_box` instead, calling this function will print a warning detailing which default values need to be made explicit.

put_char (*x: int, y: int, ch: int, bg_blend: int = 13*) → *None*

Draw the character *c* at *x,y* using the default colors and a blend mode.

Parameters

- **x** (*int*) – The x coordinate from the left.
- **y** (*int*) – The y coordinate from the top.
- **ch** (*int*) – Character code to draw. Must be in integer form.
- **bg_blend** (*int*) – Blending mode to use, defaults to `BKGND_DEFAULT`.

rect (*x: int, y: int, width: int, height: int, clear: bool, bg_blend: int = 13*) → *None*

Draw a the background color on a rect optionally clearing the text.

If *clear* is True the affected tiles are changed to space character.

Parameters

- **x** (*int*) – The x coordinate from the left.
- **y** (*int*) – The y coordinate from the top.

- **width** (*int*) – Maximum width to render the text.
- **height** (*int*) – Maximum lines to render the text.
- **clear** (*bool*) – If True all text in the affected area will be removed.
- **bg_blend** (*int*) – Background blending flag.

Deprecated since version 8.5: Console methods which depend on console defaults have been deprecated. Use `Console.draw_rect` instead, calling this function will print a warning detailing which default values need to be made explicit.

set_key_color (*color: Optional[Tuple[int, int, int]]*) → None
Set a consoles blit transparent color.

color is the (r, g, b) color, or None to disable key color.

Deprecated since version 8.5: Pass the key color to `Console.blit` instead of calling this function.

vline (*x: int, y: int, height: int, bg_blend: int = 13*) → None
Draw a vertical line on the console.

This always uses `ord('|')`, the vertical line character.

Parameters

- **x** (*int*) – The x coordinate from the left.
- **y** (*int*) – The y coordinate from the top.
- **height** (*int*) – The horizontal length of this line.
- **bg_blend** (*int*) – The background blending flag.

Deprecated since version 8.5: Console methods which depend on console defaults have been deprecated. Use `Console.draw_rect` instead, calling this function will print a warning detailing which default values need to be made explicit.

bg

A uint8 array with the shape (height, width, 3).

You can change the consoles background colors by using this array.

Index this array with `console.bg[i, j, channel] # order='C'` or `console.bg[x, y, channel] # order='F'`.

ch

An integer array with the shape (height, width).

You can change the consoles character codes by using this array.

Index this array with `console.ch[i, j] # order='C'` or `console.ch[x, y] # order='F'`.

default_alignment

int – The default text alignment.

default_bg

Tuple[int, int, int] – The default background color.

default_bg_blend

int – The default blending mode.

default_fg

Tuple[int, int, int] – The default foreground color.

fg

A uint8 array with the shape (height, width, 3).

You can change the consoles foreground colors by using this array.

Index this array with `console.fg[i, j, channel] # order='C'` or `console.fg[x, y, channel] # order='F'`.

height

int – The height of this Console. (read-only)

width

int – The width of this Console. (read-only)

libtcod map attributes and field-of-view functions.

Example:

```
>>> import tcod.map
>>> m = tcod.map.Map(width=3, height=4)
>>> m.walkable
array([[False, False, False],
       [False, False, False],
       [False, False, False],
       [False, False, False]]...)

# Like the rest of the tcod modules, all arrays here are
# in row-major order and are addressed with [y,x]
>>> m.transparent[:] = True # Sets all to True.
>>> m.transparent[1:3,0] = False # Sets (1, 0) and (2, 0) to False.
>>> m.transparent
array([[ True,  True,  True],
       [False,  True,  True],
       [False,  True,  True],
       [ True,  True,  True]]...)

>>> m.compute_fov(0, 0)
>>> m.fov
array([[ True,  True,  True],
       [ True,  True,  True],
       [False,  True,  True],
       [False, False,  True]]...)
>>> m.fov[3,1]
False
```

class tcod.map.**Map** (*width: int, height: int, order: str = 'C'*)

A map containing libtcod attributes.

Changed in version 4.1: *transparent*, *walkable*, and *fov* are now numpy boolean arrays.

Changed in version 4.3: Added *order* parameter.

Parameters

- **width** (*int*) – Width of the new Map.
- **height** (*int*) – Height of the new Map.
- **order** (*str*) – Which numpy memory order to use.

width

int – Read only width of this Map.

height

int – Read only height of this Map.

transparent

A boolean array of transparent cells.

walkable

A boolean array of walkable cells.

fov

A boolean array of the cells lit by :any: 'compute_fov'.

compute_fov (*x: int, y: int, radius: int = 0, light_walls: bool = True, algorithm: int = 12*) → None
Compute a field-of-view on the current instance.

Parameters

- **x** (*int*) – Point of view, x-coordinate.
- **y** (*int*) – Point of view, y-coordinate.
- **radius** (*int*) – Maximum view distance from the point of view.
A value of 0 will give an infinite distance.
- **light_walls** (*bool*) – Light up walls, or only the floor.
- **algorithm** (*int*) – Defaults to `tcod.FOV_RESTRICTIVE`

The following example shows how to traverse the BSP tree using Python. This assumes *create_room* and *connect_rooms* will be replaced by custom code.

Example:

```
import tcod.bsp

bsp = tcod.bsp.BSP(x=0, y=0, width=80, height=60)
bsp.split_recursive(
    depth=5,
    min_width=3,
    min_height=3,
    max_horizontal_ratio=1.5,
    max_vertical_ratio=1.5,
)

# In pre order, leaf nodes are visited before the nodes that connect them.
for node in bsp.pre_order():
    if node.children:
        node1, node2 = node.children
        print('Connect the rooms:\n%s\n%s' % (node1, node2))
    else:
        print('Dig a room for %s.' % node)
```

class tcod.bsp.BSP (*x: int, y: int, width: int, height: int*)

A binary space partitioning tree which can be used for simple dungeon generation.

x
int – Rectangle left coordinate.

y
int – Rectangle top coordinate.

width
int – Rectangle width.

height

int – Rectangle height.

level

int – This nodes depth.

position

int – The integer of where the node was split.

horizontal

bool – This nodes split orientation.

parent

Optional[BSP] – This nodes parent or None

children

Union[Tuple[()], Tuple[BSP, BSP]] – A tuple of (left, right) BSP instances, or an empty tuple if this BSP has no children.

Parameters

- **x** (*int*) – Rectangle left coordinate.
- **y** (*int*) – Rectangle top coordinate.
- **width** (*int*) – Rectangle width.
- **height** (*int*) – Rectangle height.

`__str__` () → str

Provide a useful readout when printed.

`contains` (*x: int, y: int*) → bool

Returns True if this node contains these coordinates.

Parameters

- **x** (*int*) – X position to check.
- **y** (*int*) – Y position to check.

Returns

True if this node contains these coordinates. Otherwise False.

Return type bool

`find_node` (*x: int, y: int*) → *Optional[tcod.bsp.BSP]*

Return the deepest node which contains these coordinates.

Returns BSP object or None.

Return type *Optional[BSP]*

`in_order` () → *Iterator[tcod.bsp.BSP]*

Iterate over this BSP's hierarchy in order.

New in version 8.3.

`inverted_level_order` () → *Iterator[tcod.bsp.BSP]*

Iterate over this BSP's hierarchy in inverse level order.

New in version 8.3.

level_order () → Iterator[tcod.bsp.BSP]
Iterate over this BSP's hierarchy in level order.

New in version 8.3.

post_order () → Iterator[tcod.bsp.BSP]
Iterate over this BSP's hierarchy in post order.

New in version 8.3.

pre_order () → Iterator[tcod.bsp.BSP]
Iterate over this BSP's hierarchy in pre order.

New in version 8.3.

split_once (*horizontal: bool, position: int*) → None
Split this partition into 2 sub-partitions.

Parameters

- **horizontal** (*bool*) –
- **position** (*int*) –

split_recursive (*depth: int, min_width: int, min_height: int, max_horizontal_ratio: float, max_vertical_ratio: float, seed: Optional[tcod.random.Random] = None*) → None
Divide this partition recursively.

Parameters

- **depth** (*int*) – The maximum depth to divide this object recursively.
- **min_width** (*int*) – The minimum width of any individual partition.
- **min_height** (*int*) – The minimum height of any individual partition.
- **max_horizontal_ratio** (*float*) – Prevent creating a horizontal ratio more extreme than this.
- **max_vertical_ratio** (*float*) – Prevent creating a vertical ratio more extreme than this.
- **seed** (*Optional[tcod.random.Random]*) – The random number generator to use.

walk () → Iterator[tcod.bsp.BSP]
Iterate over this BSP's hierarchy in pre order.

Deprecated since version 2.3: Use *pre_order* instead.

Example:

```
>>> import numpy as np
>>> import tcod.path
>>> dungeon = np.array(
...     [
...         [1, 0, 1, 1, 1],
...         [1, 0, 1, 0, 1],
...         [1, 1, 1, 0, 1],
...     ],
...     dtype=np.int8,
... )
...

# Create a pathfinder from a numpy array.
# This is the recommended way to use the tcod.path module.
>>> astar = tcod.path.AStar(dungeon)
>>> print(astar.get_path(0, 0, 2, 4))
[(1, 0), (2, 1), (1, 2), (0, 3), (1, 4), (2, 4)]
>>> astar.cost[0, 1] = 1 # You can access the map array via this attribute.
>>> print(astar.get_path(0, 0, 2, 4))
[(0, 1), (0, 2), (0, 3), (1, 4), (2, 4)]

# Create a pathfinder from an edge_cost function.
# Calling Python functions from C is known to be very slow.
>>> def edge_cost(my_x, my_y, dest_x, dest_y):
...     return dungeon[dest_x, dest_y]
...
>>> dijkstra = tcod.path.Dijkstra(
...     tcod.path.EdgeCostCallback(edge_cost, dungeon.shape),
... )
...
>>> dijkstra.set_goal(0, 0)
>>> print(dijkstra.get_path(2, 4))
[(0, 1), (0, 2), (0, 3), (1, 4), (2, 4)]
```

Changed in version 5.0: All path-finding functions now respect the NumPy array shape (if a NumPy array is used.)

class `tcod.path.AStar` (*cost: Any, diagonal: float = 1.41*)

Parameters

- **cost** (*Union[tcod.map.Map, numpy.ndarray, Any]*) –
- **diagonal** (*float*) – Multiplier for diagonal movement. A value of 0 will disable diagonal movement entirely.

get_path (*start_x: int, start_y: int, goal_x: int, goal_y: int*) → List[Tuple[int, int]]

Return a list of (x, y) steps to reach the goal point, if possible.

Parameters

- **start_x** (*int*) – Starting X position.
- **start_y** (*int*) – Starting Y position.
- **goal_x** (*int*) – Destination X position.
- **goal_y** (*int*) – Destination Y position.

Returns A list of points, or an empty list if there is no valid path.

Return type List[Tuple[int, int]]

class `tcod.path.Dijkstra` (*cost: Any, diagonal: float = 1.41*)

Parameters

- **cost** (*Union[tcod.map.Map, numpy.ndarray, Any]*) –
- **diagonal** (*float*) – Multiplier for diagonal movement. A value of 0 will disable diagonal movement entirely.

get_path (*x: int, y: int*) → List[Tuple[int, int]]

Return a list of (x, y) steps to reach the goal point, if possible.

set_goal (*x: int, y: int*) → None

Set the goal point and recompute the Dijkstra path-finder.

class `tcod.path.EdgeCostCallback` (*callback: Callable[[int, int, int, int], float], shape: Tuple[int, int]*)

Calculate cost from an edge-cost callback.

callback is the custom userdata to send to the C call.

shape is a 2-item tuple representing the maximum boundary for the algorithm. The callback will not be called with parameters outside of these bounds.

Changed in version 5.0: Now only accepts a *shape* argument instead of *width* and *height*.

class `tcod.path.NodeCostArray`

Calculate cost from a numpy array of nodes.

array is a NumPy array holding the path-cost of each node. A cost of 0 means the node is blocking.

static `__new__` (*cls, array: numpy.array*) → `tcod.path.NodeCostArray`

Validate a numpy array and setup a C callback.

class `tcod.image.Image` (*width: int, height: int*)

Parameters

- **width** (*int*) – Width of the new Image.
- **height** (*int*) – Height of the new Image.

width

int – Read only width of this Image.

height

int – Read only height of this Image.

blit (*console: tcod.console.Console, x: float, y: float, bg_blend: int, scale_x: float, scale_y: float, angle: float*) → None

Blit onto a Console using scaling and rotation.

Parameters

- **console** (*Console*) – Blit destination Console.
- **x** (*float*) – Console X position for the center of the Image blit.
- **y** (*float*) – Console Y position for the center of the Image blit. The Image blit is centered on this position.
- **bg_blend** (*int*) – Background blending mode to use.
- **scale_x** (*float*) – Scaling along Image x axis. Set to 1 for no scaling. Must be over 0.
- **scale_y** (*float*) – Scaling along Image y axis. Set to 1 for no scaling. Must be over 0.
- **angle** (*float*) – Rotation angle in radians. (Clockwise?)

blit_2x (*console: tcod.console.Console, dest_x: int, dest_y: int, img_x: int = 0, img_y: int = 0, img_width: int = -1, img_height: int = -1*) → None

Blit onto a Console with double resolution.

Parameters

- **console** (*Console*) – Blit destination Console.
- **dest_x** (*int*) – Console tile X position starting from the left at 0.
- **dest_y** (*int*) – Console tile Y position starting from the top at 0.
- **img_x** (*int*) – Left corner pixel of the Image to blit
- **img_y** (*int*) – Top corner pixel of the Image to blit
- **img_width** (*int*) – Width of the Image to blit. Use -1 for the full Image width.
- **img_height** (*int*) – Height of the Image to blit. Use -1 for the full Image height.

blit_rect (*console: tcod.console.Console, x: int, y: int, width: int, height: int, bg_blend: int*) → *None*
Blit onto a Console without scaling or rotation.

Parameters

- **console** (*Console*) – Blit destination Console.
- **x** (*int*) – Console tile X position starting from the left at 0.
- **y** (*int*) – Console tile Y position starting from the top at 0.
- **width** (*int*) – Use -1 for Image width.
- **height** (*int*) – Use -1 for Image height.
- **bg_blend** (*int*) – Background blending mode to use.

clear (*color: Tuple[int, int, int]*) → *None*
Fill this entire Image with color.

Parameters **color** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

get_alpha (*x: int, y: int*) → *int*
Get the Image alpha of the pixel at x, y.

Parameters

- **x** (*int*) – X pixel of the image. Starting from the left at 0.
- **y** (*int*) – Y pixel of the image. Starting from the top at 0.

Returns The alpha value of the pixel. With 0 being fully transparent and 255 being fully opaque.

Return type *int*

get_mipmap_pixel (*left: float, top: float, right: float, bottom: float*) → *Tuple[int, int, int]*
Get the average color of a rectangle in this Image.

Parameters should stay within the following limits: * 0 <= left < right < Image.width * 0 <= top < bottom < Image.height

Parameters

- **left** (*float*) – Left corner of the region.
- **top** (*float*) – Top corner of the region.
- **right** (*float*) – Right corner of the region.
- **bottom** (*float*) – Bottom corner of the region.

Returns An (r, g, b) tuple containing the averaged color value. Values are in a 0 to 255 range.

Return type *Tuple[int, int, int]*

get_pixel (*x: int, y: int*) → Tuple[int, int, int]

Get the color of a pixel in this Image.

Parameters

- **x** (*int*) – X pixel of the Image. Starting from the left at 0.
- **y** (*int*) – Y pixel of the Image. Starting from the top at 0.

Returns An (r, g, b) tuple containing the pixels color value. Values are in a 0 to 255 range.

Return type Tuple[int, int, int]

hflip () → None

Horizontally flip this Image.

invert () → None

Invert all colors in this Image.

put_pixel (*x: int, y: int, color: Tuple[int, int, int]*) → None

Change a pixel on this Image.

Parameters

- **x** (*int*) – X pixel of the Image. Starting from the left at 0.
- **y** (*int*) – Y pixel of the Image. Starting from the top at 0.
- **color** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

refresh_console (*console: tcod.console.Console*) → None

Update an Image created with `tcod.image_from_console`.

The console used with this function should have the same width and height as the Console given to `tcod.image_from_console`. The font width and height must also be the same as when `tcod.image_from_console` was called.

Parameters console (*Console*) – A Console with a pixel width and height matching this Image.

rotate90 (*rotations: int = 1*) → None

Rotate this Image clockwise in 90 degree steps.

Parameters rotations (*int*) – Number of 90 degree clockwise rotations.

save_as (*filename: str*) → None

Save the Image to a 32-bit .bmp or .png file.

Parameters filename (*Text*) – File path to same this Image.

scale (*width: int, height: int*) → None

Scale this Image to the new width and height.

Parameters

- **width** (*int*) – The new width of the Image after scaling.
- **height** (*int*) – The new height of the Image after scaling.

set_key_color (*color: Tuple[int, int, int]*) → None

Set a color to be transparent during blitting functions.

Parameters color (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

vflip () → None
Vertically flip this Image.

Random module docs.

class `tcod.random.Random` (*algorithm: int, seed: Optional[Hashable] = None*)

The libtcod random number generator.

If all you need is a random number generator then it's recommended that you use the `random` module from the Python standard library.

If `seed` is `None` then a random seed will be generated.

Parameters

- **algorithm** (*int*) – The algorithm to use.
- **seed** (*Optional[Hashable]*) – Could be a 32-bit integer, but any hashable object is accepted.

`random_c`

CData – A cffi pointer to a `TCOD_random_t` object.

`__getstate__` () → Any

Pack the `self.random_c` attribute into a portable state.

`__setstate__` (*state: Any*) → None

Create a new `cdata` object with the stored parameters.

guass (*mu: float, sigma: float*) → float

Return a random number using Gaussian distribution.

Parameters

- **mu** (*float*) – The median returned value.
- **sigma** (*float*) – The standard deviation.

Returns A random float.

Return type float

inverse_guass (*mu: float, sigma: float*) → float

Return a random Gaussian number using the Box-Muller transform.

Parameters

- **mu** (*float*) – The median returned value.
- **sigma** (*float*) – The standard deviation.

Returns A random float.

Return type float

randint (*low: int, high: int*) → int

Return a random integer within the linear range: low <= n <= high.

Parameters

- **low** (*int*) – The lower bound of the random range.
- **high** (*int*) – The upper bound of the random range.

Returns A random integer.

Return type int

uniform (*low: float, high: float*) → float

Return a random floating number in the range: low <= n <= high.

Parameters

- **low** (*float*) – The lower bound of the random range.
- **high** (*float*) – The upper bound of the random range.

Returns A random float.

Return type float

The *Noise.sample_mgrid* and *Noise.sample_ogrid* methods are multi-threaded operations when the Python runtime supports OpenMP. Even when single threaded these methods will perform much better than multiple calls to *Noise.get_point*.

Example:

```
import numpy as np
import tcod
import tcod.noise

noise = tcod.noise.Noise(
    dimensions=2,
    algorithm=tcod.NOISE_SIMPLEX,
    implementation=tcod.noise.TURBULENCE,
    hurst=0.5,
    lacunarity=2.0,
    octaves=4,
    seed=None,
)

# Create a 5x5 open multi-dimensional mesh-grid.
ogrid = [np.arange(5, dtype=np.float32),
         np.arange(5, dtype=np.float32)]
print(ogrid)

# Scale the grid.
ogrid[0] *= 0.25
ogrid[1] *= 0.25

# Return the sampled noise from this grid of points.
samples = noise.sample_ogrid(ogrid)
print(samples)
```

```
class tcod.noise.Noise(dimensions: int, algorithm: int = 2, implementation: int = 0, hurst:  
float = 0.5, lacunarity: float = 2.0, octaves: float = 4, seed: Op-  
tional[tcod.random.Random] = None)
```

The `hurst` exponent describes the raggedness of the resultant noise, with a higher value leading to a smoother noise. Not used with `tcod.noise.SIMPLE`.

`lacunarity` is a multiplier that determines how fast the noise frequency increases for each successive octave. Not used with `tcod.noise.SIMPLE`.

Parameters

- **dimensions** (*int*) – Must be from 1 to 4.
- **algorithm** (*int*) – Defaults to `NOISE_SIMPLEX`
- **implementation** (*int*) – Defaults to `tcod.noise.SIMPLE`
- **hurst** (*float*) – The hurst exponent. Should be in the 0.0-1.0 range.
- **lacunarity** (*float*) – The noise lacunarity.
- **octaves** (*float*) – The level of detail on fBm and turbulence implementations.
- **seed** (*Optional[Random]*) – A `Random` instance, or `None`.

`noise_c`

CData – A cffi pointer to a `TCOD_noise_t` object.

get_point (*x: float = 0, y: float = 0, z: float = 0, w: float = 0*) → *float*

Return the noise value at the (x, y, z, w) point.

Parameters

- **x** (*float*) – The position on the 1st axis.
- **y** (*float*) – The position on the 2nd axis.
- **z** (*float*) – The position on the 3rd axis.
- **w** (*float*) – The position on the 4th axis.

sample_mgrid (*mgrid: numpy.array*) → *numpy.array*

Sample a mesh-grid array and return the result.

The `sample_ogrid` method performs better as there is a lot of overhead when working with large mesh-grids.

Parameters **mgrid** (*numpy.ndarray*) – A mesh-grid array of points to sample. A contiguous array of type `numpy.float32` is preferred.

Returns

An array of sampled points.

This array has the shape: `mgrid.shape[:-1]`. The `dtype` is `numpy.float32`.

Return type `numpy.ndarray`

sample_ogrid (*ogrid: numpy.array*) → *numpy.array*

Sample an open mesh-grid array and return the result.

Args **ogrid** (`Sequence[Sequence[float]]`): An open mesh-grid.

Returns

An array of sampled points.

The `shape` is based on the lengths of the open mesh-grid arrays. The `dtype` is `numpy.float32`.

Return type `numpy.ndarray`

An alternative, more direct implementation of event handling based on using cffi calls to SDL functions. The current code is partially incomplete.

Printing any event will tell you its attributes in a human readable format. An events type attribute if omitted is just the classes name with all letters upper-case. Do not use `isinstance` to tell events apart as that method won't be forward compatible.

As a general guideline, you should use `KeyboardEvent.sym` for command inputs, and `TextInput.text` for name entry fields.

Remember to add the line `import tcod.event`, as importing this module is not implied by `import tcod`.

New in version 8.4.

```
class tcod.event.Point(x, y)
```

```
    x
        Alias for field number 0
```

```
    y
        Alias for field number 1
```

```
class tcod.event.Event(type: Optional[str] = None)
```

The base event class.

```
type
    str – This events type.
```

```
sdl_event
    When available, this holds a python-cffi 'SDL_Event*' pointer. All sub-classes have this attribute.
```

```
classmethod from_sdl_event(sdl_event: Any) → Any
    Return a class instance from a python-cffi 'SDL_Event*' pointer.
```

```
class tcod.event.Quit(type: Optional[str] = None)
```

An application quit request event.

For more info on when this event is triggered see: https://wiki.libsdl.org/SDL_EventType#SDL_QUIT

type

str – Always “QUIT”.

classmethod from_sdl_event (*sdl_event: Any*) → `tcod.event.Quit`

Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.KeyboardEvent` (*scancode: int, sym: int, mod: int, repeat: bool = False*)

type

str – Will be “KEYDOWN” or “KEYUP”, depending on the event.

scancode

int – The keyboard scan-code, this is the physical location of the key on the keyboard rather than the keys symbol.

sym

int – The keyboard symbol.

mod

int – A bitmask of modifier keys.

repeat

bool – True if this event exists because of key repeat.

classmethod from_sdl_event (*sdl_event: Any*) → `Any`

Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.KeyDown` (*scancode: int, sym: int, mod: int, repeat: bool = False*)

class `tcod.event.KeyUp` (*scancode: int, sym: int, mod: int, repeat: bool = False*)

class `tcod.event.MouseMotion` (*pixel: Tuple[int, int] = (0, 0), pixel_motion: Tuple[int, int] = (0, 0), tile: Tuple[int, int] = (0, 0), tile_motion: Tuple[int, int] = (0, 0), state: int = 0*)

type

str – Always “MOUSEMOTION”.

pixel

Point – The pixel coordinates of the mouse.

pixel_motion

Point – The pixel delta.

tile

Point – The integer tile coordinates of the mouse on the screen.

tile_motion

Point – The integer tile delta.

state

int – A bitmask of which mouse buttons are currently held.

Will be a combination of the following names:

- `tcod.event.BUTTON_LMASK`
- `tcod.event.BUTTON_MMASK`
- `tcod.event.BUTTON_RMASK`
- `tcod.event.BUTTON_X1MASK`
- `tcod.event.BUTTON_X2MASK`

classmethod from_sdl_event (*sdl_event: Any*) → `tcod.event.MouseMotion`

Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.MouseButtonEvent` (*pixel: Tuple[int, int] = (0, 0)*, *tile: Tuple[int, int] = (0, 0)*,
button: int = 0)

type

str – Will be “MOUSEBUTTONDOWN” or “MOUSEBUTTONUP”, depending on the event.

pixel

Point – The pixel coordinates of the mouse.

tile

Point – The integer tile coordinates of the mouse on the screen.

button

int – Which mouse button.

This will be one of the following names:

- `tcod.event.BUTTON_LEFT`
- `tcod.event.BUTTON_MIDDLE`
- `tcod.event.BUTTON_RIGHT`
- `tcod.event.BUTTON_X1`
- `tcod.event.BUTTON_X2`

classmethod from_sdl_event (*sdl_event: Any*) → `Any`

Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.MouseButtonDown` (*pixel: Tuple[int, int] = (0, 0)*, *tile: Tuple[int, int] = (0, 0)*,
button: int = 0)

class `tcod.event.MouseButtonUp` (*pixel: Tuple[int, int] = (0, 0)*, *tile: Tuple[int, int] = (0, 0)*, *button:*
int = 0)

class `tcod.event.MouseWheel` (*x: int*, *y: int*, *flipped: bool = False*)

type

str – Always “MOUSEWHEEL”.

x

int – Horizontal scrolling. A positive value means scrolling right.

y

int – Vertical scrolling. A positive value means scrolling away from the user.

flipped

bool – If True then the values of *x* and *y* are the opposite of their usual values.

classmethod from_sdl_event (*sdl_event: Any*) → `tcod.event.MouseWheel`

Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.TextInput` (*text: str*)

type

str – Always “TEXTINPUT”.

text

str – A Unicode string with the input.

classmethod from_sdl_event (*sdl_event: Any*) → `tcod.event.TextInput`
Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.WindowEvent` (*type: Optional[str] = None*)

type
str – A window event could mean various event types.

classmethod from_sdl_event (*sdl_event: Any*) → `Any`
Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.WindowMoved` (*x: int, y: int*)

type
str – Always “WINDOWMOVED”.

x
int – Movement on the x-axis.

y
int – Movement on the y-axis.

class `tcod.event.WindowResized` (*type: str, width: int, height: int*)

type
str – “WINDOWRESIZED” or “WINDOWSIZEDCHANGED”

width
int – The current width of the window.

height
int – The current height of the window.

class `tcod.event.Undefined`
This class is a place holder for SDL events without their own `tcod.event` class.

classmethod from_sdl_event (*sdl_event: Any*) → `tcod.event.Undefined`
Return a class instance from a python-cffi ‘SDL_Event*’ pointer.

class `tcod.event.EventDispatch`
This class dispatches events to methods depending on the events type attribute.

To use this class, make a sub-class and override the relevant `ev_*` methods. Then send events to the dispatch method.

Example:

```
import tcod
import tcod.event

class State(tcod.event.EventDispatch):
    def ev_quit(self, event):
        raise SystemExit()

    def ev_keydown(self, event):
        print(event)

    def ev_mousebuttondown(self, event):
        print(event)
```

(continues on next page)

(continued from previous page)

```

def ev_mousemotion(self, event):
    print(event)

root_console = tcod.console_init_root(80, 60)
state = State()
while True:
    for event in tcod.event.wait():
        state.dispatch(event)

```

dispatch (*event: Any*) → None

Send an event to an *ev_** method.

* will be the events type converted to lower-case.

If *event.type* is an empty string or None then it will be ignored.

ev_keydown (*event: tcod.event.KeyDown*) → None

Called when a keyboard key is pressed or repeated.

ev_keyup (*event: tcod.event.KeyUp*) → None

Called when a keyboard key is released.

ev_mousebuttondown (*event: tcod.event.MouseButtonDown*) → None

Called when a mouse button is pressed.

ev_mousebuttonup (*event: tcod.event.MouseButtonUp*) → None

Called when a mouse button is released.

ev_mousemotion (*event: tcod.event.MouseMotion*) → None

Called when the mouse is moved.

ev_mousewheel (*event: tcod.event.MouseWheel*) → None

Called when the mouse wheel is scrolled.

ev_quit (*event: tcod.event.Quit*) → None

Called when the termination of the program is requested.

ev_textinput (*event: tcod.event.TextInput*) → None

Called to handle Unicode input.

ev_windowclose (*event: tcod.event.WindowEvent*) → None

Called when the window manager requests the window to be closed.

ev_windowenter (*event: tcod.event.WindowEvent*) → None

Called when the window gains mouse focus.

ev_windowexposed (*event: tcod.event.WindowEvent*) → None

Called when a window is exposed, and needs to be refreshed.

This usually means a call to *tcod.console_flush* is necessary.

ev_windowfocusgained (*event: tcod.event.WindowEvent*) → None

Called when the window gains keyboard focus.

ev_windowfocuslost (*event: tcod.event.WindowEvent*) → None

Called when the window loses keyboard focus.

ev_windowhidden (*event: tcod.event.WindowEvent*) → None

Called when the window is hidden.

ev_windowleave (*event: tcod.event.WindowEvent*) → None
Called when the window loses mouse focus.

ev_windowmaximized (*event: tcod.event.WindowEvent*) → None
Called when the window is maximized.

ev_windowminimized (*event: tcod.event.WindowEvent*) → None
Called when the window is minimized.

ev_windowmoved (*event: tcod.event.WindowMoved*) → None
Called when the window is moved.

ev_windowresized (*event: tcod.event.WindowResized*) → None
Called when the window is resized.

ev_windowrestored (*event: tcod.event.WindowEvent*) → None
Called when the window is restored.

ev_windowsshown (*event: tcod.event.WindowEvent*) → None
Called when the window is shown.

ev_windowsizechanged (*event: tcod.event.WindowResized*) → None
Called when the system or user changes the size of the window.

`tcod.event.get()` → `Iterator[Any]`
Return an iterator for all pending events.

Events are processed as the iterator is consumed. Breaking out of, or discarding the iterator will leave the remaining events on the event queue.

Example:

```
for event in tcod.event.get():
    if event.type == "QUIT":
        print(event)
        raise SystemExit()
    elif event.type == "KEYDOWN":
        print(event)
    elif event.type == "MOUSEBUTTONDOWN":
        print(event)
    elif event.type == "MOUSEMOTION":
        print(event)
    else:
        print(event)
```

`tcod.event.wait(timeout: Optional[float] = None)` → `Iterator[Any]`
Block until events exist, then return an event iterator.

timeout is the maximum number of seconds to wait as a floating point number with millisecond precision, or it can be None to wait forever.

Returns the same iterator as a call to `tcod.event.get`.

Example:

```
for event in tcod.event.wait():
    if event.type == "QUIT":
        print(event)
        raise SystemExit()
    elif event.type == "KEYDOWN":
        print(event)
    elif event.type == "MOUSEBUTTONDOWN":
```

(continues on next page)

(continued from previous page)

```
print(event)
elif event.type == "MOUSEMOTION":
    print(event)
else:
    print(event)
```


17.1 bsp

`tcod.bsp_new_with_size` (*x*: *int*, *y*: *int*, *w*: *int*, *h*: *int*) → `tcod.bsp.BSP`
Create a new BSP instance with the given rectangle.

Parameters

- **x** (*int*) – Rectangle left coordinate.
- **y** (*int*) – Rectangle top coordinate.
- **w** (*int*) – Rectangle width.
- **h** (*int*) – Rectangle height.

Returns A new BSP instance.

Return type *BSP*

Deprecated since version 2.0: Call the *BSP* class instead.

`tcod.bsp_split_once` (*node*: `tcod.bsp.BSP`, *horizontal*: *bool*, *position*: *int*) → `None`
Deprecated since version 2.0: Use *BSP.split_once* instead.

`tcod.bsp_split_recursive` (*node*: `tcod.bsp.BSP`, *randomizer*: *Optional*[`tcod.random.Random`], *nb*:
int, *minHSize*: *int*, *minVSize*: *int*, *maxHRatio*: *int*, *maxVRatio*: *int*) →
`None`
Deprecated since version 2.0: Use *BSP.split_recursive* instead.

`tcod.bsp_resize` (*node*: `tcod.bsp.BSP`, *x*: *int*, *y*: *int*, *w*: *int*, *h*: *int*) → `None`
Deprecated since version 2.0: Assign directly to *BSP* attributes instead.

`tcod.bsp_left` (*node*: `tcod.bsp.BSP`) → *Optional*[`tcod.bsp.BSP`]
Deprecated since version 2.0: Use *BSP.children* instead.

`tcod.bsp_right` (*node*: `tcod.bsp.BSP`) → *Optional*[`tcod.bsp.BSP`]
Deprecated since version 2.0: Use *BSP.children* instead.

`tcod.bsp_father` (*node: tcod.bsp.BSP*) → Optional[tcod.bsp.BSP]
 Deprecated since version 2.0: Use `BSP.parent` instead.

`tcod.bsp_is_leaf` (*node: tcod.bsp.BSP*) → bool
 Deprecated since version 2.0: Use `BSP.children` instead.

`tcod.bsp_contains` (*node: tcod.bsp.BSP, cx: int, cy: int*) → bool
 Deprecated since version 2.0: Use `BSP.contains` instead.

`tcod.bsp_find_node` (*node: tcod.bsp.BSP, cx: int, cy: int*) → Optional[tcod.bsp.BSP]
 Deprecated since version 2.0: Use `BSP.find_node` instead.

`tcod.bsp_traverse_pre_order` (*node: tcod.bsp.BSP, callback: Callable[[tcod.bsp.BSP, Any], None],
 userData: Any = 0*) → None
 Traverse this nodes hierarchy with a callback.
 Deprecated since version 2.0: Use `BSP.pre_order` instead.

`tcod.bsp_traverse_in_order` (*node: tcod.bsp.BSP, callback: Callable[[tcod.bsp.BSP, Any], None],
 userData: Any = 0*) → None
 Traverse this nodes hierarchy with a callback.
 Deprecated since version 2.0: Use `BSP.in_order` instead.

`tcod.bsp_traverse_post_order` (*node: tcod.bsp.BSP, callback: Callable[[tcod.bsp.BSP, Any],
 None], userData: Any = 0*) → None
 Traverse this nodes hierarchy with a callback.
 Deprecated since version 2.0: Use `BSP.post_order` instead.

`tcod.bsp_traverse_level_order` (*node: tcod.bsp.BSP, callback: Callable[[tcod.bsp.BSP, Any],
 None], userData: Any = 0*) → None
 Traverse this nodes hierarchy with a callback.
 Deprecated since version 2.0: Use `BSP.level_order` instead.

`tcod.bsp_traverse_inverted_level_order` (*node: tcod.bsp.BSP, callback: Callable[[tcod.bsp.BSP, Any],
 None], userData: Any = 0*) → None
 Traverse this nodes hierarchy with a callback.
 Deprecated since version 2.0: Use `BSP.inverted_level_order` instead.

`tcod.bsp_remove_sons` (*node: tcod.bsp.BSP*) → None
 Delete all children of a given node. Not recommended.

Note: This function will add unnecessary complexity to your code. Don't use it.

Deprecated since version 2.0: BSP deletion is automatic.

`tcod.bsp_delete` (*node: tcod.bsp.BSP*) → None
 Exists for backward compatibility. Does nothing.

BSP's created by this library are automatically garbage collected once there are no references to the tree. This function exists for backwards compatibility.

Deprecated since version 2.0: BSP deletion is automatic.

17.2 color

class `tcod.Color` (*r: int = 0, g: int = 0, b: int = 0*)

Parameters

- **r** (*int*) – Red value, from 0 to 255.
- **g** (*int*) – Green value, from 0 to 255.
- **b** (*int*) – Blue value, from 0 to 255.

r*int* – Red value, always normalised to 0-255.**g***int* – Green value, always normalised to 0-255.**b***int* – Blue value, always normalised to 0-255.**__eq__** (*other: Any*) → bool

Compare equality between colors.

Also compares with standard sequences such as 3-item tuples or lists.

__add__ (*other: Any*) → `tcod.color.Color`

Add two colors together.

__sub__ (*other: Any*) → `tcod.color.Color`

Subtract one color from another.

__mul__ (*other: Any*) → `tcod.color.Color`

Multiply with a scaler or another color.

__repr__ () → str

Return a printable representation of the current color.

`tcod.color.lerp` (*c1: Tuple[int, int, int], c2: Tuple[int, int, int], a: float*) → `tcod.color.Color`

Return the linear interpolation between two colors.

a is the interpolation value, with 0 returning *c1*, 1 returning *c2*, and 0.5 returning a color halfway between both.**Parameters**

- **c1** (*Union[Tuple[int, int, int], Sequence[int]]*) – The first color. At *a=0*.
- **c2** (*Union[Tuple[int, int, int], Sequence[int]]*) – The second color. At *a=1*.
- **a** (*float*) – The interpolation value,

Returns The interpolated Color.**Return type** *Color*`tcod.color.set_hsv` (*c: tcod.color.Color, h: float, s: float, v: float*) → None

Set a color using: hue, saturation, and value parameters.

Does not return a new Color. *c* is modified inplace.**Parameters**

- **c** (*Union[Color, List[Any]]*) – A Color instance, or a list of any kind.
- **h** (*float*) – Hue, from 0 to 360.
- **s** (*float*) – Saturation, from 0 to 1.
- **v** (*float*) – Value, from 0 to 1.

`tcod.color_get_hsv(c: Tuple[int, int, int]) → Tuple[float, float, float]`

Return the (hue, saturation, value) of a color.

Parameters `c` (`Union[Tuple[int, int, int], Sequence[int]]`) – An (r, g, b) sequence or `Color` instance.

Returns A tuple with (hue, saturation, value) values, from 0 to 1.

Return type `Tuple[float, float, float]`

`tcod.color_scale_HSV(c: tcod.color.Color, scoef: float, vcoef: float) → None`

Scale a color's saturation and value.

Does not return a new `Color`. `c` is modified inplace.

Parameters

- `c` (`Union[Color, List[int]]`) – A `Color` instance, or an [r, g, b] list.
- `scoef` (`float`) – Saturation multiplier, from 0 to 1. Use 1 to keep current saturation.
- `vcoef` (`float`) – Value multiplier, from 0 to 1. Use 1 to keep current value.

`tcod.color_gen_map(colors: Iterable[Tuple[int, int, int]], indexes: Iterable[int]) → List[tcod.color.Color]`

Return a smoothly defined scale of colors.

If `indexes` is [0, 3, 9] for example, the first color from `colors` will be returned at 0, the 2nd will be at 3, and the 3rd will be at 9. All in-betweens will be filled with a gradient.

Parameters

- `colors` (`Iterable[Union[Tuple[int, int, int], Sequence[int]]]`) – Array of colors to be sampled.
- `indexes` (`Iterable[int]`) – A list of indexes.

Returns A list of `Color` instances.

Return type `List[Color]`

Example

```
>>> tcod.color_gen_map([(0, 0, 0), (255, 128, 0)], [0, 5])
[Color(0, 0, 0), Color(51, 25, 0), Color(102, 51, 0), Color(153, 76, 0),
 ↪Color(204, 102, 0), Color(255, 128, 0)]
```

17.2.1 color controls

Configurable color control constants which can be set up with `tcod.console_set_color_control`.

`tcod.COLCTRL_1`

`tcod.COLCTRL_2`

`tcod.COLCTRL_3`

`tcod.COLCTRL_4`

`tcod.COLCTRL_5`

`tcod.COLCTRL_STOP`

`tcod.COLCTRL_FORE_RGB`

`tcod.COLCTRL_BACK_RGB`

17.3 console

`tcod.console_set_custom_font` (*fontFile*: AnyStr, *flags*: int = 1, *nb_char_horiz*: int = 0, *nb_char_vertic*: int = 0) → None

Load the custom font file at *fontFile*.

Call this before function before calling `tcod.console_init_root`.

Flags can be a mix of the following:

- `tcod.FONT_LAYOUT_ASCII_INCOL`: Decode tileset raw in column-major order.
- `tcod.FONT_LAYOUT_ASCII_INROW`: Decode tileset raw in row-major order.
- `tcod.FONT_TYPE_GREYSCALE`: Force tileset to be read as greyscale.
- `tcod.FONT_TYPE_GRAYSCALE`
- `tcod.FONT_LAYOUT_TCOD`: Unique layout used by libtcod.
- `tcod.FONT_LAYOUT_CP437`: Decode a row-major Code Page 437 tileset into Unicode.

nb_char_horiz and *nb_char_vertic* are the columns and rows of the font file respectfully.

`tcod.console_init_root` (*w*: int, *h*: int, *title*: Optional[str] = None, *fullscreen*: bool = False, *renderer*: Optional[int] = None, *order*: str = 'C') → `tcod.console.Console`

Set up the primary display and return the root console.

w and *h* are the columns and rows of the new window (in tiles.)

title is an optional string to display on the windows title bar.

fullscreen determines if the window will start in fullscreen. Fullscreen mode is unreliable unless the renderer is set to `RENDERER_SDL2` or `RENDERER_OPENGL2`.

renderer is the rendering back-end that libtcod will use. Options are:

- `tcod.RENDERER_SDL`
- `tcod.RENDERER_OPENGL`
- `tcod.RENDERER_GLSL`
- `tcod.RENDERER_SDL2`
- `tcod.RENDERER_OPENGL2`

order will affect how the array attributes of the returned root console are indexed. *order*='C' is the default, but *order*='F' is recommended.

Changed in version 4.3: Added *order* parameter. *title* parameter is now optional.

Changed in version 8.0: The default *renderer* is now automatic instead of always being `RENDERER_SDL`.

`tcod.console_flush` () → None

Update the display to represent the root consoles current state.

`tcod.console_blit` (*src*: `tcod.console.Console`, *x*: int, *y*: int, *w*: int, *h*: int, *dst*: `tcod.console.Console`, *xdst*: int, *ydst*: int, *ffade*: float = 1.0, *bfade*: float = 1.0) → None

Blit the console src from x,y,w,h to console dst at xdst,ydst.

Deprecated since version 8.5: Call the `Console.blit` method instead.

`tcod.console_check_for_keypress` (*flags: int = 2*) → `tcod.libtcodpy.Key`

`tcod.console_clear` (*con: tcod.console.Console*) → `None`
Reset a console to its default colors and the space character.

Parameters `con` (`Console`) – Any Console instance.

See also:

`console_set_default_background` `console_set_default_foreground`

Deprecated since version 8.5: Call the `Console.clear` method instead.

`tcod.console_credits` () → `None`

`tcod.console_credits_render` (*x: int, y: int, alpha: bool*) → `bool`

`tcod.console_credits_reset` () → `None`

`tcod.console_delete` (*con: tcod.console.Console*) → `None`
Closes the window if `con` is the root console.

libtcod objects are automatically garbage collected once they go out of scope.

This function exists for backwards compatibility.

`tcod.console_fill_background` (*con: tcod.console.Console, r: Sequence[int], g: Sequence[int], b: Sequence[int]*) → `None`

Fill the background of a console with r,g,b.

Parameters

- `con` (`Console`) – Any Console instance.
- `r` (`Sequence[int]`) – An array of integers with a length of width*height.
- `g` (`Sequence[int]`) – An array of integers with a length of width*height.
- `b` (`Sequence[int]`) – An array of integers with a length of width*height.

Deprecated since version 8.4: You should assign to `tcod.console.Console.bg` instead.

`tcod.console_fill_char` (*con: tcod.console.Console, arr: Sequence[int]*) → `None`
Fill the character tiles of a console with an array.

`arr` is an array of integers with a length of the consoles width and height.

Deprecated since version 8.4: You should assign to `tcod.console.Console.ch` instead.

`tcod.console_fill_foreground` (*con: tcod.console.Console, r: Sequence[int], g: Sequence[int], b: Sequence[int]*) → `None`

Fill the foreground of a console with r,g,b.

Parameters

- `con` (`Console`) – Any Console instance.
- `r` (`Sequence[int]`) – An array of integers with a length of width*height.
- `g` (`Sequence[int]`) – An array of integers with a length of width*height.
- `b` (`Sequence[int]`) – An array of integers with a length of width*height.

Deprecated since version 8.4: You should assign to `tcod.console.Console.fg` instead.

`tcod.console_from_file` (*filename: str*) → `tcod.console.Console`
Return a new console object from a filename.

The file format is automatically determined. This can load REXPaint *.xp*, ASCII Paint *.apf*, or Non-delimited ASCII *.asc* files.

Parameters `filename` (*Text*) – The path to the file, as a string.

Returns: A new `:any` ‘Console’ instance.

`tcod.console_from_xp` (*filename: str*) → `tcod.console.Console`
Return a single console from a REXPaint *.xp* file.

`tcod.console_get_alignment` (*con: tcod.console.Console*) → `int`
Return this consoles current alignment mode.

Parameters `con` (*Console*) – Any Console instance.

Deprecated since version 8.5: Check `Console.default_alignment` instead.

`tcod.console_get_background_flag` (*con: tcod.console.Console*) → `int`
Return this consoles current blend mode.

Parameters `con` (*Console*) – Any Console instance.

Deprecated since version 8.5: Check `Console.default_bg_blend` instead.

`tcod.console_get_char` (*con: tcod.console.Console, x: int, y: int*) → `int`
Return the character at the *x,y* of this console.

Deprecated since version 8.4: Array access performs significantly faster than using this function. See `Console.ch`.

`tcod.console_get_char_background` (*con: tcod.console.Console, x: int, y: int*) → `tcod.color.Color`
Return the background color at the *x,y* of this console.

Deprecated since version 8.4: Array access performs significantly faster than using this function. See `Console.bg`.

`tcod.console_get_char_foreground` (*con: tcod.console.Console, x: int, y: int*) → `tcod.color.Color`
Return the foreground color at the *x,y* of this console.

Deprecated since version 8.4: Array access performs significantly faster than using this function. See `Console.fg`.

`tcod.console_get_default_background` (*con: tcod.console.Console*) → `tcod.color.Color`
Return this consoles default background color.

Deprecated since version 8.5: Use `Console.default_bg` instead.

`tcod.console_get_default_foreground` (*con: tcod.console.Console*) → `tcod.color.Color`
Return this consoles default foreground color.

Deprecated since version 8.5: Use `Console.default_fg` instead.

`tcod.console_get_fade` () → `int`

`tcod.console_get_fading_color` () → `tcod.color.Color`

`tcod.console_get_height` (*con: tcod.console.Console*) → `int`
Return the height of a console.

Parameters `con` (*Console*) – Any Console instance.

Returns The height of a Console.

Return type `int`

Deprecated since version 2.0: Use `Console.height` instead.

`tcod.console_get_height_rect` (*con: tcod.console.Console, x: int, y: int, w: int, h: int, fmt: str*) →

int
Return the height of this text once word-wrapped into this rectangle.

Returns The number of lines of text once word-wrapped.

Return type `int`

Deprecated since version 8.5: Use `Console.get_height_rect` instead.

`tcod.console_get_width` (*con: tcod.console.Console*) → `int`

Return the width of a console.

Parameters `con` (`Console`) – Any Console instance.

Returns The width of a Console.

Return type `int`

Deprecated since version 2.0: Use `Console.width` instead.

`tcod.console_hline` (*con: tcod.console.Console, x: int, y: int, l: int, flag: int = 13*) → `None`

Draw a horizontal line on the console.

This always uses the character 196, the horizontal line character.

Deprecated since version 8.5: Use `Console.hline` instead.

`tcod.console_is_fullscreen` () → `bool`

Returns True if the display is fullscreen.

Returns True if the display is fullscreen, otherwise False.

Return type `bool`

`tcod.console_is_key_pressed` (*key: int*) → `bool`

`tcod.console_is_window_closed` () → `bool`

Returns True if the window has received and exit event.

`tcod.console_load_apf` (*con: tcod.console.Console, filename: str*) → `bool`

Update a console from an ASCII Paint `.apf` file.

`tcod.console_load_asc` (*con: tcod.console.Console, filename: str*) → `bool`

Update a console from a non-delimited ASCII `.asc` file.

`tcod.console_load_xp` (*con: tcod.console.Console, filename: str*) → `bool`

Update a console from a REXPaint `.xp` file.

`tcod.console_list_load_xp` (*filename: str*) → `Optional[List[tcod.console.Console]]`

Return a list of consoles from a REXPaint `.xp` file.

`tcod.console_list_save_xp` (*console_list: Sequence[tcod.console.Console], filename: str, compress_level: int = 9*) → `bool`

Save a list of consoles to a REXPaint `.xp` file.

`tcod.console_map_ascii_code_to_font` (*asciiCode: int, fontCharX: int, fontCharY: int*) → `None`

Set a character code to new coordinates on the tile-set.

`asciiCode` must be within the bounds created during the initialization of the loaded tile-set. For example, you can't use 255 here unless you have a 256 tile tile-set loaded. This applies to all functions in this group.

Parameters

- **asciiCode** (`int`) – The character code to change.
- **fontCharX** (`int`) – The X tile coordinate on the loaded tileset. 0 is the leftmost tile.

- **fontCharY** (*int*) – The Y tile coordinate on the loaded tileset. 0 is the topmost tile.

`tcod.console_map_ascii_codes_to_font` (*firstCharCode: int, nbCodes: int, fontCharX: int, fontCharY: int*) → None

Remap a contiguous set of codes to a contiguous set of tiles.

Both the tile-set and character codes must be contiguous to use this function. If this is not the case you may want to use `console_map_ascii_code_to_font`.

Parameters

- **firstCharCode** (*int*) – The starting character code.
- **nbCodes** (*int*) – The length of the contiguous set.
- **fontCharX** (*int*) – The starting X tile coordinate on the loaded tileset. 0 is the leftmost tile.
- **fontCharY** (*int*) – The starting Y tile coordinate on the loaded tileset. 0 is the topmost tile.

`tcod.console_map_string_to_font` (*s: str, fontCharX: int, fontCharY: int*) → None

Remap a string of codes to a contiguous set of tiles.

Parameters

- **s** (*AnyStr*) – A string of character codes to map to new values. The null character ‘`x00`’ will prematurely end this function.
- **fontCharX** (*int*) – The starting X tile coordinate on the loaded tileset. 0 is the leftmost tile.
- **fontCharY** (*int*) – The starting Y tile coordinate on the loaded tileset. 0 is the topmost tile.

`tcod.console_new` (*w: int, h: int*) → `tcod.console.Console`

Return an offscreen console of size: w,h.

Deprecated since version 8.5: Create new consoles using `tcod.console.Console` instead of this function.

`tcod.console_print` (*con: tcod.console.Console, x: int, y: int, fmt: str*) → None

Print a color formatted string on a console.

Parameters

- **con** (`Console`) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.
- **fmt** (*AnyStr*) – A unicode or bytes string optionally using color codes.

Deprecated since version 8.5: Use `Console.print_` instead.

`tcod.console_print_ex` (*con: tcod.console.Console, x: int, y: int, flag: int, alignment: int, fmt: str*) → None

Print a string on a console using a blend mode and alignment mode.

Parameters

- **con** (`Console`) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.

Deprecated since version 8.5: Use `Console.print_` instead.

`tcod.console_print_frame` (*con: tcod.console.Console, x: int, y: int, w: int, h: int, clear: bool = True, flag: int = 13, fmt: str = "*) → None

Draw a framed rectangle with optional text.

This uses the default background color and blend mode to fill the rectangle and the default foreground to draw the outline.

fmt will be printed on the inside of the rectangle, word-wrapped. If *fmt* is empty then no title will be drawn.

Changed in version 8.2: Now supports Unicode strings.

Deprecated since version 8.5: Use `Console.print_frame` instead.

`tcod.console_print_rect` (*con: tcod.console.Console, x: int, y: int, w: int, h: int, fmt: str*) → int

Print a string constrained to a rectangle.

If *h* > 0 and the bottom of the rectangle is reached, the string is truncated. If *h* = 0, the string is only truncated if it reaches the bottom of the console.

Returns The number of lines of text once word-wrapped.

Return type int

Deprecated since version 8.5: Use `Console.print_rect` instead.

`tcod.console_print_rect_ex` (*con: tcod.console.Console, x: int, y: int, w: int, h: int, flag: int, alignment: int, fmt: str*) → int

Print a string constrained to a rectangle with blend and alignment.

Returns The number of lines of text once word-wrapped.

Return type int

Deprecated since version 8.5: Use `Console.print_rect` instead.

`tcod.console_put_char` (*con: tcod.console.Console, x: int, y: int, c: Union[int, str], flag: int = 13*) → None

Draw the character *c* at *x,y* using the default colors and a blend mode.

Parameters

- **con** (`Console`) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.
- **c** (`Union[int, AnyStr]`) – Character to draw, can be an integer or string.
- **flag** (*int*) – Blending mode to use, defaults to BKGND_DEFAULT.

`tcod.console_put_char_ex` (*con: tcod.console.Console, x: int, y: int, c: Union[int, str], fore: Tuple[int, int, int], back: Tuple[int, int, int]*) → None

Draw the character *c* at *x,y* using the colors *fore* and *back*.

Parameters

- **con** (`Console`) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.
- **c** (`Union[int, AnyStr]`) – Character to draw, can be an integer or string.
- **fore** (`Union[Tuple[int, int, int], Sequence[int]]`) – An (r, g, b) sequence or Color instance.

- **back** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

`tcod.console_rect` (*con: tcod.console.Console, x: int, y: int, w: int, h: int, clr: bool, flag: int = 13*) → None

Draw a the background color on a rect optionally clearing the text.

If `clr` is `True` the affected tiles are changed to space character.

Deprecated since version 8.5: Use `Console.rect` instead.

`tcod.console_save_apf` (*con: tcod.console.Console, filename: str*) → bool

Save a console to an ASCII Paint `.apf` file.

`tcod.console_save_asc` (*con: tcod.console.Console, filename: str*) → bool

Save a console to a non-delimited ASCII `.asc` file.

`tcod.console_save_xp` (*con: tcod.console.Console, filename: str, compress_level: int = 9*) → bool

Save a console to a REXPaint `.xp` file.

`tcod.console_set_alignment` (*con: tcod.console.Console, alignment: int*) → None

Change this consoles current alignment mode.

- `tcod.LEFT`
- `tcod.CENTER`
- `tcod.RIGHT`

Parameters

- **con** (*Console*) – Any Console instance.
- **alignment** (*int*) –

Deprecated since version 8.5: Set `Console.default_alignment` instead.

`tcod.console_set_background_flag` (*con: tcod.console.Console, flag: int*) → None

Change the default blend mode for this console.

Parameters

- **con** (*Console*) – Any Console instance.
- **flag** (*int*) – Blend mode to use by default.

Deprecated since version 8.5: Set `Console.default_bg_blend` instead.

`tcod.console_set_char` (*con: tcod.console.Console, x: int, y: int, c: Union[int, str]*) → None

Change the character at x,y to c, keeping the current colors.

Parameters

- **con** (*Console*) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.
- **c** (*Union[int, AnyStr]*) – Character to draw, can be an integer or string.

Deprecated since version 8.4: Array access performs significantly faster than using this function. See `Console.ch`.

`tcod.console_set_char_background` (*con: tcod.console.Console, x: int, y: int, col: Tuple[int, int, int], flag: int = 1*) → None

Change the background color of x,y to col using a blend mode.

Parameters

- **con** (*Console*) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.
- **col** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.
- **flag** (*int*) – Blending mode to use, defaults to BKGND_SET.

`tcod.console_set_char_foreground` (*con: tcod.console.Console, x: int, y: int, col: Tuple[int, int, int]*) → None

Change the foreground color of x,y to col.

Parameters

- **con** (*Console*) – Any Console instance.
- **x** (*int*) – Character x position from the left.
- **y** (*int*) – Character y position from the top.
- **col** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

Deprecated since version 8.4: Array access performs significantly faster than using this function. See [Console.fg](#).

`tcod.console_set_color_control` (*con: int, fore: Tuple[int, int, int], back: Tuple[int, int, int]*) → None

Configure color controls.

Parameters

- **con** (*int*) – Color control constant to modify.
- **fore** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.
- **back** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

`tcod.console_set_default_background` (*con: tcod.console.Console, col: Tuple[int, int, int]*) → None

Change the default background color for a console.

Parameters

- **con** (*Console*) – Any Console instance.
- **col** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

Deprecated since version 8.5: Use [Console.default_bg](#) instead.

`tcod.console_set_default_foreground` (*con: tcod.console.Console, col: Tuple[int, int, int]*) → None

Change the default foreground color for a console.

Parameters

- **con** (*Console*) – Any Console instance.
- **col** (*Union[Tuple[int, int, int], Sequence[int]]*) – An (r, g, b) sequence or Color instance.

Deprecated since version 8.5: Use `Console.default_fg` instead.

`tcod.console_set_fade` (*fade: int, fadingColor: Tuple[int, int, int]*) → None

`tcod.console_set_fullscreen` (*fullscreen: bool*) → None

Change the display to be fullscreen or windowed.

Parameters `fullscreen` (*bool*) – Use True to change to fullscreen. Use False to change to windowed.

`tcod.console_set_key_color` (*con: tcod.console.Console, col: Tuple[int, int, int]*) → None

Set a consoles blit transparent color.

Deprecated since version 8.5: Pass the key color to `tcod.console.Console.blit` instead of calling this function.

`tcod.console_set_window_title` (*title: str*) → None

Change the current title bar string.

Parameters `title` (*AnyStr*) – A string to change the title bar to.

`tcod.console_vline` (*con: tcod.console.Console, x: int, y: int, l: int, flag: int = 13*) → None

Draw a vertical line on the console.

This always uses the character 179, the vertical line character.

Deprecated since version 8.5: Use `Console.vline` instead.

`tcod.console_wait_for_keypress` (*flush: bool*) → `tcod.libtcodpy.Key`

Block until the user presses a key, then returns a new `Key`.

Parameters `bool` (*flush*) – If True then the event queue is cleared before waiting for the next event.

Returns A new `Key` instance.

Return type `Key`

17.4 Event

class `tcod.Key`

Key Event instance

vk

int – `TCOD_keycode_t` key code

c

int – character if `vk == TCODK_CHAR` else 0

text

Text – `text[TCOD_KEY_TEXT_SIZE]`; text if `vk == TCODK_TEXT` else `text[0] == ''`

pressed

bool – does this correspond to a key press or key release event?

lalt

bool – True when left alt is held.

lctrl

bool – True when left control is held.

lmeta

bool – True when left meta key is held.

ralt
bool – True when right alt is held.

rctrl
bool – True when right control is held.

rmeta
bool – True when right meta key is held.

shift
bool – True when any shift is held.

repr () → str
Return a representation of this Key object.

class `tcod.Mouse`

Mouse event instance

x
int – Absolute mouse position at pixel x.

y
int

dx
int – Movement since last update in pixels.

dy
int

cx
int – Cell coordinates in the root console.

cy
int

dcx
int – Movement since last update in console cells.

dcy
int

lbutton
bool – Left button status.

rbutton
bool – Right button status.

mbutton
bool – Middle button status.

lbutton_pressed
bool – Left button pressed event.

rbutton_pressed
bool – Right button pressed event.

mbutton_pressed
bool – Middle button pressed event.

wheel_up
bool – Wheel up event.

wheel_down

bool – Wheel down event.

__repr__ () → str

Return a representation of this Mouse object.

17.4.1 Event Types

`tcod.EVENT_NONE`

`tcod.EVENT_KEY_PRESS`

`tcod.EVENT_KEY_RELEASE`

`tcod.EVENT_KEY`

Same as `tcod.EVENT_KEY_PRESS` | `tcod.EVENT_KEY_RELEASE`

`tcod.EVENT_MOUSE_MOVE`

`tcod.EVENT_MOUSE_PRESS`

`tcod.EVENT_MOUSE_RELEASE`

`tcod.EVENT_MOUSE`

Same as `tcod.EVENT_MOUSE_MOVE` | `tcod.EVENT_MOUSE_PRESS` | `tcod.EVENT_MOUSE_RELEASE`

`tcod.EVENT_FINGER_MOVE`

`tcod.EVENT_FINGER_PRESS`

`tcod.EVENT_FINGER_RELEASE`

`tcod.EVENT_FINGER`

Same as `tcod.EVENT_FINGER_MOVE` | `tcod.EVENT_FINGER_PRESS` | `tcod.EVENT_FINGER_RELEASE`

`tcod.EVENT_ANY`

Same as `tcod.EVENT_KEY` | `tcod.EVENT_MOUSE` | `tcod.EVENT_FINGER`

17.5 sys

`tcod.sys_set_fps (fps: int) → None`

Set the maximum frame rate.

You can disable the frame limit again by setting fps to 0.

Parameters `fps (int)` – A frame rate limit (i.e. 60)

`tcod.sys_get_fps () → int`

Return the current frames per second.

This the actual frame rate, not the frame limit set by `tcod.sys_set_fps`.

This number is updated every second.

Returns The currently measured frame rate.

Return type `int`

`tcod.sys_get_last_frame_length () → float`

Return the delta time of the last rendered frame in seconds.

Returns The delta time of the last rendered frame.

Return type `float`

`tcod.sys_sleep_milli (val: int) → None`
Sleep for 'val' milliseconds.

Parameters `val (int)` – Time to sleep for in milliseconds.

Deprecated since version 2.0: Use `time.sleep` instead.

`tcod.sys_elapsed_milli () → int`
Get number of milliseconds since the start of the program.

Returns Time since the program has started in milliseconds.

Return type `int`

Deprecated since version 2.0: Use `time.clock` instead.

`tcod.sys_elapsed_seconds () → float`
Get number of seconds since the start of the program.

Returns Time since the program has started in seconds.

Return type `float`

Deprecated since version 2.0: Use `time.clock` instead.

`tcod.sys_set_renderer (renderer: int) → None`
Change the current rendering mode to `renderer`.

Deprecated since version 2.0: `RENDERER_GLSL` and `RENDERER_OPENGL` are not currently available.

`tcod.sys_get_renderer () → int`
Return the current rendering mode.

`tcod.sys_save_screenshot (name: Optional[str] = None) → None`
Save a screenshot to a file.

By default this will automatically save screenshots in the working directory.

The automatic names are formatted as `screenshotNNN.png`. For example: `screenshot000.png`, `screenshot001.png`, etc. Whichever is available first.

Parameters `Optional[AnyStr] (file)` – File path to save screenshot.

`tcod.sys_force_fullscreen_resolution (width: int, height: int) → None`
Force a specific resolution in fullscreen.

Will use the smallest available resolution so that:

- resolution width \geq width and resolution width \geq root console width * font char width
- resolution height \geq height and resolution height \geq root console height * font char height

Parameters

- `width (int)` – The desired resolution width.
- `height (int)` – The desired resolution height.

`tcod.sys_get_current_resolution () → Tuple[int, int]`
Return the current resolution as (width, height)

Returns The current resolution.

Return type Tuple[int,int]

`tcod.sys_get_char_size()` → Tuple[int, int]

Return the current fonts character size as (width, height)

Returns The current font glyph size in (width, height)

Return type Tuple[int,int]

`tcod.sys_update_char(asciiCode: int, fontx: int, fonty: int, img: tcod.image.Image, x: int, y: int)` → None

Dynamically update the current font with img.

All cells using this asciiCode will be updated at the next call to `tcod.console_flush`.

Parameters

- **asciiCode** (*int*) – Ascii code corresponding to the character to update.
- **fontx** (*int*) – Left coordinate of the character in the bitmap font (in tiles)
- **fonty** (*int*) – Top coordinate of the character in the bitmap font (in tiles)
- **img** (*Image*) – An image containing the new character bitmap.
- **x** (*int*) – Left pixel of the character in the image.
- **y** (*int*) – Top pixel of the character in the image.

`tcod.sys_register_SDL_renderer(callback: Callable[[Any], None])` → None

Register a custom rendering function with libtcod.

Note: This callback will only be called by the SDL renderer.

The callack will receive a CData void* to an SDL_Surface* struct.

The callback is called on every call to `tcod.console_flush`.

Parameters Callable[[CData], None] (*callback*) – A function which takes a single argument.

`tcod.sys_check_for_event(mask: int, k: Optional[tcod.libtcodpy.Key], m: Optional[tcod.libtcodpy.Mouse])` → int

Check for and return an event.

Parameters

- **mask** (*int*) – *Event Types* to wait for.
- **k** (*Optional[Key]*) – A tcod.Key instance which might be updated with an event. Can be None.
- **m** (*Optional[Mouse]*) – A tcod.Mouse instance which might be updated with an event. Can be None.

`tcod.sys_wait_for_event(mask: int, k: Optional[tcod.libtcodpy.Key], m: Optional[tcod.libtcodpy.Mouse], flush: bool)` → int

Wait for an event then return.

If flush is True then the buffer will be cleared before waiting. Otherwise each available event will be returned in the order they're recieved.

Parameters

- **mask** (*int*) – *Event Types* to wait for.

- **k** (*Optional*[*Key*]) – A `tcod.Key` instance which might be updated with an event. Can be `None`.
- **m** (*Optional*[*Mouse*]) – A `tcod.Mouse` instance which might be updated with an event. Can be `None`.
- **flush** (*bool*) – Clear the event buffer before waiting.

17.6 pathfinding

`tcod.dijkstra_compute` (*p: tcod.path.Dijkstra, ox: int, oy: int*) → `None`

`tcod.dijkstra_delete` (*p: tcod.path.Dijkstra*) → `None`

Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.dijkstra_get` (*p: tcod.path.Dijkstra, idx: int*) → `Tuple[int, int]`

`tcod.dijkstra_get_distance` (*p: tcod.path.Dijkstra, x: int, y: int*) → `int`

`tcod.dijkstra_is_empty` (*p: tcod.path.Dijkstra*) → `bool`

`tcod.dijkstra_new` (*m: tcod.map.Map, dcost: float = 1.41*) → `tcod.path.Dijkstra`

`tcod.dijkstra_new_using_function` (*w: int, h: int, func: Callable[[int, int, int, int, Any], float], userData: Any = 0, dcost: float = 1.41*) → `tcod.path.Dijkstra`

`tcod.dijkstra_path_set` (*p: tcod.path.Dijkstra, x: int, y: int*) → `bool`

`tcod.dijkstra_path_walk` (*p: tcod.path.Dijkstra*) → `Union[Tuple[int, int], Tuple[None, None]]`

`tcod.dijkstra_reverse` (*p: tcod.path.Dijkstra*) → `None`

`tcod.dijkstra_size` (*p: tcod.path.Dijkstra*) → `int`

`tcod.path_compute` (*p: tcod.path.AStar, ox: int, oy: int, dx: int, dy: int*) → `bool`

Find a path from (ox, oy) to (dx, dy). Return `True` if path is found.

Parameters

- **p** (*AStar*) – An `AStar` instance.
- **ox** (*int*) – Starting x position.
- **oy** (*int*) – Starting y position.
- **dx** (*int*) – Destination x position.
- **dy** (*int*) – Destination y position.

Returns `True` if a valid path was found. Otherwise `False`.

Return type `bool`

`tcod.path_delete` (*p: tcod.path.AStar*) → `None`

Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.path_get` (*p: tcod.path.AStar, idx: int*) → `Tuple[int, int]`

Get a point on a path.

Parameters

- **p** (*AStar*) – An `AStar` instance.

- **idx** (*int*) – Should be in range: $0 \leq \text{inx} < \text{path_size}$

`tcod.path.get_destination` (*p: tcod.path.AStar*) → Tuple[int, int]
Get the current destination position.

Parameters *p* (*AStar*) – An AStar instance.

Returns An (x, y) point.

Return type Tuple[int, int]

`tcod.path.get_origin` (*p: tcod.path.AStar*) → Tuple[int, int]
Get the current origin position.

This point moves when `path_walk` returns the next x,y step.

Parameters *p* (*AStar*) – An AStar instance.

Returns An (x, y) point.

Return type Tuple[int, int]

`tcod.path.is_empty` (*p: tcod.path.AStar*) → bool
Return True if a path is empty.

Parameters *p* (*AStar*) – An AStar instance.

Returns True if a path is empty. Otherwise False.

Return type bool

`tcod.path.new_using_function` (*w: int, h: int, func: Callable[[int, int, int, int, Any], float], userData: Any = 0, dcost: float = 1.41*) → *tcod.path.AStar*
Return a new AStar using the given callable function.

Parameters

- **w** (*int*) – Clipping width.
- **h** (*int*) – Clipping height.
- **func** (*Callable[[int, int, int, int, Any], float]*) –
- **userData** (*Any*) –
- **dcost** (*float*) – A multiplier for the cost of diagonal movement. Can be set to 0 to disable diagonal movement.

Returns A new AStar instance.

Return type *AStar*

`tcod.path.new_using_map` (*m: tcod.map.Map, dcost: float = 1.41*) → *tcod.path.AStar*
Return a new AStar using the given Map.

Parameters

- **m** (*Map*) – A Map instance.
- **dcost** (*float*) – The path-finding cost of diagonal movement. Can be set to 0 to disable diagonal movement.

Returns A new AStar instance.

Return type *AStar*

`tcod.path_reverse` (*p*: `tcod.path.AStar`) → None
Reverse the direction of a path.

This effectively swaps the origin and destination points.

Parameters *p* (`AStar`) – An `AStar` instance.

`tcod.path_size` (*p*: `tcod.path.AStar`) → int
Return the current length of the computed path.

Parameters *p* (`AStar`) – An `AStar` instance.

Returns Length of the path.

Return type int

`tcod.path_walk` (*p*: `tcod.path.AStar`, *recompute*: `bool`) → Union[Tuple[int, int], Tuple[None, None]]
Return the next (x, y) point in a path, or (None, None) if it's empty.

When `recompute` is `True` and a previously valid path reaches a point where it is now blocked, a new path will automatically be found.

Parameters

- *p* (`AStar`) – An `AStar` instance.
- *recompute* (`bool`) – Recompute the path automatically.

Returns A single (x, y) point, or (None, None)

Return type Union[Tuple[int, int], Tuple[None, None]]

17.7 heightmap

`tcod.heightmap_add` (*hm*: `numpy.ndarray`, *value*: `float`) → None
Add value to all values on this heightmap.

Parameters

- *hm* (`numpy.ndarray`) – A `numpy.ndarray` formatted for heightmap functions.
- *value* (`float`) – A number to add to this heightmap.

Deprecated since version 2.0: Do `hm[:] += value` instead.

`tcod.heightmap_add_fbm` (*hm*: `numpy.ndarray`, *noise*: `tcod.noise.Noise`, *mulx*: `float`, *muly*: `float`, *addx*: `float`, *addy*: `float`, *octaves*: `float`, *delta*: `float`, *scale*: `float`) → None
Add FBM noise to the heightmap.

The noise coordinate for each map cell is $((x + addx) * mulx / width, (y + addy) * muly / height)$.

The value added to the heightmap is $delta + noise * scale$.

Parameters

- *hm* (`numpy.ndarray`) – A `numpy.ndarray` formatted for heightmap functions.
- *noise* (`Noise`) – A `Noise` instance.
- *mulx* (`float`) – Scaling of each x coordinate.
- *muly* (`float`) – Scaling of each y coordinate.
- *addx* (`float`) – Translation of each x coordinate.
- *addy* (`float`) – Translation of each y coordinate.

- **octaves** (*float*) – Number of octaves in the FBM sum.
- **delta** (*float*) – The value added to all heightmap cells.
- **scale** (*float*) – The noise value is scaled with this parameter.

Deprecated since version 8.1: An equivalent array of noise samples can be taken using a method such as `Noise.sample_ogrid`.

`tcod.heightmap_add_hill` (*hm: numpy.ndarray, x: float, y: float, radius: float, height: float*) → None
Add a hill (a half spheroid) at given position.

If height == radius or -radius, the hill is a half-sphere.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **x** (*float*) – The x position at the center of the new hill.
- **y** (*float*) – The y position at the center of the new hill.
- **radius** (*float*) – The size of the new hill.
- **height** (*float*) – The height or depth of the new hill.

`tcod.heightmap_add_hm` (*hm1: numpy.ndarray, hm2: numpy.ndarray, hm3: numpy.ndarray*) → None
Add two heightmaps together and stores the result in `hm3`.

Parameters

- **hm1** (*numpy.ndarray*) – The first heightmap.
- **hm2** (*numpy.ndarray*) – The second heightmap to add to the first.
- **hm3** (*numpy.ndarray*) – A destination heightmap to store the result.

Deprecated since version 2.0: Do `hm3[:] = hm1[:] + hm2[:]` instead.

`tcod.heightmap_add_voronoi` (*hm: numpy.ndarray, nbPoints: Any, nbCoef: int, coef: Sequence[float], rnd: Optional[tcod.random.Random] = None*) → None
Add values from a Voronoi diagram to the heightmap.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **nbPoints** (*Any*) – Number of Voronoi sites.
- **nbCoef** (*int*) – The diagram value is calculated from the `nbCoef` closest sites.
- **coef** (*Sequence[float]*) – The distance to each site is scaled by the corresponding `coef`. Closest site : `coef[0]`, second closest site : `coef[1]`, ...
- **rnd** (*Optional[Random]*) – A `Random` instance, or `None`.

`tcod.heightmap_clamp` (*hm: numpy.ndarray, mi: float, ma: float*) → None
Clamp all values on this heightmap between `mi` and `ma`

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **mi** (*float*) – The lower bound to clamp to.
- **ma** (*float*) – The upper bound to clamp to.

Deprecated since version 2.0: Do `hm.clip(mi, ma)` instead.

`tcod.heightmap_clear` (*hm: numpy.ndarray*) → None

Add value to all values on this heightmap.

Parameters `hm` (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.

Deprecated since version 2.0: Do `hm.array[:] = 0` instead.

`tcod.heightmap_copy` (*hm1: numpy.ndarray, hm2: numpy.ndarray*) → None

Copy the heightmap `hm1` to `hm2`.

Parameters

- `hm1` (*numpy.ndarray*) – The source heightmap.
- `hm2` (*numpy.ndarray*) – The destination heightmap.

Deprecated since version 2.0: Do `hm2[:] = hm1[:]` instead.

`tcod.heightmap_count_cells` (*hm: numpy.ndarray, mi: float, ma: float*) → int

Return the number of map cells which value is between `mi` and `ma`.

Parameters

- `hm` (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- `mi` (*float*) – The lower bound.
- `ma` (*float*) – The upper bound.

Returns The count of values which fall between `mi` and `ma`.

Return type int

Deprecated since version 8.1: Can be replaced by an equivalent NumPy function such as: `numpy.count_nonzero((mi <= hm) & (hm < ma))`

`tcod.heightmap_delete` (*hm: Any*) → None

Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

Deprecated since version 2.0: libtcod-cffi deletes heightmaps automatically.

`tcod.heightmap_dig_bezier` (*hm: numpy.ndarray, px: Tuple[int, int, int, int], py: Tuple[int, int, int, int], startRadius: float, startDepth: float, endRadius: float, endDepth: float*) → None

Carve a path along a cubic Bezier curve.

Both radius and depth can vary linearly along the path.

Parameters

- `hm` (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- `px` (*Sequence[int]*) – The 4 *x* coordinates of the Bezier curve.
- `py` (*Sequence[int]*) – The 4 *y* coordinates of the Bezier curve.
- `startRadius` (*float*) – The starting radius size.
- `startDepth` (*float*) – The starting depth.
- `endRadius` (*float*) – The ending radius size.
- `endDepth` (*float*) – The ending depth.

`tcod.heightmap_dig_hill` (*hm: numpy.ndarray, x: float, y: float, radius: float, height: float*) → None
 This function takes the highest value (if height > 0) or the lowest (if height < 0) between the map and the hill.

It's main goal is to carve things in maps (like rivers) by digging hills along a curve.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **x** (*float*) – The x position at the center of the new carving.
- **y** (*float*) – The y position at the center of the new carving.
- **radius** (*float*) – The size of the carving.
- **height** (*float*) – The height or depth of the hill to dig out.

`tcod.heightmap_get_interpolated_value` (*hm: numpy.ndarray, x: float, y: float*) → float
 Return the interpolated height at non integer coordinates.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **x** (*float*) – A floating point x coordinate.
- **y** (*float*) – A floating point y coordinate.

Returns The value at x, y.

Return type float

`tcod.heightmap_get_minmax` (*hm: numpy.ndarray*) → Tuple[float, float]
 Return the min and max values of this heightmap.

Parameters **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.

Returns The (min, max) values.

Return type Tuple[float, float]

Deprecated since version 2.0: Use `hm.min()` or `hm.max()` instead.

`tcod.heightmap_get_normal` (*hm: numpy.ndarray, x: float, y: float, waterLevel: float*) → Tuple[float, float, float]
 Return the map normal at given coordinates.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **x** (*float*) – The x coordinate.
- **y** (*float*) – The y coordinate.
- **waterLevel** (*float*) – The heightmap is considered flat below this value.

Returns An (x, y, z) vector normal.

Return type Tuple[float, float, float]

`tcod.heightmap_get_slope` (*hm: numpy.ndarray, x: int, y: int*) → float
 Return the slope between 0 and ($\pi / 2$) at given coordinates.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **x** (*int*) – The x coordinate.

- **y** (*int*) – The y coordinate.

Returns The steepness at x, y. From 0 to (pi / 2)

Return type float

`tcod.heightmap_get_value` (*hm: numpy.ndarray, x: int, y: int*) → float

Return the value at x, y in a heightmap.

Deprecated since version 2.0: Access *hm* as a NumPy array instead.

`tcod.heightmap_has_land_on_border` (*hm: numpy.ndarray, waterlevel: float*) → bool

Returns True if the map edges are below *waterlevel*, otherwise False.

Parameters

- **hm** (*numpy.ndarray*) – A *numpy.ndarray* formatted for heightmap functions.
- **waterLevel** (*float*) – The water level to use.

Returns True if the map edges are below *waterlevel*, otherwise False.

Return type bool

`tcod.heightmap_kernel_transform` (*hm: numpy.ndarray, kernelSize: int, dx: Sequence[int], dy: Sequence[int], weight: Sequence[float], minLevel: float, maxLevel: float*) → None

Apply a generic transformation on the map, so that each resulting cell value is the weighted sum of several neighbour cells.

This can be used to smooth/sharpen the map.

Parameters

- **hm** (*numpy.ndarray*) – A *numpy.ndarray* formatted for heightmap functions.
- **kernelSize** (*int*) –
Should be set to the length of the parameters:: dx, dy, and weight.
- **dx** (*Sequence[int]*) – A sequence of x coordinates.
- **dy** (*Sequence[int]*) – A sequence of y coordinates.
- **weight** (*Sequence[float]*) – A sequence of *kernelSize* cells weight. The value of each neighbour cell is scaled by its corresponding weight
- **minLevel** (*float*) – No transformation will apply to cells below this value.
- **maxLevel** (*float*) – No transformation will apply to cells above this value.

See examples below for a simple horizontal smoothing kernel : replace *value(x,y)* with $0.33*\text{value}(x-1,y) + 0.33*\text{value}(x,y) + 0.33*\text{value}(x+1,y)$. To do this, you need a kernel of size 3 (the sum involves 3 surrounding cells). The *dx,dy* array will contain:

- *dx=-1, dy=0* for cell (x-1, y)
- *dx=1, dy=0* for cell (x+1, y)
- *dx=0, dy=0* for cell (x, y)
- The weight array will contain 0.33 for each cell.

Example

```

>>> import numpy as np
>>> heightmap = np.zeros((3, 3), dtype=np.float32)
>>> heightmap[:,1] = 1
>>> dx = [-1, 1, 0]
>>> dy = [0, 0, 0]
>>> weight = [0.33, 0.33, 0.33]
>>> tcod.heightmap_kernel_transform(heightmap, 3, dx, dy, weight,
...                               0.0, 1.0)

```

`tcod.heightmap_lerp_hm` (*hm1*: *numpy.ndarray*, *hm2*: *numpy.ndarray*, *hm3*: *numpy.ndarray*, *coef*: *float*) → *None*

Perform linear interpolation between two heightmaps storing the result in *hm3*.

This is the same as doing $hm3[:] = hm1[:] + (hm2[:] - hm1[:]) * coef$

Parameters

- **hm1** (*numpy.ndarray*) – The first heightmap.
- **hm2** (*numpy.ndarray*) – The second heightmap to add to the first.
- **hm3** (*numpy.ndarray*) – A destination heightmap to store the result.
- **coef** (*float*) – The linear interpolation coefficient.

`tcod.heightmap_multiply_hm` (*hm1*: *numpy.ndarray*, *hm2*: *numpy.ndarray*, *hm3*: *numpy.ndarray*) → *None*

Multiplies two heightmap's together and stores the result in *hm3*.

Parameters

- **hm1** (*numpy.ndarray*) – The first heightmap.
- **hm2** (*numpy.ndarray*) – The second heightmap to multiply with the first.
- **hm3** (*numpy.ndarray*) – A destination heightmap to store the result.

Deprecated since version 2.0: Do $hm3[:] = hm1[:] * hm2[:]$ instead. Alternatively you can do `HeightMap(hm1.array[:] * hm2.array[:])`.

`tcod.heightmap_new` (*w*: *int*, *h*: *int*, *order*: *str = 'C'*) → *numpy.ndarray*

Return a new *numpy.ndarray* formatted for use with heightmap functions.

w and *h* are the width and height of the array.

order is given to the new NumPy array, it can be 'C' or 'F'.

You can pass a NumPy array to any heightmap function as long as all the following are true:: * The array is 2 dimensional. * The array has the `C_CONTIGUOUS` or `F_CONTIGUOUS` flag. * The array's dtype is `dtype.float32`.

The returned NumPy array will fit all these conditions.

Changed in version 8.1: Added the *order* parameter.

`tcod.heightmap_normalize` (*hm*: *numpy.ndarray*, *mi*: *float = 0.0*, *ma*: *float = 1.0*) → *None*

Normalize heightmap values between *mi* and *ma*.

Parameters

- **mi** (*float*) – The lowest value after normalization.
- **ma** (*float*) – The highest value after normalization.

`tcod.heightmap_rain_erosion` (*hm: numpy.ndarray, nbDrops: int, erosionCoef: float, sedimentationCoef: float, rnd: Optional[tcod.random.Random] = None*) → None
Simulate the effect of rain drops on the terrain, resulting in erosion.

`nbDrops` should be at least `hm.size`.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **nbDrops** (*int*) – Number of rain drops to simulate.
- **erosionCoef** (*float*) – Amount of ground eroded on the drop’s path.
- **sedimentationCoef** (*float*) – Amount of ground deposited when the drops stops to flow.
- **rnd** (*Optional[Random]*) – A `tcod.Random` instance, or None.

`tcod.heightmap_scale` (*hm: numpy.ndarray, value: float*) → None
Multiply all items on this heightmap by value.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **value** (*float*) – A number to scale this heightmap by.

Deprecated since version 2.0: Do `hm[:] *= value` instead.

`tcod.heightmap_scale_fbm` (*hm: numpy.ndarray, noise: tcod.noise.Noise, mulx: float, muly: float, addx: float, addy: float, octaves: float, delta: float, scale: float*) → None
Multiply the heighmap values with FBM noise.

Parameters

- **hm** (*numpy.ndarray*) – A `numpy.ndarray` formatted for heightmap functions.
- **noise** (*Noise*) – A `Noise` instance.
- **mulx** (*float*) – Scaling of each x coordinate.
- **muly** (*float*) – Scaling of each y coordinate.
- **addx** (*float*) – Translation of each x coordinate.
- **addy** (*float*) – Translation of each y coordinate.
- **octaves** (*float*) – Number of octaves in the FBM sum.
- **delta** (*float*) – The value added to all heightmap cells.
- **scale** (*float*) – The noise value is scaled with this parameter.

Deprecated since version 8.1: An equivalent array of noise samples can be taken using a method such as `Noise.sample_ogrid`.

`tcod.heightmap_set_value` (*hm: numpy.ndarray, x: int, y: int, value: float*) → None
Set the value of a point on a heightmap.

Deprecated since version 2.0: `hm` is a NumPy array, so values should be assigned to it directly.

17.8 image

`tcod.image_load` (*filename: str*) → `tcod.image.Image`
Load an image file into an `Image` instance and return it.

Parameters `filename` (*AnyStr*) – Path to a .bmp or .png image file.

`tcod.image_from_console` (*console: tcod.console.Console*) → `tcod.image.Image`
Return an Image with a Consoles pixel data.

This effectively takes a screen-shot of the Console.

Parameters `console` (*Console*) – Any Console instance.

`tcod.image_blit` (*image: tcod.image.Image, console: tcod.console.Console, x: float, y: float, bkgnd_flag: int, scalex: float, scaley: float, angle: float*) → `None`

`tcod.image_blit_2x` (*image: tcod.image.Image, console: tcod.console.Console, dx: int, dy: int, sx: int = 0, sy: int = 0, w: int = -1, h: int = -1*) → `None`

`tcod.image_blit_rect` (*image: tcod.image.Image, console: tcod.console.Console, x: int, y: int, w: int, h: int, bkgnd_flag: int*) → `None`

`tcod.image_clear` (*image: tcod.image.Image, col: Tuple[int, int, int]*) → `None`

`tcod.image_delete` (*image: tcod.image.Image*) → `None`
Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.image_get_alpha` (*image: tcod.image.Image, x: int, y: int*) → `int`

`tcod.image_get_mipmap_pixel` (*image: tcod.image.Image, x0: float, y0: float, x1: float, y1: float*) → `Tuple[int, int, int]`

`tcod.image_get_pixel` (*image: tcod.image.Image, x: int, y: int*) → `Tuple[int, int, int]`

`tcod.image_get_size` (*image: tcod.image.Image*) → `Tuple[int, int]`

`tcod.image_hflip` (*image: tcod.image.Image*) → `None`

`tcod.image_invert` (*image: tcod.image.Image*) → `None`

`tcod.image_is_pixel_transparent` (*image: tcod.image.Image, x: int, y: int*) → `bool`

`tcod.image_new` (*width: int, height: int*) → `tcod.image.Image`

`tcod.image_put_pixel` (*image: tcod.image.Image, x: int, y: int, col: Tuple[int, int, int]*) → `None`

`tcod.image_refresh_console` (*image: tcod.image.Image, console: tcod.console.Console*) → `None`

`tcod.image_rotate90` (*image: tcod.image.Image, num: int = 1*) → `None`

`tcod.image_save` (*image: tcod.image.Image, filename: str*) → `None`

`tcod.image_scale` (*image: tcod.image.Image, neww: int, newh: int*) → `None`

`tcod.image_set_key_color` (*image: tcod.image.Image, col: Tuple[int, int, int]*) → `None`

`tcod.image_vflip` (*image: tcod.image.Image*) → `None`

17.9 line

`tcod.line_init` (*xo: int, yo: int, xd: int, yd: int*) → `None`
Initilize a line whose points will be returned by `line_step`.

This function does not return anything on its own.

Does not include the origin point.

Parameters

- `xo(int)` – X starting point.
- `yo(int)` – Y starting point.
- `xd(int)` – X destination point.
- `yd(int)` – Y destination point.

Deprecated since version 2.0: Use `line_iter` instead.

`tcod.line_step()` → Union[Tuple[int, int], Tuple[None, None]]

After calling `line_init` returns (x, y) points of the line.

Once all points are exhausted this function will return (None, None)

Returns The next (x, y) point of the line setup by `line_init`, or (None, None) if there are no more points.

Return type Union[Tuple[int, int], Tuple[None, None]]

Deprecated since version 2.0: Use `line_iter` instead.

`tcod.line(xo: int, yo: int, xd: int, yd: int, py_callback: Callable[[int, int], bool])` → bool

Iterate over a line using a callback function.

Your callback function will take x and y parameters and return True to continue iteration or False to stop iteration and return.

This function includes both the start and end points.

Parameters

- `xo(int)` – X starting point.
- `yo(int)` – Y starting point.
- `xd(int)` – X destination point.
- `yd(int)` – Y destination point.
- `py_callback(Callable[[int, int], bool])` – A callback which takes x and y parameters and returns bool.

Returns

False if the callback cancels the line iteration by returning False or None, otherwise True.

Return type bool

Deprecated since version 2.0: Use `line_iter` instead.

`tcod.line_iter(xo: int, yo: int, xd: int, yd: int)` → Iterator[Tuple[int, int]]

returns an Iterable

This Iterable does not include the origin point.

Parameters

- `xo(int)` – X starting point.
- `yo(int)` – Y starting point.
- `xd(int)` – X destination point.
- `yd(int)` – Y destination point.

Returns An Iterable of (x,y) points.

Return type Iterable[Tuple[int,int]]

`tcod.line_where` (*x1*: int, *y1*: int, *x2*: int, *y2*: int, *inclusive*: bool = True) → Tuple[numpy.array, numpy.array]
 Return a NumPy index array following a Bresenham line.
 If *inclusive* is true then the start point is included in the result.

Example

```
>>> where = tcod.line_where(1, 0, 3, 4)
>>> where
(array([1, 1, 2, 2, 3]...), array([0, 1, 2, 3, 4]...))
>>> array = np.zeros((5, 5), dtype=np.int32)
>>> array[where] = np.arange(len(where[0])) + 1
>>> array
array([[0, 0, 0, 0, 0],
       [1, 2, 0, 0, 0],
       [0, 0, 3, 4, 0],
       [0, 0, 0, 0, 5],
       [0, 0, 0, 0, 0]]...)
```

New in version 4.6.

17.10 map

`tcod.map_clear` (*m*: `tcod.map.Map`, *transparent*: bool = False, *walkable*: bool = False) → None
 Change all map cells to a specific value.

Deprecated since version 4.5: Use `tcod.map.Map.transparent` and `tcod.map.Map.walkable` arrays to set these properties.

`tcod.map_compute_fov` (*m*: `tcod.map.Map`, *x*: int, *y*: int, *radius*: int = 0, *light_walls*: bool = True, *algo*: int = 12) → None
 Compute the field-of-view for a map instance.

Deprecated since version 4.5: Use `tcod.map.Map.compute_fov` instead.

`tcod.map_copy` (*source*: `tcod.map.Map`, *dest*: `tcod.map.Map`) → None
 Copy map data from *source* to *dest*.

Deprecated since version 4.5: Use Python's copy module, or see `tcod.map.Map` and assign between array attributes manually.

`tcod.map_delete` (*m*: `tcod.map.Map`) → None
 Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.map_get_height` (*map*: `tcod.map.Map`) → int
 Return the height of a map.

Deprecated since version 4.5: Check the `tcod.map.Map.height` attribute instead.

`tcod.map_get_width` (*map*: `tcod.map.Map`) → int
 Return the width of a map.

Deprecated since version 4.5: Check the `tcod.map.Map.width` attribute instead.

`tcod.map_is_in_fov` (*m*: *tcod.map.Map*, *x*: *int*, *y*: *int*) → bool
Return True if the cell at *x,y* is lit by the last field-of-view algorithm.

Note: This function is slow.

Deprecated since version 4.5: Use `tcod.map.Map.fov` to check this property.

`tcod.map_is_transparent` (*m*: *tcod.map.Map*, *x*: *int*, *y*: *int*) → bool

Note: This function is slow.

Deprecated since version 4.5: Use `tcod.map.Map.transparent` to check this property.

`tcod.map_is_walkable` (*m*: *tcod.map.Map*, *x*: *int*, *y*: *int*) → bool

Note: This function is slow.

Deprecated since version 4.5: Use `tcod.map.Map.walkable` to check this property.

`tcod.map_new` (*w*: *int*, *h*: *int*) → *tcod.map.Map*
Return a `tcod.map.Map` with a width and height.

Deprecated since version 4.5: Use the `tcod.map` module for working with field-of-view, or `tcod.path` for working with path-finding.

`tcod.map_set_properties` (*m*: *tcod.map.Map*, *x*: *int*, *y*: *int*, *isTrans*: *bool*, *isWalk*: *bool*) → None
Set the properties of a single cell.

Note: This function is slow.

Deprecated since version 4.5: Use `tcod.map.Map.transparent` and `tcod.map.Map.walkable` arrays to set these properties.

17.11 mouse

`tcod.mouse_get_status` () → *tcod.libtcodpy.Mouse*

`tcod.mouse_is_cursor_visible` () → bool
Return True if the mouse cursor is visible.

`tcod.mouse_move` (*x*: *int*, *y*: *int*) → None

`tcod.mouse_show_cursor` (*visible*: *bool*) → None
Change the visibility of the mouse cursor.

17.12 namegen

`tcod.namegen_destroy` () → None

`tcod.namegen_generate` (*name: str*) → str

`tcod.namegen_generate_custom` (*name: str, rule: str*) → str

`tcod.namegen_get_sets` () → List[str]

`tcod.namegen_parse` (*filename: str, random: Optional[tcod.random.Random] = None*) → None

17.13 noise

`tcod.noise_delete` (*n: tcod.noise.Noise*) → None

Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.noise_get` (*n: tcod.noise.Noise, f: Sequence[float], typ: int = 0*) → float

Return the noise value sampled from the *f* coordinate.

f should be a tuple or list with a length matching `Noise.dimensions`. If *f* is shorter than `Noise.dimensions` the missing coordinates will be filled with zeros.

Parameters

- **n** (`Noise`) – A `Noise` instance.
- **f** (`Sequence[float]`) – The point to sample the noise from.
- **typ** (`int`) – The noise algorithm to use.

Returns The sampled noise value.

Return type float

`tcod.noise_get_fbm` (*n: tcod.noise.Noise, f: Sequence[float], oc: float, typ: int = 0*) → float

Return the fractal Brownian motion sampled from the *f* coordinate.

Parameters

- **n** (`Noise`) – A `Noise` instance.
- **f** (`Sequence[float]`) – The point to sample the noise from.
- **typ** (`int`) – The noise algorithm to use.
- **octaves** (`float`) – The level of level. Should be more than 1.

Returns The sampled noise value.

Return type float

`tcod.noise_get_turbulence` (*n: tcod.noise.Noise, f: Sequence[float], oc: float, typ: int = 0*) → float

Return the turbulence noise sampled from the *f* coordinate.

Parameters

- **n** (`Noise`) – A `Noise` instance.
- **f** (`Sequence[float]`) – The point to sample the noise from.
- **typ** (`int`) – The noise algorithm to use.
- **octaves** (`float`) – The level of level. Should be more than 1.

Returns The sampled noise value.

Return type float

`tcod.noise_new` (*dim: int, h: float = 0.5, l: float = 2.0, random: Optional[tcod.random.Random] = None*)
→ `tcod.noise.Noise`
Return a new Noise instance.

Parameters

- **dim** (*int*) – Number of dimensions. From 1 to 4.
- **h** (*float*) – The hurst exponent. Should be in the 0.0-1.0 range.
- **l** (*float*) – The noise lacunarity.
- **random** (*Optional[Random]*) – A Random instance, or None.

Returns The new Noise instance.

Return type *Noise*

`tcod.noise_set_type` (*n: tcod.noise.Noise, typ: int*) → None
Set a Noise objects default noise algorithm.

Parameters **typ** (*int*) – Any NOISE_* constant.

17.14 parser

`tcod.parser_delete` (*parser: Any*) → None
Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.parser_get_bool_property` (*parser: Any, name: str*) → bool

`tcod.parser_get_char_property` (*parser: Any, name: str*) → str

`tcod.parser_get_color_property` (*parser: Any, name: str*) → `tcod.color.Color`

`tcod.parser_get_dice_property` (*parser: Any, name: str*) → `tcod.libtcodpy.Dice`

`tcod.parser_get_float_property` (*parser: Any, name: str*) → float

`tcod.parser_get_int_property` (*parser: Any, name: str*) → int

`tcod.parser_get_list_property` (*parser: Any, name: str, type: Any*) → Any

`tcod.parser_get_string_property` (*parser: Any, name: str*) → str

`tcod.parser_new` () → Any

`tcod.parser_new_struct` (*parser: Any, name: str*) → Any

`tcod.parser_run` (*parser: Any, filename: str, listener: Any = None*) → None

17.15 random

`tcod.random_delete` (*rnd: tcod.random.Random*) → None
Does nothing. libtcod objects are managed by Python's garbage collector.

This function exists for backwards compatibility with libtcodpy.

`tcod.random_get_double` (*rnd*: *Optional*[*tcod.random.Random*], *mi*: *float*, *ma*: *float*) → *float*
 Return a random float in the range: $mi \leq n \leq ma$.

Deprecated since version 2.0: Use `random_get_float` instead. Both funtions return a double precision float.

`tcod.random_get_double_mean` (*rnd*: *Optional*[*tcod.random.Random*], *mi*: *float*, *ma*: *float*, *mean*: *float*) → *float*

Return a random weighted float in the range: $mi \leq n \leq ma$.

Deprecated since version 2.0: Use `random_get_float_mean` instead. Both funtions return a double precision float.

`tcod.random_get_float` (*rnd*: *Optional*[*tcod.random.Random*], *mi*: *float*, *ma*: *float*) → *float*
 Return a random float in the range: $mi \leq n \leq ma$.

The result is affacted by calls to `random_set_distribution`.

Parameters

- **rnd** (*Optional*[*Random*]) – A *Random* instance, or *None* to use the default.
- **low** (*float*) – The lower bound of the random range, inclusive.
- **high** (*float*) – The upper bound of the random range, inclusive.

Returns

A random double precision float in the range $mi \leq n \leq ma$.

Return type *float*

`tcod.random_get_float_mean` (*rnd*: *Optional*[*tcod.random.Random*], *mi*: *float*, *ma*: *float*, *mean*: *float*) → *float*

Return a random weighted float in the range: $mi \leq n \leq ma$.

The result is affacted by calls to `random_set_distribution`.

Parameters

- **rnd** (*Optional*[*Random*]) – A *Random* instance, or *None* to use the default.
- **low** (*float*) – The lower bound of the random range, inclusive.
- **high** (*float*) – The upper bound of the random range, inclusive.
- **mean** (*float*) – The mean return value.

Returns

A random weighted double precision float in the range $mi \leq n \leq ma$.

Return type *float*

`tcod.random_get_instance` () → *tcod.random.Random*
 Return the default *Random* instance.

Returns A *Random* instance using the default random number generator.

Return type *Random*

`tcod.random_get_int` (*rnd*: *Optional*[*tcod.random.Random*], *mi*: *int*, *ma*: *int*) → *int*
 Return a random integer in the range: $mi \leq n \leq ma$.

The result is affacted by calls to `random_set_distribution`.

Parameters

- **rnd** (*Optional*[*Random*]) – A *Random* instance, or *None* to use the default.

- **low** (*int*) – The lower bound of the random range, inclusive.
- **high** (*int*) – The upper bound of the random range, inclusive.

Returns A random integer in the range $m_i \leq n \leq m_a$.

Return type *int*

`tcod.random_get_int_mean` (*rnd: Optional[tcod.random.Random]*, *mi: int*, *ma: int*, *mean: int*) → *int*
Return a random weighted integer in the range: $m_i \leq n \leq m_a$.

The result is affected by calls to *random_set_distribution*.

Parameters

- **rnd** (*Optional[Random]*) – A Random instance, or None to use the default.
- **low** (*int*) – The lower bound of the random range, inclusive.
- **high** (*int*) – The upper bound of the random range, inclusive.
- **mean** (*int*) – The mean return value.

Returns A random weighted integer in the range $m_i \leq n \leq m_a$.

Return type *int*

`tcod.random_new` (*algo: int = 1*) → *tcod.random.Random*
Return a new Random instance. Using *algo*.

Parameters **algo** (*int*) – The random number algorithm to use.

Returns A new Random instance using the given algorithm.

Return type *Random*

`tcod.random_new_from_seed` (*seed: Hashable*, *algo: int = 1*) → *tcod.random.Random*
Return a new Random instance. Using the given *seed* and *algo*.

Parameters

- **seed** (*Hashable*) – The RNG seed. Should be a 32-bit integer, but any hashable object is accepted.
- **algo** (*int*) – The random number algorithm to use.

Returns A new Random instance using the given algorithm.

Return type *Random*

`tcod.random_restore` (*rnd: Optional[tcod.random.Random]*, *backup: tcod.random.Random*) → *None*
Restore a random number generator from a backed up copy.

Parameters

- **rnd** (*Optional[Random]*) – A Random instance, or None to use the default.
- **backup** (*Random*) – The Random instance which was used as a backup.

Deprecated since version 8.4: You can use the standard library copy and pickle modules to save a random state.

`tcod.random_save` (*rnd: Optional[tcod.random.Random]*) → *tcod.random.Random*
Return a copy of a random number generator.

Deprecated since version 8.4: You can use the standard library copy and pickle modules to save a random state.

`tcod.random_set_distribution` (*rnd: Optional[tcod.random.Random]*, *dist: int*) → *None*
Change the distribution mode of a random number generator.

Parameters

- **rnd** (*Optional [Random]*) – A `Random` instance, or `None` to use the default.
- **dist** (*int*) – The distribution mode to use. Should be `DISTRIBUTION_*`.

17.16 struct

`tcod.struct_add_flag` (*struct, name*)

`tcod.struct_add_list_property` (*struct, name, typ, mandatory*)

`tcod.struct_add_property` (*struct, name, typ, mandatory*)

`tcod.struct_add_structure` (*struct, sub_struct*)

`tcod.struct_add_value_list` (*struct, name, value_list, mandatory*)

`tcod.struct_get_name` (*struct*)

`tcod.struct_get_type` (*struct, name*)

`tcod.struct_is_mandatory` (*struct, name*)

17.17 other

class `tcod.ConsoleBuffer` (*width: int, height: int, back_r: int = 0, back_g: int = 0, back_b: int = 0, fore_r: int = 0, fore_g: int = 0, fore_b: int = 0, char: str = ''*)

Simple console that allows direct (fast) access to cells. simplifies use of the “fill” functions.

Deprecated since version 6.0: Console array attributes perform better than this class.

Parameters

- **width** (*int*) – Width of the new `ConsoleBuffer`.
- **height** (*int*) – Height of the new `ConsoleBuffer`.
- **back_r** (*int*) – Red background color, from 0 to 255.
- **back_g** (*int*) – Green background color, from 0 to 255.
- **back_b** (*int*) – Blue background color, from 0 to 255.
- **fore_r** (*int*) – Red foreground color, from 0 to 255.
- **fore_g** (*int*) – Green foreground color, from 0 to 255.
- **fore_b** (*int*) – Blue foreground color, from 0 to 255.
- **char** (*AnyStr*) – A single character `str` or `bytes` object.

blit (*dest: tcod.console.Console, fill_fore: bool = True, fill_back: bool = True*) → `None`

Use `libtcod`’s “fill” functions to write the buffer to a console.

Parameters

- **dest** (`Console`) – Console object to modify.
- **fill_fore** (`bool`) – If `True`, fill the foreground color and characters.
- **fill_back** (`bool`) – If `True`, fill the background color.

clear (*back_r: int = 0, back_g: int = 0, back_b: int = 0, fore_r: int = 0, fore_g: int = 0, fore_b: int = 0, char: str = ' ')* → None
Clears the console. Values to fill it with are optional, defaults to black with no characters.

Parameters

- **back_r** (*int*) – Red background color, from 0 to 255.
- **back_g** (*int*) – Green background color, from 0 to 255.
- **back_b** (*int*) – Blue background color, from 0 to 255.
- **fore_r** (*int*) – Red foreground color, from 0 to 255.
- **fore_g** (*int*) – Green foreground color, from 0 to 255.
- **fore_b** (*int*) – Blue foreground color, from 0 to 255.
- **char** (*AnyStr*) – A single character str or bytes object.

copy () → `tcod.libtcodpy.ConsoleBuffer`
Returns a copy of this ConsoleBuffer.

Returns A new ConsoleBuffer copy.

Return type *ConsoleBuffer*

set (*x: int, y: int, back_r: int, back_g: int, back_b: int, fore_r: int, fore_g: int, fore_b: int, char: str*) → None
Set the background color, foreground color and character of one cell.

Parameters

- **x** (*int*) – X position to change.
- **y** (*int*) – Y position to change.
- **back_r** (*int*) – Red background color, from 0 to 255.
- **back_g** (*int*) – Green background color, from 0 to 255.
- **back_b** (*int*) – Blue background color, from 0 to 255.
- **fore_r** (*int*) – Red foreground color, from 0 to 255.
- **fore_g** (*int*) – Green foreground color, from 0 to 255.
- **fore_b** (*int*) – Blue foreground color, from 0 to 255.
- **char** (*AnyStr*) – A single character str or bytes object.

set_back (*x: int, y: int, r: int, g: int, b: int*) → None
Set the background color of one cell.

Parameters

- **x** (*int*) – X position to change.
- **y** (*int*) – Y position to change.
- **r** (*int*) – Red background color, from 0 to 255.
- **g** (*int*) – Green background color, from 0 to 255.
- **b** (*int*) – Blue background color, from 0 to 255.

set_fore (*x: int, y: int, r: int, g: int, b: int, char: str*) → None
Set the character and foreground color of one cell.

Parameters

- **x** (*int*) – X position to change.
- **y** (*int*) – Y position to change.
- **r** (*int*) – Red foreground color, from 0 to 255.
- **g** (*int*) – Green foreground color, from 0 to 255.
- **b** (*int*) – Blue foreground color, from 0 to 255.
- **char** (*AnyStr*) – A single character str or bytes object.

class `tcod.Dice` (*nb_dices=0, nb_faces=0, multiplier=0, addsub=0*)

Parameters

- **nb_dices** (*int*) – Number of dice.
- **nb_faces** (*int*) – Number of sides on a die.
- **multiplier** (*float*) – Multiplier.
- **addsub** (*float*) – Addition.

Deprecated since version 2.0: You should make your own dice functions instead of using this class which is tied to a CData object.

Deprecated since version 8.4: This module has been deprecated.

18.1 Getting Started

Once the library is imported you can load the font you want to use with `tdl.set_font`. This is optional and when skipped will use a decent default font.

After that you call `tdl.init` to set the size of the window and get the root console in return. This console is the canvas to what will appear on the screen.

18.2 Indexing Consoles

For most methods taking a position you can use Python-style negative indexes to refer to the opposite side of a console with `(-1, -1)` starting at the bottom right. You can also check if a point is part of a console using containment logic i.e. `((x, y) in console)`.

You may also iterate over a console using a for statement. This returns every x,y coordinate available to draw on but it will be extremely slow to actually operate on every coordinate individually. Try to minimize draws by using an offscreen `Console`, only drawing what needs to be updated, and using `Console.blit`.

18.3 Drawing and Colors

Once you have the root console from `tdl.init` you can start drawing on it using a method such as `Console.draw_char`. When using this method you can have the char parameter be an integer or a single character string.

The `fg` and `bg` parameters expect a variety of types. The parameters default to Ellipsis which will tell the function to use the colors previously set by the `Console.set_colors` method. The colors set by

:any 'Console.set_colors' are per each *Console/Window* and default to white on black. You can use a 3-item list/tuple of [red, green, blue] with integers in the 0-255 range with [0, 0, 0] being black and [255, 255, 255] being white. You can even use a single integer of 0xRRGGBB if you like.

Using None in the place of any of the three parameters (char, fg, bg) will tell the function to not overwrite that color or character.

After the drawing functions are called a call to `tdl.flush` will update the screen.

18.4 tdl API

`tdl.set_font` (*path*, *columns=None*, *rows=None*, *columnFirst=False*, *greyscale=False*, *altLayout=False*)

Changes the font to be used for this session. This should be called before `tdl.init`

If the font specifies its size in its filename (i.e. font_NxN.png) then this function can auto-detect the tileset formatting and the parameters columns and rows can be left None.

While it's possible you can change the font mid program it can sometimes break in rare circumstances. So use caution when doing this.

Parameters

- **path** (*Text*) – A file path to a *.bmp* or *.png* file.
- **columns** (*int*) – Number of columns in the tileset.
Can be left None for auto-detection.
- **rows** (*int*) – Number of rows in the tileset.
Can be left None for auto-detection.
- **columnFirst** (*bool*) – Defines if the character order goes along the rows or columns.
It should be True if the character codes 0-15 are in the first column, and should be False if the characters 0-15 are in the first row.
- **greyscale** (*bool*) – Creates an anti-aliased font from a greyscale bitmap. Otherwise it uses the alpha channel for anti-aliasing.
Unless you actually need anti-aliasing from a font you know uses a smooth greyscale channel you should leave this on False.
- **altLayout** (*bool*) – An alternative layout with space in the upper left corner. The column parameter is ignored if this is True, find examples of this layout in the *font/libtcod/* directory included with the python-tdl source.

Raises *TDLError* – Will be raised if no file is found at path or if auto- detection fails.

`tdl.init` (*width*, *height*, *title=None*, *fullscreen=False*, *renderer='SDL'*)

Start the main console with the given width and height and return the root console.

Call the consoles drawing functions. Then remember to use `L{tdl.flush}` to make what's drawn visible on the console.

Parameters

- **width** (*int*) – width of the root console (in tiles)
- **height** (*int*) – height of the root console (in tiles)
- **title** (*Optional[Text]*) – Text to display as the window title.
If left None it defaults to the running scripts filename.

- **fullscreen** (*bool*) – Can be set to True to start in fullscreen mode.
- **renderer** (*Text*) – Can be one of ‘GLSL’, ‘OPENGL’, or ‘SDL’.
- **to way Python works you're unlikely to see much of an** (*Due*) –
- **by using 'GLSL' over 'OPENGL' as most of the** (*improvement*) –
- **Python is slow interacting with the console and the** (*time*) –
- **itself is pretty fast even on 'SDL'.** (*rendering*) –

Returns

The root console.

Only what is drawn on the root console is what's visible after a call to `tdl.flush`. After the root console is garbage collected, the window made by this function will close.

Return type `tdl.Console`

See also:

`Console.set_font`

`tdl.flush()`

Make all changes visible and update the screen.

Remember to call this function after drawing operations. Calls to flush will enforce the frame rate limit set by `tdl.set_fps`.

This function can only be called after `tdl.init`

`tdl.screenshot(path=None)`

Capture the screen and save it as a png file.

If path is None then the image will be placed in the current folder with the names: `screenshot001.png`, `screenshot002.png`, ...

Parameters `path` (*Optional[Text]*) – The file path to save the screenshot.

`tdl.get_fullscreen()`

Returns True if program is fullscreen.

Returns

Returns True if the application is in full-screen mode. Otherwise returns False.

Return type `bool`

`tdl.set_fullscreen(fullscreen)`

Changes the fullscreen state.

Parameters `fullscreen` (*bool*) – True for full-screen, False for windowed mode.

`tdl.set_title(title)`

Change the window title.

Parameters `title` (*Text*) – The new title text.

`tdl.get_fps()`

Return the current frames per second of the running program set by `set_fps`

Returns

The frame rate set by `set_fps`. If there is no current limit, this will return 0.

Return type `int`

`tdl.set_fps` (*fps*)

Set the maximum frame rate.

Further calls to `tdl.flush` will limit the speed of the program to run at *fps* frames per second. This can also be set to `None` to remove the frame rate limit.

Parameters `fps` (*optional[int]*) – The frames per second limit, or `None`.

`tdl.force_resolution` (*width, height*)

Change the fullscreen resolution.

Parameters

- `width` (*int*) – Width in pixels.
- `height` (*int*) – Height in pixels.

exception `tdl.TDLError`

The catch all for most TDL specific errors.

18.5 tdl.Console

class `tdl.Console` (*width, height*)

Contains character and color data and can be drawn to.

The console created by the `tdl.init` function is the root console and is the console that is rendered to the screen with `flush`.

Any console created from the `Console` class is an off-screen console that can be drawn on before being `blit` to the root console.

Parameters

- `width` (*int*) – Width of the new console in tiles
- `height` (*int*) – Height of the new console in tiles

`__contains__` (*position*)

Use `((x, y) in console)` to check if a position is drawable on this console.

`__del__` ()

If the main console is garbage collected then the window will be closed as well

`__iter__` ()

Return an iterator with every possible (x, y) value for this console.

It goes without saying that working on the console this way is a slow process, especially for Python, and should be minimized.

Returns An `((x, y), ...)` iterator.

Return type `Iterator[Tuple[int, int]]`

blit (*source, x=0, y=0, width=None, height=None, srcX=0, srcY=0, fg_alpha=1.0, bg_alpha=1.0*)

Blit another console or `Window` onto the current console.

By default it blits the entire source to the topleft corner.

Parameters

- `source` (*Union[tdl.Console, tdl.Window]*) – The blitting source. A console can blit to itself without any problems.
- `x` (*int*) – x-coordinate of this console to blit on.

- **y** (*int*) – y-coordinate of this console to blit on.
- **width** (*Optional[int]*) – Width of the rectangle.
Can be None to extend as far as possible to the bottom right corner of the blit area or can be a negative number to be sized relative to the total size of the B{destination} console.
- **height** (*Optional[int]*) – Height of the rectangle.
- **srcX** (*int*) – x-coordinate of the source region to blit.
- **srcY** (*int*) – y-coordinate of the source region to blit.
- **fg_alpha** (*float*) – The foreground alpha.

clear (*fg=Ellipsis, bg=Ellipsis*)

Clears the entire L{Console}/L{Window}.

Unlike other drawing functions, fg and bg can not be None.

Parameters

- **fg** (*Union[Tuple[int, int, int], int, Ellipsis]*)–
- **bg** (*Union[Tuple[int, int, int], int, Ellipsis]*)–

See also:

draw_rect

draw_char (*x, y, char, fg=Ellipsis, bg=Ellipsis*)

Draws a single character.

Parameters

- **x** (*int*) – x-coordinate to draw on.
- **y** (*int*) – y-coordinate to draw on.
- **char** (*Optional[Union[int, Text]]*) – An integer, single character string, or None.
You can set the char parameter as None if you only want to change the colors of the tile.
- **fg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*)–
- **bg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*)–

Raises: AssertionError: Having x or y values that can't be placed inside of the console will raise an AssertionError. You can use always use ((x, y) in console) to check if a tile is drawable.

See also:

get_char

draw_frame (*x, y, width, height, string, fg=Ellipsis, bg=Ellipsis*)

Similar to L{draw_rect} but only draws the outline of the rectangle.

width or *height* can be None to extend to the bottom right of the console or can be a negative number to be sized relative to the total size of the console.

Parameters

- **x** (*int*) – The x-coordinate to start on.
- **y** (*int*) – The y-coordinate to start on.
- **width** (*Optional[int]*) – Width of the rectangle.

- **height** (*Optional[int]*) – Height of the rectangle.
- **string** (*Optional[Union[Text, int]]*) – An integer, single character string, or None.

You can set this parameter as None if you only want to change the colors of an area.

- **fg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –
- **bg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –

Raises

AssertionError – Having x or y values that can't be placed inside of the console will raise an AssertionError.

You can use always use ((x, y) in console) to check if a tile is drawable.

See also:

draw_rect, Window

draw_rect (*x, y, width, height, string, fg=Ellipsis, bg=Ellipsis*)

Draws a rectangle starting from x and y and extending to width and height.

If width or height are None then it will extend to the edge of the console.

Parameters

- **x** (*int*) – x-coordinate for the top side of the rect.
- **y** (*int*) – y-coordinate for the left side of the rect.
- **width** (*Optional[int]*) – The width of the rectangle.
Can be None to extend to the bottom right of the console or can be a negative number to be sized relative to the total size of the console.
- **height** (*Optional[int]*) – The height of the rectangle.
- **string** (*Optional[Union[Text, int]]*) – An integer, single character string, or None.

You can set the string parameter as None if you only want to change the colors of an area.

- **fg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –
- **bg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –

Raises

- **AssertionError** – Having x or y values that can't be placed inside of the console will raise an AssertionError.
- You can use always use ((x, y) in console) to check if a tile
- is drawable.

See also:

clear, draw_frame

draw_str (*x, y, string, fg=Ellipsis, bg=Ellipsis*)

Draws a string starting at x and y.

A string that goes past the right side will wrap around. A string wrapping to below the console will raise *tdl.TDLError* but will still be written out. This means you can safely ignore the errors with a try..except block if you're fine with partially written strings.

r and n are drawn on the console as normal character tiles. No special encoding is done and any string will translate to the character table as is.

For a string drawing operation that respects special characters see `print_str`.

Parameters

- **x** (*int*) – x-coordinate to start at.
- **y** (*int*) – y-coordinate to start at.
- **string** (*Union[Text, Iterable[int]]*) – A string or an iterable of numbers.
Special characters are ignored and rendered as any other character.
- **fg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –
- **bg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –

Raises

AssertionError – Having x or y values that can't be placed inside of the console will raise an AssertionError.

You can use always use `((x, y) in console)` to check if a tile is drawable.

See also:

`print_str`

get_char (*x, y*)

Return the character and colors of a tile as (ch, fg, bg)

This method runs very slowly as is not recommended to be called frequently.

Parameters

- **x** (*int*) – The x-coordinate to pick.
- **y** (*int*) – The y-coordinate to pick.

Returns

A 3-item tuple: (*int, fg, bg*)

The first item is an integer of the character at the position (x, y) the second and third are the foreground and background colors respectfully.

Return type `Tuple[int, Tuple[int, int, int], Tuple[int, int, int]]`

See also:

`draw_char`

get_cursor ()

Return the virtual cursor position.

The cursor can be moved with the `move` method.

Returns

The (x, y) coordinate of where `print_str` will continue from.

Return type `Tuple[int, int]`

See also:

`:any:move`

get_size()

Return the size of the console as (width, height)

Returns A (width, height) tuple.

Return type Tuple[int, int]

move(x, y)

Move the virtual cursor.

Parameters

- **x** (*int*) – x-coordinate to place the cursor.
- **y** (*int*) – y-coordinate to place the cursor.

See also:

get_cursor, print_str, write

print_str(string)

Print a string at the virtual cursor.

Handles special characters such as ‘n’ and ‘r’. Printing past the bottom of the console will scroll everything upwards if *set_mode* is set to ‘scroll’.

Colors can be set with *set_colors* and the virtual cursor can be moved with *move*.

Parameters **string** (*Text*) – The text to print.

See also:

draw_str, move, set_colors, set_mode, write, Window

scroll(x, y)

Scroll the contents of the console in the direction of x,y.

Uncovered areas will be cleared to the default background color. Does not move the virtual cursor.

Parameters

- **x** (*int*) – Distance to scroll along the x-axis.
- **y** (*int*) – Distance to scroll along the y-axis.

Returns An iterator over the (x, y) coordinates of any tile uncovered after scrolling.

Return type Iterator[Tuple[int, int]]

See also:

set_colors

set_colors(fg=None, bg=None)

Sets the colors to be used with the L{print_str} and draw_* methods.

Values of None will only leave the current values unchanged.

Parameters

- **fg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –
- **bg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –

See also:

move, print_str

set_mode (*mode*)

Configure how this console will react to the cursor writing past the end of the console.

This is for methods that use the virtual cursor, such as `print_str`.

Parameters

- **mode** (*Text*) – The mode to set.
- **settings are** (*Possible*) –
 - ‘error’ - A `TDLError` will be raised once the cursor reaches the end of the console. Everything up until the error will still be drawn. This is the default setting.
 - ‘scroll’ - The console will scroll up as stuff is written to the end. You can restrict the region with `tdl.Window` when doing this.

..seealso: `write`, `print_str`

write (*string*)

This method mimics basic file-like behaviour.

Because of this method you can replace `sys.stdout` or `sys.stderr` with a `Console` or `Window` instance.

This is a convoluted process and behaviour seen now can be expected to change on later versions.

Parameters **string** (*Text*) – The text to write out.

See also:

`set_colors`, `set_mode`, `Window`

18.6 tdl.Window

class `tdl.Window` (*console, x, y, width, height*)

Isolate part of a `Console` or `Window` instance.

This classes methods are the same as `tdl.Console`

Making a `Window` and setting its width or height to `None` will extend it to the edge of the console.

This follows the normal rules for indexing so you can use a negative integer to place the `Window` relative to the bottom right of the parent `Console` instance.

width or *height* can be set to `None` to extend as far as possible to the bottom right corner of the parent `Console` or can be a negative number to be sized relative to the `Consoles` total size.

Parameters

- **console** (*Union*(`tdl.Console`, `tdl.Window`)) – The parent object.
- **x** (*int*) – x-coordinate to place the `Window`.
- **y** (*int*) – y-coordinate to place the `Window`.
- **width** (*Optional*[*int*]) – Width of the `Window`.
- **height** (*Optional*[*int*]) – Height of the `Window`.

clear (*fg=Ellipsis, bg=Ellipsis*)

Clears the entire `L{Console}/L{Window}`.

Unlike other drawing functions, `fg` and `bg` can not be `None`.

Parameters

- **fg** (*Union*[*Tuple*[*int*, *int*, *int*], *int*, *Ellipsis*)]-
- **bg** (*Union*[*Tuple*[*int*, *int*, *int*], *int*, *Ellipsis*)]-

See also:

draw_rect

draw_char (*x*, *y*, *char*, *fg=Ellipsis*, *bg=Ellipsis*)

Draws a single character.

Parameters

- **x** (*int*) – x-coordinate to draw on.
- **y** (*int*) – y-coordinate to draw on.
- **char** (*Optional*[*Union*[*int*, *Text*]]) – An integer, single character string, or None.

You can set the char parameter as None if you only want to change the colors of the tile.

- **fg** (*Optional*[*Union*[*Tuple*[*int*, *int*, *int*], *int*, *Ellipsis*]])-
- **bg** (*Optional*[*Union*[*Tuple*[*int*, *int*, *int*], *int*, *Ellipsis*]])-

Raises: AssertionError: Having x or y values that can't be placed inside of the console will raise an AssertionError. You can use always use ((*x*, *y*) in console) to check if a tile is drawable.

See also:

get_char

draw_frame (*x*, *y*, *width*, *height*, *string*, *fg=Ellipsis*, *bg=Ellipsis*)

Similar to L{draw_rect} but only draws the outline of the rectangle.

width or *height* can be None to extend to the bottom right of the console or can be a negative number to be sized relative to the total size of the console.

Parameters

- **x** (*int*) – The x-coordinate to start on.
- **y** (*int*) – The y-coordinate to start on.
- **width** (*Optional*[*int*]) – Width of the rectangle.
- **height** (*Optional*[*int*]) – Height of the rectangle.
- **string** (*Optional*[*Union*[*Text*, *int*]]) – An integer, single character string, or None.

You can set this parameter as None if you only want to change the colors of an area.

- **fg** (*Optional*[*Union*[*Tuple*[*int*, *int*, *int*], *int*, *Ellipsis*]])-
- **bg** (*Optional*[*Union*[*Tuple*[*int*, *int*, *int*], *int*, *Ellipsis*]])-

Raises

AssertionError – Having x or y values that can't be placed inside of the console will raise an AssertionError.

You can use always use ((*x*, *y*) in console) to check if a tile is drawable.

See also:

draw_rect, *Window*

draw_rect (*x*, *y*, *width*, *height*, *string*, *fg=Ellipsis*, *bg=Ellipsis*)

Draws a rectangle starting from *x* and *y* and extending to *width* and *height*.

If *width* or *height* are `None` then it will extend to the edge of the console.

Parameters

- **x** (*int*) – x-coordinate for the top side of the rect.
- **y** (*int*) – y-coordinate for the left side of the rect.
- **width** (*Optional[int]*) – The width of the rectangle.
Can be `None` to extend to the bottom right of the console or can be a negative number to be sized relative to the total size of the console.
- **height** (*Optional[int]*) – The height of the rectangle.
- **string** (*Optional[Union[Text, int]]*) – An integer, single character string, or `None`.
You can set the `string` parameter as `None` if you only want to change the colors of an area.
- **fg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –
- **bg** (*Optional[Union[Tuple[int, int, int], int, Ellipsis]]*) –

Raises

- `AssertionError` – Having *x* or *y* values that can't be placed inside of the console will raise an `AssertionError`.
- You can use always use `((x, y) in console)` to check if a tile
- is drawable.

See also:

`clear`, `draw_frame`

get_char (*x*, *y*)

Return the character and colors of a tile as (*ch*, *fg*, *bg*)

This method runs very slowly as is not recommended to be called frequently.

Parameters

- **x** (*int*) – The x-coordinate to pick.
- **y** (*int*) – The y-coordinate to pick.

Returns

A 3-item tuple: (*int*, *fg*, *bg*)

The first item is an integer of the character at the position (*x*, *y*) the second and third are the foreground and background colors respectively.

Return type `Tuple[int, Tuple[int, int, int], Tuple[int, int, int]]`

See also:

`draw_char`

This module handles user input.

To handle user input you will likely want to use the `event.get` function or create a subclass of `event.App`.

- `tdl.event.get` iterates over recent events.
- `tdl.event.App` passes events to the overridable methods: `ev_*` and `key_*`.

But there are other options such as `event.key_wait` and `event.is_window_closed`.

A few event attributes are actually string constants. Here's a reference for those:

- `Event.type`: 'QUIT', 'KEYDOWN', 'KEYUP', 'MOUSEDOWN', 'MOUSEUP', or 'MOUSEMOTION.'
- `MouseButtonEvent.button` (found in `MouseDown` and `MouseUp` events): 'LEFT', 'MIDDLE', 'RIGHT', 'SCROLLUP', 'SCROLLDOWN'
- `KeyEvent.key` (found in `KeyDown` and `KeyUp` events): 'NONE', 'ESCAPE', 'BACKSPACE', 'TAB', 'ENTER', 'SHIFT', 'CONTROL', 'ALT', 'PAUSE', 'CAPSLOCK', 'PAGEUP', 'PAGEDOWN', 'END', 'HOME', 'UP', 'LEFT', 'RIGHT', 'DOWN', 'PRINTSCREEN', 'INSERT', 'DELETE', 'LWIN', 'RWIN', 'APPS', '0', '1', '2', '3', '4', '5', '6', '7', '8', '9', 'KP0', 'KP1', 'KP2', 'KP3', 'KP4', 'KP5', 'KP6', 'KP7', 'KP8', 'KP9', 'KPADD', 'KPSUB', 'KPDIV', 'KPMUL', 'KPDEC', 'KPENTER', 'F1', 'F2', 'F3', 'F4', 'F5', 'F6', 'F7', 'F8', 'F9', 'F10', 'F11', 'F12', 'NUMLOCK', 'SCROLLLOCK', 'SPACE', 'CHAR'

class `tdl.event.Event`

Base Event class.

You can easily subclass this to make your own events. Be sure to set the class attribute `L{Event.type}` for it to be passed to a custom `App ev_*` method.

`__repr__()`

List an events public attributes when printed.

`type = None`

String constant representing the type of event.

The `App ev_*` methods depend on this attribute.

Can be: 'QUIT', 'KEYDOWN', 'KEYUP', 'MOUSEDOWN', 'MOUSEUP', or 'MOUSEMOTION.'

class `tdl.event.Quit`

Fired when the window is closed by the user.

class `tdl.event.KeyEvent` (*key=""*, *char=""*, *text=""*, *shift=False*, *left_alt=False*, *right_alt=False*,
left_control=False, *right_control=False*, *left_meta=False*,
right_meta=False)

Base class for key events.

alt = None

bool – True if alt was held down during this event.

char = None

Text – A single character string of the letter or symbol pressed.

Special characters like delete and return are not cross-platform. `L{key}` or `L{keychar}` should be used instead for special keys. Characters are also case sensitive.

control = None

bool – True if control was held down during this event.

key = None

Text – Human readable names of the key pressed. Non special characters will show up as ‘CHAR’.

Can be one of ‘NONE’, ‘ESCAPE’, ‘BACKSPACE’, ‘TAB’, ‘ENTER’, ‘SHIFT’, ‘CONTROL’, ‘ALT’, ‘PAUSE’, ‘CAPSLOCK’, ‘PAGEUP’, ‘PAGEDOWN’, ‘END’, ‘HOME’, ‘UP’, ‘LEFT’, ‘RIGHT’, ‘DOWN’, ‘PRINTSCREEN’, ‘INSERT’, ‘DELETE’, ‘LWIN’, ‘RWIN’, ‘APPS’, ‘0’, ‘1’, ‘2’, ‘3’, ‘4’, ‘5’, ‘6’, ‘7’, ‘8’, ‘9’, ‘KP0’, ‘KP1’, ‘KP2’, ‘KP3’, ‘KP4’, ‘KP5’, ‘KP6’, ‘KP7’, ‘KP8’, ‘KP9’, ‘KPADD’, ‘KPSUB’, ‘KPDIV’, ‘KPMUL’, ‘KPDEC’, ‘KPENTER’, ‘F1’, ‘F2’, ‘F3’, ‘F4’, ‘F5’, ‘F6’, ‘F7’, ‘F8’, ‘F9’, ‘F10’, ‘F11’, ‘F12’, ‘NUMLOCK’, ‘SCROLLLOCK’, ‘SPACE’, ‘CHAR’

For the actual character instead of ‘CHAR’ use *keychar*.

keychar = None

Similar to `L{key}` but returns a case sensitive letter or symbol instead of ‘CHAR’.

This variable makes available the widest variety of symbols and should be used for key-mappings or anywhere where a narrower sample of keys isn’t needed.

left_alt = None

bool

left_control = None

bool

right_alt = None

bool

right_control = None

bool

shift = None

bool – True if shift was held down during this event.

class `tdl.event.KeyDown` (*key=""*, *char=""*, *text=""*, *shift=False*, *left_alt=False*, *right_alt=False*,
left_control=False, *right_control=False*, *left_meta=False*,
right_meta=False)

Fired when the user presses a key on the keyboard or a key repeats.

class `tdl.event.KeyUp` (*key=""*, *char=""*, *text=""*, *shift=False*, *left_alt=False*, *right_alt=False*,
left_control=False, *right_control=False*, *left_meta=False*, *right_meta=False*)

Fired when the user releases a key on the keyboard.

class `tdl.event.MouseButtonEvent` (*button, pos, cell*)

Base class for mouse button events.

button = `None`

Text – Can be one of ‘LEFT’, ‘MIDDLE’, ‘RIGHT’, ‘SCROLLUP’, ‘SCROLLDOWN’

cell = `None`

Tuple[int, int] – (x, y) position of the mouse snapped to a cell on the root console

pos = `None`

Tuple[int, int] – (x, y) position of the mouse on the screen.

class `tdl.event.MouseDown` (*button, pos, cell*)

Fired when a mouse button is pressed.

class `tdl.event.MouseUp` (*button, pos, cell*)

Fired when a mouse button is released.

class `tdl.event.MouseMotion` (*pos, cell, motion, cellmotion*)

Fired when the mouse is moved.

cell = `None`

(x, y) position of the mouse snapped to a cell on the root console. type: (int, int)

cellmotion = `None`

(x, y) motion of the mouse moving over cells on the root console. type: (int, int)

motion = `None`

(x, y) motion of the mouse on the screen. type: (int, int)

pos = `None`

(x, y) position of the mouse on the screen. type: (int, int)

class `tdl.event.App`

Application framework.

- `ev_*`: Events are passed to methods based on their `Event.type` attribute. If an event type is ‘KEY-DOWN’ the `ev_KEYDOWN` method will be called with the event instance as a parameter.
- `key_*`: When a key is pressed another method will be called based on the `KeyEvent.key` attribute. For example the ‘ENTER’ key will call `key_ENTER` with the associated `KeyDown` event as its parameter.
- `update`: This method is called every loop. It is passed a single parameter detailing the time in seconds since the last update (often known as `deltaTime`.)

You may want to call drawing routines in this method followed by `tdl.flush`.

ev_KEYDOWN (*event*)

Override this method to handle a `KeyDown` event.

ev_KEYUP (*event*)

Override this method to handle a `KeyUp` event.

ev_MOUSEDOWN (*event*)

Override this method to handle a `MouseDown` event.

ev_MOUSEMOTION (*event*)

Override this method to handle a `MouseMotion` event.

ev_MOUSEUP (*event*)

Override this method to handle a `MouseUp` event.

ev_QUIT (*event*)

Unless overridden this method raises a `SystemExit` exception closing the program.

run ()

Delegate control over to this App instance. This function will process all events and send them to the special methods `ev_*` and `key_*`.

A call to `App.suspend` will return the control flow back to where this function is called. And then the App can be run again. But a single App instance can not be run multiple times simultaneously.

run_once ()

Pump events to this App instance and then return.

This works in the way described in `App.run` except it immediately returns after the first `update` call.

Having multiple `App` instances and selectively calling `runOnce` on them is a decent way to create a state machine.

suspend ()

When called the App will begin to return control to where `App.run` was called.

Some further events are processed and the `App.update` method will be called one last time before exiting (unless suspended during a call to `App.update`.)

update (deltaTime)

Override this method to handle per frame logic and drawing.

Parameters `deltaTime` (*float*) – This parameter tells the amount of time passed since the last call measured in seconds as a floating point number.

You can use this variable to make your program frame rate independent. Use this parameter to adjust the speed of motion, timers, and other game logic.

tdl.event.get ()

Flushes the event queue and returns the list of events.

This function returns `Event` objects that can be identified by their type attribute or their class.

Returns: `Iterator[Type[Event]]`: An iterable of Events or anything put in a `push` call.

If the iterator is deleted or otherwise interrupted before finishing the excess items are preserved for the next call.

tdl.event.wait (timeout=None, flush=True)

Wait for an event.

Parameters

- **timeout** (*Optional[int]*) – The time in seconds that this function will wait before giving up and returning None.

With the default value of None, this will block forever.

- **flush** (*bool*) – If True a call to `tdl.flush` will be made before listening for events.

Returns: `Type[Event]`: An event, or None if the function has timed out. Anything added via `push` will also be returned.

tdl.event.push (event)

Push an event into the event buffer.

Parameters `event` (*Any*) – This event will be available on the next call to `event.get`.

An event pushed in the middle of a `get` will not show until the next time `get` called preventing push related infinite loops.

This object should at least have a 'type' attribute.

`tdl.event.key_wait()`

Waits until the user presses a key. Then returns a *KeyDown* event.

Key events will repeat if held down.

A click to close the window will be converted into an Alt+F4 KeyDown event.

Returns The pressed key.

Return type *tdl.event.KeyDown*

`tdl.event.set_key_repeat (delay=500, interval=0)`

Does nothing.

`tdl.event.is_window_closed()`

Returns True if the exit button on the window has been clicked and stays True afterwards.

Returns: bool:

Rogue-like map utilities such as line-of-sight, field-of-view, and path-finding.

Deprecated since version 3.2: The features provided here are better realized in the *tcod.map* and *tcod.path* modules.

class `tdl.map.AStar` (*width*, *height*, *callback*, *diagonalCost=1.4142135623730951*, *advanced=False*)
An A* pathfinder using a callback.

Deprecated since version 3.2: See *tcod.path*.

Before crating this instance you should make one of two types of callbacks:

- A function that returns the cost to move to (x, y)
- A function that returns the cost to move between (destX, destY, sourceX, sourceY)

If path is blocked the function should return zero or None. When using the second type of callback be sure to set `advanced=True`

Parameters

- **width** (*int*) – Width of the pathfinding area (in tiles.)
- **height** (*int*) – Height of the pathfinding area (in tiles.)
- **(Union[Callable[[int, int], float], (callback) – Callable[[int, int, int, int], float]]):** A callback returning the cost of a tile or edge.

A callback taking parameters depending on the setting of ‘advanced’ and returning the cost of movement for an open tile or zero for a blocked tile.

- **diagonalCost** (*float*) – Multiplier for diagonal movement.

Can be set to zero to disable diagonal movement entirely.

- **advanced** (*bool*) – Give 2 additional parameters to the callback.

A simple callback with 2 positional parameters may not provide enough information. Setting this to True will call the callback with 2 additional parameters giving you both the destination and the source of movement.

When True the callback will need to accept (destX, destY, sourceX, sourceY) as parameters. Instead of just (destX, destY).

get_path (*origX, origY, destX, destY*)
Get the shortest path from origXY to destXY.

Returns

Returns a list walking the path from orig to dest.

This excludes the starting point and includes the destination.

If no path is found then an empty list is returned.

Return type List[Tuple[int, int]]

class `tdl.map.Map` (*width, height, order='F'*)
Field-of-view and path-finding on stored data.

Changed in version 4.1: *transparent*, *walkable*, and *fov* are now numpy boolean arrays.

Changed in version 4.3: Added *order* parameter.

Deprecated since version 3.2: *tcod.map.Map* should be used instead.

Set map conditions with the walkable and transparency attributes, this object can be iterated and checked for containment similar to consoles.

For example, you can set all tiles and transparent and walkable with the following code:

Example

```
>>> import tdl.map
>>> map_ = tdl.map.Map(80, 60)
>>> map_.transparent[:] = True
>>> map_.walkable[:] = True
```

transparent

Map transparency

Access this attribute with `map.transparent[x, y]`

Set to True to allow field-of-view rays, False will block field-of-view.

Transparent tiles only affect field-of-view.

walkable

Map accessibility

Access this attribute with `map.walkable[x, y]`

Set to True to allow path-finding through that tile, False will block passage to that tile.

Walkable tiles only affect path-finding.

fov

Map tiles touched by a field-of-view computation.

Access this attribute with `map.fov[x, y]`

Is True if a the tile is if view, otherwise False.

You can set to this attribute if you want, but you'll typically be using it to read the field-of-view of a `compute_fov` call.

compute_fov (*x*, *y*, *fov*='PERMISSIVE', *radius*=None, *light_walls*=True, *sphere*=True, *cumulative*=False)

Compute the field-of-view of this Map and return an iterator of the points touched.

Parameters

- **x** (*int*) – Point of view, x-coordinate.
- **y** (*int*) – Point of view, y-coordinate.
- **fov** (*Text*) – The type of field-of-view to be used.
Available types are: 'BASIC', 'DIAMOND', 'SHADOW', 'RESTRICTIVE', 'PERMISSIVE', 'PERMISSIVE0', 'PERMISSIVE1', ..., 'PERMISSIVE8'
- **radius** (*Optional[int]*) – Maximum view distance from the point of view.
A value of 0 will give an infinite distance.
- **light_walls** (*bool*) – Light up walls, or only the floor.
- **sphere** (*bool*) – If True the lit area will be round instead of square.
- **cumulative** (*bool*) – If True the lit cells will accumulate instead of being cleared before the computation.

Returns

An iterator of (x, y) points of tiles touched by the field-of-view.

Return type Iterator[Tuple[int, int]]

compute_path (*start_x*, *start_y*, *dest_x*, *dest_y*, *diagonal_cost*=1.4142135623730951)

Get the shortest path between two points.

Parameters

- **start_x** (*int*) – Starting x-position.
- **start_y** (*int*) – Starting y-position.
- **dest_x** (*int*) – Destination x-position.
- **dest_y** (*int*) – Destination y-position.
- **diagonal_cost** (*float*) – Multiplier for diagonal movement.
Can be set to zero to disable diagonal movement entirely.

Returns

The shortest list of points to the destination position from the starting position.

The start point is not included in this list.

Return type List[Tuple[int, int]]

`tdl.map.bresenham` (*x1*, *y1*, *x2*, *y2*)

Return a list of points in a bresenham line.

Implementation hastily copied from RogueBasin.

Returns

A list of (x, y) points, including both the start and end-points.

Return type List[Tuple[int, int]]

`tdl.map.quick_fov(x, y, callback, fov='PERMISSIVE', radius=7.5, lightWalls=True, sphere=True)`
All field-of-view functionality in one call.

Before using this call be sure to make a function, lambda, or method that takes 2 positional parameters and returns True if light can pass through the tile or False for light-blocking tiles and for indexes that are out of bounds of the dungeon.

This function is 'quick' as in no hassle but can quickly become a very slow function call if a large radius is used or the callback provided itself isn't optimized.

Always check if the index is in bounds both in the callback and in the returned values. These values can go into the negatives as well.

Parameters

- **x** (*int*) – x center of the field-of-view
- **y** (*int*) – y center of the field-of-view
- **callback** (*Callable[[int, int], bool]*) – This should be a function that takes two positional arguments x,y and returns True if the tile at that position is transparent or False if the tile blocks light or is out of bounds.
- **fov** (*Text*) – The type of field-of-view to be used.

Available types are: 'BASIC', 'DIAMOND', 'SHADOW', 'RESTRICTIVE', 'PERMISSIVE', 'PERMISSIVE0', 'PERMISSIVE1', ..., 'PERMISSIVE8'

- **radius** (*float*) – When sphere is True a floating point can be used to fine-tune the range. Otherwise the radius is just rounded up.

Be careful as a large radius has an exponential affect on how long this function takes.

- **lightWalls** (*bool*) – Include or exclude wall tiles in the field-of-view.
- **sphere** (*bool*) – True for a spherical field-of-view. False for a square one.

Returns

A set of (x, y) points that are within the field-of-view.

Return type Set[Tuple[int, int]]

This module provides advanced noise generation.

Noise is sometimes used for over-world generation, height-maps, and cloud/mist/smoke effects among other things.

You can see examples of the available noise algorithms in the libtcod documentation [here](#).

```
class tdl.noise.Noise (algorithm='PERLIN', mode='FLAT', hurst=0.5, lacunarity=2.0, octaves=4.0, seed=None, dimensions=4)
```

An advanced noise generator.

Deprecated since version 3.2: This class has been replaced by `tcod.noise.Noise`.

Parameters

- **algorithm** (*Text*) – The primary noise algorithm to be used.
Can be one of 'PERLIN', 'SIMPLEX', 'WAVELET'
 - 'PERLIN' - A popular noise generator.
 - 'SIMPLEX' - In theory this is a slightly faster generator with less noticeable directional artifacts.
 - 'WAVELET' - A noise generator designed to reduce aliasing and not lose detail when summed into a fractal (as with the 'FBM' and 'TURBULENCE' modes.) This works faster at higher dimensions.
- **mode** (*Text*) – A secondary parameter to determine how noise is generated.
Can be one of 'FLAT', 'FBM', 'TURBULENCE'
 - 'FLAT' - Generates the simplest form of noise. This mode does not use the hurst, lacunarity, and octaves parameters.
 - 'FBM' - Generates fractal brownian motion.
 - 'TURBULENCE' - Generates detailed noise with smoother and more natural transitions.
- **hurst** (*float*) – The hurst exponent.

This describes the raggedness of the resultant noise, with a higher value leading to a smoother noise. It should be in the 0.0-1.0 range.

This is only used in 'FBM' and 'TURBULENCE' modes.

- **lacunarity** (*float*) – A multiplier that determines how quickly the frequency increases for each successive octave.

The frequency of each successive octave is equal to the product of the previous octave's frequency and the lacunarity value.

This is only used in 'FBM' and 'TURBULENCE' modes.

- **octaves** (*float*) – Controls the amount of detail in the noise.

This is only used in 'FBM' and 'TURBULENCE' modes.

- **seed** (*Hashable*) – You can use any hashable object to be a seed for the noise generator.

If None is used then a random seed will be generated.

get_point (**position*)

Return the noise value of a specific position.

Example usage: `value = noise.getPoint(x, y, z)`

Parameters **position** (*Tuple[`float`, ...]*) – The point to sample at.

Returns

The noise value at position.

This will be a floating point in the 0.0-1.0 range.

Return type `float`

CHAPTER 22

Indices and tables

- `genindex`
- `modindex`
- `search`

t

tcod, ??
tcod.bsp, 43
tcod.console, 33
tcod.event, 59
tcod.image, 49
tcod.map, 41
tcod.noise, 55
tcod.path, 47
tcod.random, 53
tdl, 105
tdl.event, 117
tdl.map, 123
tdl.noise, 127

Symbols

__add__() (tcod.Color method), 69
 __bool__() (tcod.console.Console method), 34
 __contains__() (tdl.Console method), 108
 __del__() (tdl.Console method), 108
 __enter__() (tcod.console.Console method), 34
 __eq__() (tcod.Color method), 69
 __exit__() (tcod.console.Console method), 34
 __getstate__() (tcod.random.Random method), 53
 __iter__() (tdl.Console method), 108
 __mul__() (tcod.Color method), 69
 __new__() (tcod.path.NodeCostArray static method), 48
 __repr__() (tcod.Color method), 69
 __repr__() (tcod.Key method), 80
 __repr__() (tcod.Mouse method), 81
 __repr__() (tcod.console.Console method), 34
 __repr__() (tdl.event.Event method), 117
 __setstate__() (tcod.random.Random method), 53
 __str__() (tcod.bsp.BSP method), 44
 __str__() (tcod.console.Console method), 34
 __sub__() (tcod.Color method), 69

A

alt (tdl.event.KeyEvent attribute), 118
 App (class in tdl.event), 119
 AStar (class in tcod.path), 48
 AStar (class in tdl.map), 123

B

b (tcod.Color attribute), 69
 bg (tcod.console.Console attribute), 39
 blit() (tcod.console.Console method), 34
 blit() (tcod.ConsoleBuffer method), 101
 blit() (tcod.image.Image method), 49
 blit() (tdl.Console method), 108
 blit_2x() (tcod.image.Image method), 49
 blit_rect() (tcod.image.Image method), 50
 bresenham() (in module tdl.map), 125
 BSP (class in tcod.bsp), 43

bsp_contains() (in module tcod), 68
 bsp_delete() (in module tcod), 68
 bsp_father() (in module tcod), 67
 bsp_find_node() (in module tcod), 68
 bsp_is_leaf() (in module tcod), 68
 bsp_left() (in module tcod), 67
 bsp_new_with_size() (in module tcod), 67
 bsp_remove_sons() (in module tcod), 68
 bsp_resize() (in module tcod), 67
 bsp_right() (in module tcod), 67
 bsp_split_once() (in module tcod), 67
 bsp_split_recursive() (in module tcod), 67
 bsp_traverse_in_order() (in module tcod), 68
 bsp_traverse_inverted_level_order() (in module tcod), 68
 bsp_traverse_level_order() (in module tcod), 68
 bsp_traverse_post_order() (in module tcod), 68
 bsp_traverse_pre_order() (in module tcod), 68
 button (tcod.event.MouseButtonEvent attribute), 61
 button (tdl.event.MouseButtonEvent attribute), 119

C

c (tcod.Key attribute), 79
 cell (tdl.event.MouseButtonEvent attribute), 119
 cell (tdl.event.MouseMotion attribute), 119
 cellmotion (tdl.event.MouseMotion attribute), 119
 ch (tcod.console.Console attribute), 39
 char (tdl.event.KeyEvent attribute), 118
 children (tcod.bsp.BSP attribute), 44
 clear() (tcod.console.Console method), 35
 clear() (tcod.ConsoleBuffer method), 101
 clear() (tcod.image.Image method), 50
 clear() (tdl.Console method), 109
 clear() (tdl.Window method), 113
 Color (class in tcod), 68
 color_gen_map() (in module tcod), 70
 color_get_hsv() (in module tcod), 69
 color_lerp() (in module tcod), 69
 color_scale_HSV() (in module tcod), 70
 color_set_hsv() (in module tcod), 69
 compute_fov() (tcod.map.Map method), 42

compute_fov() (tdl.map.Map method), 124
 compute_path() (tdl.map.Map method), 125
 Console (class in tcod.console), 33
 Console (class in tdl), 108
 console defaults, 31
 console_blit() (in module tcod), 71
 console_c (tcod.console.Console attribute), 34
 console_check_for_keypress() (in module tcod), 71
 console_clear() (in module tcod), 72
 console_credits() (in module tcod), 72
 console_credits_render() (in module tcod), 72
 console_credits_reset() (in module tcod), 72
 console_delete() (in module tcod), 72
 console_fill_background() (in module tcod), 72
 console_fill_char() (in module tcod), 72
 console_fill_foreground() (in module tcod), 72
 console_flush() (in module tcod), 71
 console_from_file() (in module tcod), 72
 console_from_xp() (in module tcod), 73
 console_get_alignment() (in module tcod), 73
 console_get_background_flag() (in module tcod), 73
 console_get_char() (in module tcod), 73
 console_get_char_background() (in module tcod), 73
 console_get_char_foreground() (in module tcod), 73
 console_get_default_background() (in module tcod), 73
 console_get_default_foreground() (in module tcod), 73
 console_get_fade() (in module tcod), 73
 console_get_fading_color() (in module tcod), 73
 console_get_height() (in module tcod), 73
 console_get_height_rect() (in module tcod), 73
 console_get_width() (in module tcod), 74
 console_hline() (in module tcod), 74
 console_init_root() (in module tcod), 71
 console_is_fullscreen() (in module tcod), 74
 console_is_key_pressed() (in module tcod), 74
 console_is_window_closed() (in module tcod), 74
 console_list_load_xp() (in module tcod), 74
 console_list_save_xp() (in module tcod), 74
 console_load_apf() (in module tcod), 74
 console_load_asc() (in module tcod), 74
 console_load_xp() (in module tcod), 74
 console_map_ascii_code_to_font() (in module tcod), 74
 console_map_ascii_codes_to_font() (in module tcod), 75
 console_map_string_to_font() (in module tcod), 75
 console_new() (in module tcod), 75
 console_print() (in module tcod), 75
 console_print_ex() (in module tcod), 75
 console_print_frame() (in module tcod), 75
 console_print_rect() (in module tcod), 76
 console_print_rect_ex() (in module tcod), 76
 console_put_char() (in module tcod), 76
 console_put_char_ex() (in module tcod), 76
 console_rect() (in module tcod), 77
 console_save_apf() (in module tcod), 77

console_save_asc() (in module tcod), 77
 console_save_xp() (in module tcod), 77
 console_set_alignment() (in module tcod), 77
 console_set_background_flag() (in module tcod), 77
 console_set_char() (in module tcod), 77
 console_set_char_background() (in module tcod), 77
 console_set_char_foreground() (in module tcod), 78
 console_set_color_control() (in module tcod), 78
 console_set_custom_font() (in module tcod), 71
 console_set_default_background() (in module tcod), 78
 console_set_default_foreground() (in module tcod), 78
 console_set_fade() (in module tcod), 79
 console_set_fullscreen() (in module tcod), 79
 console_set_key_color() (in module tcod), 79
 console_set_window_title() (in module tcod), 79
 console_vline() (in module tcod), 79
 console_wait_for_keypress() (in module tcod), 79
 ConsoleBuffer (class in tcod), 101
 contains() (tcod.bsp.BSP method), 44
 control (tdl.event.KeyEvent attribute), 118
 copy() (tcod.ConsoleBuffer method), 102
 cx (tcod.Mouse attribute), 80
 cy (tcod.Mouse attribute), 80

D

dcx (tcod.Mouse attribute), 80
 dcy (tcod.Mouse attribute), 80
 default_alignment (tcod.console.Console attribute), 39
 default_bg (tcod.console.Console attribute), 39
 default_bg_blend (tcod.console.Console attribute), 39
 default_fg (tcod.console.Console attribute), 39
 Dice (class in tcod), 103
 Dijkstra (class in tcod.path), 48
 dijkstra_compute() (in module tcod), 84
 dijkstra_delete() (in module tcod), 84
 dijkstra_get() (in module tcod), 84
 dijkstra_get_distance() (in module tcod), 84
 dijkstra_is_empty() (in module tcod), 84
 dijkstra_new() (in module tcod), 84
 dijkstra_new_using_function() (in module tcod), 84
 dijkstra_path_set() (in module tcod), 84
 dijkstra_path_walk() (in module tcod), 84
 dijkstra_reverse() (in module tcod), 84
 dijkstra_size() (in module tcod), 84
 dispatch() (tcod.event.EventDispatch method), 63
 draw_char() (tdl.Console method), 109
 draw_char() (tdl.Window method), 114
 draw_frame() (tcod.console.Console method), 35
 draw_frame() (tdl.Console method), 109
 draw_frame() (tdl.Window method), 114
 draw_rect() (tcod.console.Console method), 35
 draw_rect() (tdl.Console method), 110
 draw_rect() (tdl.Window method), 114
 draw_str() (tdl.Console method), 110

DTYPE (tcod.console.Console attribute), 34
 dx (tcod.Mouse attribute), 80
 dy (tcod.Mouse attribute), 80

E

EdgeCostCallback (class in tcod.path), 48
 ev_keydown() (tcod.event.EventDispatch method), 63
 ev_KEYDOWN() (tdl.event.App method), 119
 ev_keyup() (tcod.event.EventDispatch method), 63
 ev_KEYUP() (tdl.event.App method), 119
 ev_mousebuttondown() (tcod.event.EventDispatch method), 63
 ev_mousebuttonup() (tcod.event.EventDispatch method), 63
 ev_MOUSEDOWN() (tdl.event.App method), 119
 ev_mousemotion() (tcod.event.EventDispatch method), 63
 ev_MOUSEMOTION() (tdl.event.App method), 119
 ev_MOUSEUP() (tdl.event.App method), 119
 ev_mousewheel() (tcod.event.EventDispatch method), 63
 ev_quit() (tcod.event.EventDispatch method), 63
 ev_QUIT() (tdl.event.App method), 119
 ev_textinput() (tcod.event.EventDispatch method), 63
 ev_windowclose() (tcod.event.EventDispatch method), 63
 ev_windowenter() (tcod.event.EventDispatch method), 63
 ev_windowexposed() (tcod.event.EventDispatch method), 63
 ev_windowfocusgained() (tcod.event.EventDispatch method), 63
 ev_windowfocuslost() (tcod.event.EventDispatch method), 63
 ev_windowhidden() (tcod.event.EventDispatch method), 63
 ev_windowleave() (tcod.event.EventDispatch method), 63
 ev_windowmaximized() (tcod.event.EventDispatch method), 64
 ev_windowminimized() (tcod.event.EventDispatch method), 64
 ev_windowmoved() (tcod.event.EventDispatch method), 64
 ev_windowresized() (tcod.event.EventDispatch method), 64
 ev_windowrestored() (tcod.event.EventDispatch method), 64
 ev_windowshown() (tcod.event.EventDispatch method), 64
 ev_windowsizechanged() (tcod.event.EventDispatch method), 64
 Event (class in tcod.event), 59
 Event (class in tdl.event), 117
 EventDispatch (class in tcod.event), 62

F

fg (tcod.console.Console attribute), 39
 find_node() (tcod.bsp.BSP method), 44
 flipped (tcod.event.MouseWheel attribute), 61
 flush() (in module tdl), 107
 force_resolution() (in module tdl), 108
 fov (tcod.map.Map attribute), 42
 fov (tdl.map.Map attribute), 124
 from_sdl_event() (tcod.event.Event class method), 59
 from_sdl_event() (tcod.event.KeyboardEvent class method), 60
 from_sdl_event() (tcod.event.MouseButtonEvent class method), 61
 from_sdl_event() (tcod.event.MouseMotion class method), 60
 from_sdl_event() (tcod.event.MouseWheel class method), 61
 from_sdl_event() (tcod.event.Quit class method), 60
 from_sdl_event() (tcod.event.TextInput class method), 61
 from_sdl_event() (tcod.event.Undefined class method), 62
 from_sdl_event() (tcod.event.WindowEvent class method), 62

G

g (tcod.Color attribute), 69
 get() (in module tcod.event), 64
 get() (in module tdl.event), 120
 get_alpha() (tcod.image.Image method), 50
 get_char() (tdl.Console method), 111
 get_char() (tdl.Window method), 115
 get_cursor() (tdl.Console method), 111
 get_fps() (in module tdl), 107
 get_fullscreen() (in module tdl), 107
 get_height_rect() (tcod.console.Console method), 36
 get_mipmap_pixel() (tcod.image.Image method), 50
 get_path() (tcod.path.AStar method), 48
 get_path() (tcod.path.Dijkstra method), 48
 get_path() (tdl.map.AStar method), 124
 get_pixel() (tcod.image.Image method), 50
 get_point() (tcod.noise.Noise method), 56
 get_point() (tdl.noise.Noise method), 128
 get_size() (tdl.Console method), 111
 guass() (tcod.random.Random method), 53

H

height (tcod.bsp.BSP attribute), 43
 height (tcod.console.Console attribute), 40
 height (tcod.event.WindowResized attribute), 62
 height (tcod.image.Image attribute), 49
 height (tcod.map.Map attribute), 42
 heightmap_add() (in module tcod), 86
 heightmap_add_fbm() (in module tcod), 86

heightmap_add_hill() (in module tcod), 87
 heightmap_add_hm() (in module tcod), 87
 heightmap_add_voronoi() (in module tcod), 87
 heightmap_clamp() (in module tcod), 87
 heightmap_clear() (in module tcod), 87
 heightmap_copy() (in module tcod), 88
 heightmap_count_cells() (in module tcod), 88
 heightmap_delete() (in module tcod), 88
 heightmap_dig_bezier() (in module tcod), 88
 heightmap_dig_hill() (in module tcod), 88
 heightmap_get_interpolated_value() (in module tcod), 89
 heightmap_get_minmax() (in module tcod), 89
 heightmap_get_normal() (in module tcod), 89
 heightmap_get_slope() (in module tcod), 89
 heightmap_get_value() (in module tcod), 90
 heightmap_has_land_on_border() (in module tcod), 90
 heightmap_kernel_transform() (in module tcod), 90
 heightmap_lerp_hm() (in module tcod), 91
 heightmap_multiply_hm() (in module tcod), 91
 heightmap_new() (in module tcod), 91
 heightmap_normalize() (in module tcod), 91
 heightmap_rain_erosion() (in module tcod), 91
 heightmap_scale() (in module tcod), 92
 heightmap_scale_fbm() (in module tcod), 92
 heightmap_set_value() (in module tcod), 92
 hflip() (tcod.image.Image method), 51
 hline() (tcod.console.Console method), 36
 horizontal (tcod.bsp.BSP attribute), 44

I

Image (class in tcod.image), 49
 image_blit() (in module tcod), 93
 image_blit_2x() (in module tcod), 93
 image_blit_rect() (in module tcod), 93
 image_clear() (in module tcod), 93
 image_delete() (in module tcod), 93
 image_from_console() (in module tcod), 93
 image_get_alpha() (in module tcod), 93
 image_get_mipmap_pixel() (in module tcod), 93
 image_get_pixel() (in module tcod), 93
 image_get_size() (in module tcod), 93
 image_hflip() (in module tcod), 93
 image_invert() (in module tcod), 93
 image_is_pixel_transparent() (in module tcod), 93
 image_load() (in module tcod), 92
 image_new() (in module tcod), 93
 image_put_pixel() (in module tcod), 93
 image_refresh_console() (in module tcod), 93
 image_rotate90() (in module tcod), 93
 image_save() (in module tcod), 93
 image_scale() (in module tcod), 93
 image_set_key_color() (in module tcod), 93
 image_vflip() (in module tcod), 93
 in_order() (tcod.bsp.BSP method), 44

init() (in module tdl), 106
 inverse_guass() (tcod.random.Random method), 53
 invert() (tcod.image.Image method), 51
 inverted_level_order() (tcod.bsp.BSP method), 44
 is_window_closed() (in module tdl.event), 121

K

Key (class in tcod), 79
 key (tdl.event.KeyEvent attribute), 118
 key_wait() (in module tdl.event), 120
 KeyboardEvent (class in tcod.event), 60
 keychar (tdl.event.KeyEvent attribute), 118
 KeyDown (class in tcod.event), 60
 KeyDown (class in tdl.event), 118
 KeyEvent (class in tdl.event), 118
 KeyUp (class in tcod.event), 60
 KeyUp (class in tdl.event), 118

L

lalt (tcod.Key attribute), 79
 lbutton (tcod.Mouse attribute), 80
 lbutton_pressed (tcod.Mouse attribute), 80
 lctrl (tcod.Key attribute), 79
 left_alt (tdl.event.KeyEvent attribute), 118
 left_control (tdl.event.KeyEvent attribute), 118
 level (tcod.bsp.BSP attribute), 44
 level_order() (tcod.bsp.BSP method), 44
 libtcod-ffi, **31**
 libtcodpy, **31**
 line() (in module tcod), 94
 line_init() (in module tcod), 93
 line_iter() (in module tcod), 94
 line_step() (in module tcod), 94
 line_where() (in module tcod), 94
 lmeta (tcod.Key attribute), 79

M

Map (class in tcod.map), 41
 Map (class in tdl.map), 124
 map_clear() (in module tcod), 95
 map_compute_fov() (in module tcod), 95
 map_copy() (in module tcod), 95
 map_delete() (in module tcod), 95
 map_get_height() (in module tcod), 95
 map_get_width() (in module tcod), 95
 map_is_in_fov() (in module tcod), 95
 map_is_transparent() (in module tcod), 96
 map_is_walkable() (in module tcod), 96
 map_new() (in module tcod), 96
 map_set_properties() (in module tcod), 96
 mbutton (tcod.Mouse attribute), 80
 mbutton_pressed (tcod.Mouse attribute), 80
 mod (tcod.event.KeyboardEvent attribute), 60
 motion (tdl.event.MouseMotion attribute), 119

Mouse (class in tcod), 80
 mouse_get_status() (in module tcod), 96
 mouse_is_cursor_visible() (in module tcod), 96
 mouse_move() (in module tcod), 96
 mouse_show_cursor() (in module tcod), 96
 MouseButtonDown (class in tcod.event), 61
 MouseButtonEvent (class in tcod.event), 61
 MouseButtonEvent (class in tdl.event), 118
 MouseButtonUp (class in tcod.event), 61
 MouseDown (class in tdl.event), 119
 MouseMotion (class in tcod.event), 60
 MouseMotion (class in tdl.event), 119
 MouseUp (class in tdl.event), 119
 MouseWheel (class in tcod.event), 61
 move() (tdl.Console method), 112

N

namegen_destroy() (in module tcod), 96
 namegen_generate() (in module tcod), 96
 namegen_generate_custom() (in module tcod), 97
 namegen_get_sets() (in module tcod), 97
 namegen_parse() (in module tcod), 97
 NodeCostArray (class in tcod.path), 48
 Noise (class in tcod.noise), 55
 Noise (class in tdl.noise), 127
 noise_c (tcod.noise.Noise attribute), 56
 noise_delete() (in module tcod), 97
 noise_get() (in module tcod), 97
 noise_get_fbm() (in module tcod), 97
 noise_get_turbulence() (in module tcod), 97
 noise_new() (in module tcod), 97
 noise_set_type() (in module tcod), 98

P

parent (tcod.bsp.BSP attribute), 44
 parser_delete() (in module tcod), 98
 parser_get_bool_property() (in module tcod), 98
 parser_get_char_property() (in module tcod), 98
 parser_get_color_property() (in module tcod), 98
 parser_get_dice_property() (in module tcod), 98
 parser_get_float_property() (in module tcod), 98
 parser_get_int_property() (in module tcod), 98
 parser_get_list_property() (in module tcod), 98
 parser_get_string_property() (in module tcod), 98
 parser_new() (in module tcod), 98
 parser_new_struct() (in module tcod), 98
 parser_run() (in module tcod), 98
 path_compute() (in module tcod), 84
 path_delete() (in module tcod), 84
 path_get() (in module tcod), 84
 path_get_destination() (in module tcod), 85
 path_get_origin() (in module tcod), 85
 path_is_empty() (in module tcod), 85
 path_new_using_function() (in module tcod), 85

path_new_using_map() (in module tcod), 85
 path_reverse() (in module tcod), 85
 path_size() (in module tcod), 86
 path_walk() (in module tcod), 86
 pixel (tcod.event.MouseButtonEvent attribute), 61
 pixel (tcod.event.MouseMotion attribute), 60
 pixel_motion (tcod.event.MouseMotion attribute), 60
 Point (class in tcod.event), 59
 pos (tdl.event.MouseButtonEvent attribute), 119
 pos (tdl.event.MouseMotion attribute), 119
 position (tcod.bsp.BSP attribute), 44
 post_order() (tcod.bsp.BSP method), 45
 pre_order() (tcod.bsp.BSP method), 45
 pressed (tcod.Key attribute), 79
 print() (tcod.console.Console method), 36
 print_() (tcod.console.Console method), 37
 print_box() (tcod.console.Console method), 37
 print_frame() (tcod.console.Console method), 37
 print_rect() (tcod.console.Console method), 38
 print_str() (tdl.Console method), 112
 push() (in module tdl.event), 120
 put_char() (tcod.console.Console method), 38
 put_pixel() (tcod.image.Image method), 51
 python-tcod, 31
 python-tdl, 31

Q

quick_fov() (in module tdl.map), 125
 Quit (class in tcod.event), 59
 Quit (class in tdl.event), 117

R

r (tcod.Color attribute), 69
 ralt (tcod.Key attribute), 79
 randint() (tcod.random.Random method), 54
 Random (class in tcod.random), 53
 random_c (tcod.random.Random attribute), 53
 random_delete() (in module tcod), 98
 random_get_double() (in module tcod), 98
 random_get_double_mean() (in module tcod), 99
 random_get_float() (in module tcod), 99
 random_get_float_mean() (in module tcod), 99
 random_get_instance() (in module tcod), 99
 random_get_int() (in module tcod), 99
 random_get_int_mean() (in module tcod), 100
 random_new() (in module tcod), 100
 random_new_from_seed() (in module tcod), 100
 random_restore() (in module tcod), 100
 random_save() (in module tcod), 100
 random_set_distribution() (in module tcod), 100
 rbutton (tcod.Mouse attribute), 80
 rbutton_pressed (tcod.Mouse attribute), 80
 rctrl (tcod.Key attribute), 80
 rect() (tcod.console.Console method), 38

refresh_console() (tcod.image.Image method), 51
 repeat (tcod.event.KeyboardEvent attribute), 60
 right_alt (tdl.event.KeyEvent attribute), 118
 right_control (tdl.event.KeyEvent attribute), 118
 rmeta (tcod.Key attribute), 80
 rotate90() (tcod.image.Image method), 51
 run() (tdl.event.App method), 119
 run_once() (tdl.event.App method), 120

S

sample_mgrid() (tcod.noise.Noise method), 56
 sample_ogrid() (tcod.noise.Noise method), 56
 save_as() (tcod.image.Image method), 51
 scale() (tcod.image.Image method), 51
 scancode (tcod.event.KeyboardEvent attribute), 60
 screenshot() (in module tdl), 107
 scroll() (tdl.Console method), 112
 sdl_event (tcod.event.Event attribute), 59
 set() (tcod.ConsoleBuffer method), 102
 set_back() (tcod.ConsoleBuffer method), 102
 set_colors() (tdl.Console method), 112
 set_font() (in module tdl), 106
 set_fore() (tcod.ConsoleBuffer method), 102
 set_fps() (in module tdl), 107
 set_fullscreen() (in module tdl), 107
 set_goal() (tcod.path.Dijkstra method), 48
 set_key_color() (tcod.console.Console method), 39
 set_key_color() (tcod.image.Image method), 51
 set_key_repeat() (in module tdl.event), 121
 set_mode() (tdl.Console method), 112
 set_title() (in module tdl), 107
 shift (tcod.Key attribute), 80
 shift (tdl.event.KeyEvent attribute), 118
 split_once() (tcod.bsp.BSP method), 45
 split_recursive() (tcod.bsp.BSP method), 45
 state (tcod.event.MouseMotion attribute), 60
 struct_add_flag() (in module tcod), 101
 struct_add_list_property() (in module tcod), 101
 struct_add_property() (in module tcod), 101
 struct_add_structure() (in module tcod), 101
 struct_add_value_list() (in module tcod), 101
 struct_get_name() (in module tcod), 101
 struct_get_type() (in module tcod), 101
 struct_is_mandatory() (in module tcod), 101
 suspend() (tdl.event.App method), 120
 sym (tcod.event.KeyboardEvent attribute), 60
 sys_check_for_event() (in module tcod), 83
 sys_elapsed_milli() (in module tcod), 82
 sys_elapsed_seconds() (in module tcod), 82
 sys_force_fullscreen_resolution() (in module tcod), 82
 sys_get_char_size() (in module tcod), 83
 sys_get_current_resolution() (in module tcod), 82
 sys_get_fps() (in module tcod), 81
 sys_get_last_frame_length() (in module tcod), 81

sys_get_renderer() (in module tcod), 82
 sys_register_SDL_renderer() (in module tcod), 83
 sys_save_screenshot() (in module tcod), 82
 sys_set_fps() (in module tcod), 81
 sys_set_renderer() (in module tcod), 82
 sys_sleep_milli() (in module tcod), 82
 sys_update_char() (in module tcod), 83
 sys_wait_for_event() (in module tcod), 83

T

tcod (module), 1
 tcod.bsp (module), 43
 tcod.COLCTRL_1 (built-in variable), 70
 tcod.COLCTRL_2 (built-in variable), 70
 tcod.COLCTRL_3 (built-in variable), 70
 tcod.COLCTRL_4 (built-in variable), 70
 tcod.COLCTRL_5 (built-in variable), 70
 tcod.COLCTRL_BACK_RGB (built-in variable), 71
 tcod.COLCTRL_FORE_RGB (built-in variable), 70
 tcod.COLCTRL_STOP (built-in variable), 70
 tcod.console (module), 33
 tcod.event (module), 59
 tcod.EVENT_ANY (built-in variable), 81
 tcod.EVENT_FINGER (built-in variable), 81
 tcod.EVENT_FINGER_MOVE (built-in variable), 81
 tcod.EVENT_FINGER_PRESS (built-in variable), 81
 tcod.EVENT_FINGER_RELEASE (built-in variable), 81
 tcod.EVENT_KEY (built-in variable), 81
 tcod.EVENT_KEY_PRESS (built-in variable), 81
 tcod.EVENT_KEY_RELEASE (built-in variable), 81
 tcod.EVENT_MOUSE (built-in variable), 81
 tcod.EVENT_MOUSE_MOVE (built-in variable), 81
 tcod.EVENT_MOUSE_PRESS (built-in variable), 81
 tcod.EVENT_MOUSE_RELEASE (built-in variable), 81
 tcod.EVENT_NONE (built-in variable), 81
 tcod.image (module), 49
 tcod.map (module), 41
 tcod.noise (module), 55
 tcod.path (module), 47
 tcod.random (module), 53
 tdl (module), 105
 tdl.event (module), 117
 tdl.map (module), 123
 tdl.noise (module), 127
 TDLError, 108
 text (tcod.event.TextInput attribute), 61
 text (tcod.Key attribute), 79
 TextInput (class in tcod.event), 61
 tile (tcod.event.MouseButtonEvent attribute), 61
 tile (tcod.event.MouseMotion attribute), 60
 tile_motion (tcod.event.MouseMotion attribute), 60
 transparent (tcod.map.Map attribute), 42
 transparent (tdl.map.Map attribute), 124
 type (tcod.event.Event attribute), 59

type (tcod.event.KeyboardEvent attribute), 60
 type (tcod.event.MouseButtonEvent attribute), 61
 type (tcod.event.MouseMotion attribute), 60
 type (tcod.event.MouseWheel attribute), 61
 type (tcod.event.Quit attribute), 59
 type (tcod.event.TextInput attribute), 61
 type (tcod.event.WindowEvent attribute), 62
 type (tcod.event.WindowMoved attribute), 62
 type (tcod.event.WindowResized attribute), 62
 type (tdl.event.Event attribute), 117

U

Undefined (class in tcod.event), 62
 uniform() (tcod.random.Random method), 54
 update() (tdl.event.App method), 120

V

vflip() (tcod.image.Image method), 51
 vk (tcod.Key attribute), 79
 vline() (tcod.console.Console method), 39

W

wait() (in module tcod.event), 64
 wait() (in module tdl.event), 120
 walk() (tcod.bsp.BSP method), 45
 walkable (tcod.map.Map attribute), 42
 walkable (tdl.map.Map attribute), 124
 wheel_down (tcod.Mouse attribute), 80
 wheel_up (tcod.Mouse attribute), 80
 width (tcod.bsp.BSP attribute), 43
 width (tcod.console.Console attribute), 40
 width (tcod.event.WindowResized attribute), 62
 width (tcod.image.Image attribute), 49
 width (tcod.map.Map attribute), 42
 Window (class in tdl), 113
 WindowEvent (class in tcod.event), 62
 WindowMoved (class in tcod.event), 62
 WindowResized (class in tcod.event), 62
 write() (tdl.Console method), 113

X

x (tcod.bsp.BSP attribute), 43
 x (tcod.event.MouseWheel attribute), 61
 x (tcod.event.Point attribute), 59
 x (tcod.event.WindowMoved attribute), 62
 x (tcod.Mouse attribute), 80

Y

y (tcod.bsp.BSP attribute), 43
 y (tcod.event.MouseWheel attribute), 61
 y (tcod.event.Point attribute), 59
 y (tcod.Mouse attribute), 80