
retdec-python Documentation

Release 0.5.1

Petr Zemek and contributors

May 20, 2017

Contents

1	Contents	3
1.1	Quickstart	3
1.2	Library	4
1.3	Scripts	8
1.4	Contributing	11
1.5	Status	11
2	Indices	15

retdec-python is a Python library and tools providing easy access to the retdec.com decompilation service through their public [REST API](#).

Quickstart

This page gives an overview of the library and tools to get you started.

Requirements

- Python \geq 3.3 or PyPy3 \geq 2.4
- `requests` module for making HTTPS calls to the retdec.com API

Installation

The recommended way of installing is from [Python Package Index \(PyPI\)](https://pypi.org/) with `pip`:

```
$ pip install retdec-python
```

This will install the latest stable version, including all dependencies. You can also install the latest development version directly from [GitHub](https://github.com):

```
$ pip install git+https://github.com/s3rvac/retdec-python
```

Prerequisites

To be able to actually use the library and scripts, you need to [register](https://retdec.com) at retdec.com. After that, [log in](#) and click on [Account](#). There, you will find your API key, which is used for authentication.

Attention: Be careful not to disclose your API key to anyone! You have to keep it a secret.

Library vs Scripts

retdec-python provides both a Python library and scripts. You can either incorporate the library in your own scripts:

```
from retdec.decompiler import Decompiler

decompiler = Decompiler(api_key='YOUR-API-KEY')
decompilation = decompiler.start_decompilation(input_file='file.exe')
decompilation.wait_until_finished()
decompilation.save_hll_code()
```

or you can use the provided scripts for stand-alone file analyses or decompilations:

```
$ decompiler -k YOUR-API-KEY file.exe
v23bmYb67R
-----
Waiting for resources (0%)... [OK]
Pre-Processing:
  Obtaining file information (5%)... [OK]
  Unpacking (10%)... [OK]
Front-End:
  Initializing (20%)... [OK]
[..]
Done (100%)...

Downloading:
- file.c
```

Either way, `file.c` then contains the decompiled C code:

```
$ cat file.c
//
// This file was generated by the Retargetable Decompiler
// Website: https://retdec.com
// Copyright (c) 2016 Retargetable Decompiler <info@retdec.com>
//
#include <stdio.h>
[..]
```

The library provides support for the [decompilation](#), [fileinfo](#), and [test](#) services. For a more detailed list, see the [status](#) page.

Next, we describe the library in a greater detail. If you wish to learn more about the provided scripts, continue [here](#) instead.

Library

This page describes the `retdec-python` library and its API.

Organization

The base package is `retdec`. Everything that the library provides is inside this package.

Authentication

The library needs to authenticate you to retdec.com. To specify your API key, either pass it as a parameter when creating a resource:

```
decompiler = retdec.decompiler.Decompiler(api_key='YOUR-API-KEY')
```

or set the `RETDEC_API_KEY` environment variable:

```
$ export RETDEC_API_KEY=YOUR-API-KEY
```

An advantage of the environment variable is that you do not need to specify the API key every time you use the library:

```
decompiler = retdec.decompiler.Decompiler()
```

Error Handling

The library uses exceptions to signalize errors. The base class is `retdec.exceptions.RetdecError`, which you can use to catch all custom exceptions raised by the library:

```
try:
    # ...
except retdec.exceptions.RetdecError as ex:
    # Handle the error.
```

You can also catch specific exceptions, e.g. `retdec.exceptions.AuthenticationError`, and react on them. See the `retdec.exceptions` module for a list of all custom exceptions.

Decompiler

The `retdec.decompiler` module provides access to the [decompilation service](#). It allows you to decompile binary files into a high-level language representation, such as C.

Creating a Decompiler

The decompiler is represented by the `retdec.decompiler.Decompiler` class:

```
decompiler = retdec.decompiler.Decompiler(api_key='YOUR-API-KEY')
```

Starting a Decompilation

To start a decompilation of a file, call `start_decompilation()` on the created decompiler:

```
decompilation = decompiler.start_decompilation(input_file=FILE)
```

`FILE` is either a path to the file or a file-like object. For a complete list of parameters that you can use when starting a decompilation, see the description of `start_decompilation()`.

The returned object is an instance of `retdec.decompilation.Decompilation`.

Waiting For the Decompileation To Finish

After the `start_decompilation()` call above returns, the decompilation has been automatically started. To wait until it finishes, call `wait_until_finished()`:

```
decompilation.wait_until_finished()
```

If you want to track the decompilation progress (e.g. by showing a progress bar or displaying the log), you can pass a callback function to `wait_until_finished()`:

```
def show_progress(decompilation):
    print(decompilation.get_completion())

decompilation.wait_until_finished(
    callback=show_progress
)
```

When the status of the decompilation changes (e.g. it moves to another phase), the callback is automatically called with the decompilation being passed as its parameter.

Downloading Outputs

To obtain the generated high-level language (HLL) code as a string, call `get_hll_code()`:

```
print(decompilation.get_hll_code())
```

Alternatively, you can call `save_hll_code()`, which obtains and saves the generated HLL code into the given directory:

```
decompilation.save_hll_code('/home/user/downloads')
```

Apart from obtaining the HLL code, you can also get the disassembled code, control-flow graphs, call graph, archive with all the outputs or, in the `c` mode, the compiled version of the input C file. See the description of `Decompilation` for more details.

For a complete example, take a look the `retdec/tools/decompiler.py` file. It is an implementation of the *Decompiler* script.

Fileinfo

The `retdec.fileinfo` module provides access to the `file-analyzing service`. It allows you to obtain information about binary files.

Creating an Analyzer

The analyzer is represented by the `retdec.fileinfo.Fileinfo` class:

```
fileinfo = retdec.fileinfo.Fileinfo(api_key='YOUR-API-KEY')
```

Starting an Analysis

To start an analysis of a file, call `start_analysis()` on the created analyzer with a file to be analyzed:

```
analysis = fileinfo.start_analysis(input_file=FILE)
```

FILE is either a path to the file or a file-like object. Optionally, you can pass the following parameters:

- `verbose=True` – makes the analysis obtain all available information about the file.
- `output_format=json` – causes the output from the analysis to be in the **JSON** format instead of in the plain format.

The returned object is an instance of `retdec.analysis.Analysis`.

Waiting For the Analysis To Finish

After the `start_analysis()` call above returns, the analysis has been automatically started. To wait until it finishes, call `wait_until_finished()`:

```
analysis.wait_until_finished()
```

Obtaining the Results of the Analysis

To obtain the output from the analysis, call `get_output()`:

```
print(analysis.get_output())
```

For a complete example, take a look at the `retdec/tools/fileinfo.py` file. It is an implementation of the *Fileinfo* script.

Test

Access to the `testing service` is provided by the `retdec.test` module.

Authentication

To check whether you can authenticate successfully, use `retdec.test.Test.auth()`:

```
test = retdec.test.Test(api_key='YOUR-API-KEY')
try:
    test.auth()
    print('authentication succeeded')
except retdec.exceptions.AuthenticationError as ex:
    print('authentication failed:', ex)
```

Parameter Passing

To check that parameters are passed correctly when performing requests to the `retdec.com API`, use `retdec.test.Test.echo()`:

```
test = retdec.test.Test(api_key='YOUR-API-KEY')
result = test.echo(param='value')
print(result) # Prints {'param': 'value'}.
```

Scripts

This page describes the `retdec-python` scripts and their usage.

Currently, there are two scripts: `decompiler` and `fileinfo`. They provide access to the [decompilation](#) and [file-analyzing](#) services, respectively.

Authentication

The scripts need to authenticate you to [retdec.com](#). To specify your API key, either use the `-k KEY` or `--api-key KEY` parameter:

```
$ decompiler -k YOUR-API-KEY file.exe
```

or set the `RETDEC_API_KEY` environment variable:

```
$ export RETDEC_API_KEY=YOUR-API-KEY
$ decompiler file.exe
```

An advantage of the environment variable is that you do not have to specify the API key every time you run a script.

Decompiler

The `decompiler` script provides access to the [decompilation service](#). It allows you to decompile binary files into a high-level language representation, such as C.

Usage

```
$ decompiler [OPTIONS] FILE
```

Output files are stored into the same directory where the input file is located. For example, if the input file is `dir/prog.exe`, then the decompiled code in the C language is saved as `dir/prog.c`. You can override the output directory by using the `-o/--output-dir` parameter.

Options

See the [official documentation](#) for more details.

- `-a ARCH, --architecture ARCH` – Architecture to force when (de)compiling. Supported architectures: `x86, arm, thumb, mips, pic32, powerpc`.
- `-b, --brief` – Print fewer information during the decompilation.
- `-c COMPILER, --compiler COMPILER` – Compiler to use when compiling input C source files. Supported compilers: `gcc, clang`.
- `-C LEVEL, --compiler-optimizations LEVEL` – Optimization level to use when compiling input C source files. Supported levels: `O0, O1, O2, O3`.
- `--endian` – Endianness of the machine code (`bin` and `raw` modes only). Supported endians: `little, big`.
- `-f FORMAT, --file-format FORMAT` – File format to force when compiling input C source files. Supported formats: `elf, pe`.

- `-g, --compiler-debug` – Compile the input C file with debugging information (i.e. passes the `-g` flag to the used compiler).
- `-s, --compiler-strip` – Strip the compiled C file prior its decompilation.
- `-k KEY, --api-key KEY` – Specifies the API key to be used.
- `-l LANGUAGE, --target-language LANGUAGE` – Target high-level language. Supported languages: `c`, `py`.
- `--graph-format FORMAT` – Format of the generated call and control-flow graphs. Supported formats: `png`, `svg`, `pdf`.
- `-m MODE, --mode MODE` – Decompilation mode. **Supported modes:** `bin`, `c`, and `raw`. By default, the script performs an automatic detection based on the extension of the input file.
- `-o DIR, --output-dir DIR` – Save the outputs into this directory.
- `-p FILE, --pdb-file` – PDB file associated with the input file.
- `-q, --quiet` – Print only errors, nothing else (not even progress).
- `-V, --version` – Print the script and library version.
- `--var-names STYLE` – Naming style for variables. **Supported styles:** `readable`, `address`, `hungarian`, `simple`, and `unified`.
- `-O LEVEL, --optimizations LEVEL` – Level of optimizations performed by the decompiler. **Supported levels:** `none`, `limited`, `normal`, and `aggressive`.
- `-K, --keep-unreach-funcs` – Decompile all functions, even if they are not reachable.
- `--only-funcs` – Decompile only the given functions (a comma-separated list of function names, e.g. `func1, func2`).
- `--only-ranges '` – Decompile only the given address ranges (a comma-separated list of address ranges, e.g. `0x100-0x200, 0x500-0x600`).
- `--decoding` – What should be decoded in a selective decompilation? **Supported types:** `everything`, `only`.
- `--no-addresses` – Disable the emission of addresses in comments in the generated code.
- `--raw-entry-point` – Virtual memory address where execution flow should start in the machine code (`raw mode only`).
- `--raw-section-vma` – Address where the section created from the machine code will be placed in virtual memory (`raw mode only`).
- `--ar-index` – Index of the object file in the input archive to be decompiled when decompiling an archive.
- `--ar-name` – Name of the object file in the input archive to be decompiled when decompiling an archive.
- `--with-cg` – Generate a call graph when the decompilation ends.
- `--with-cfgs` – Generate call graphs for all functions when the decompilation ends.
- `--with-archive` – Generate an archive containing all decompilation outputs when the decompilation ends.

Example

```
$ decompiler -k YOUR-API-KEY file.exe
v23bmYb67R
```

```
-----  
Waiting for resources (0%)... [OK]  
Pre-Processing:  
  Obtaining file information (5%)... [OK]  
  Unpacking (10%)... [OK]  
Front-End:  
  Initializing (20%)... [OK]  
[...]  
Done (100%)...  
  
Downloading:  
- file.c
```

`file.c` then contains the decompiled C code.

Fileinfo

The `fileinfo` script provides access to the [file-analyzing service](#). It allows you to obtain information about binary files.

Usage

```
$ fileinfo [OPTIONS] FILE
```

Options

- `-k KEY`, `--api-key KEY` – Specifies the API key to be used.
- `-f FORMAT`, `--output-format` – Format in which the output should be printed. Available formats are `plain` (plain text; the default) and `json` (JSON).
- `-v`, `--verbose` – Print all available information about the file.
- `-V`, `--version` – Print the script and library version.

Example

```
$ fileinfo -k YOUR-API-KEY file.exe  
  
Input file           : file.exe  
File format         : PE  
File class          : 32-bit  
File type           : Executable file  
Architecture        : x86 (or later and compatible)  
Endianness          : Little endian  
Entry point address  : 0x4014e0  
Entry point offset   : 0x8e0  
Entry point section name : .text  
Entry point section index: 0  
Bytes on entry point  : 31ed5e89e183e4f05054526860c1040868f0c00408515668  
Detected compiler/packer : GCC (x86_64-unknown-linux-gnu) (4.7.2) (100%)
```

Contributing

Any contributions are welcomed! I will be very glad to get your feedback, [pull requests](#), [issues](#), or just a simple *Thanks*. Feel free to contact me for any questions you might have!

Coding Style

The code should be [PEP8](#) compliant, except for line length, which may be greater than 79 when suitable (but never exceeding 100 characters).

Testing

The code is 100% covered with unit tests. When you make a pull request, please include unit tests for your code to keep the coverage at 100%.

Make Targets

- Project documentation can be generated by running `make docs` (you need to have [sphinx](#) and [sphinx_rtd_theme](#) installed).
- To run unit tests, execute `make tests` (you need to have [nose](#) installed).
- Test coverage can be generated by executing `make tests-coverage` (once again, you need to have [nose](#) installed).
- To ensure that the code complies to [PEP8](#), execute `make lint` (you need to have [flake8](#) installed).

See the contents of [Makefile](#) to for all the possible targets.

Status

A summary of the supported parts of the [retdec.com API](#).

Decompiler

The decompilation service.

- [Starting a new decompilation](#)
- [Decompilation modes](#)
 - `bin`
 - `c`
 - `raw`
- [Input files](#)
 - `input`
 - `pdb`
- [Decompilation parameters](#)

- Mode-independent parameters
 - * target_language
 - * graph_format
 - * decomp_var_names
 - * decomp_optimizations
 - * decomp_unreach_funcs
 - * decomp_emit_addresses
 - * generate_cg
 - * generate_cfgs
 - * generate_archive
- Parameters for the bin mode
 - * architecture
 - * endian
 - * sel_decomp_funcs
 - * sel_decomp_ranges
 - * sel_decomp_decoding
 - * ar_index
 - * ar_name
- Parameters for the raw mode
 - * architecture
 - * endian
 - * raw_entry_point
 - * raw_section_vma
- Parameters for the c mode
 - * architecture
 - * file_format
 - * comp_compiler
 - * comp_optimizations
 - * comp_debug
 - * comp_strip
- Checking status
 - general (running, finished, etc.)
 - completion
 - phases
 - * part
 - * name

- * description
- * completion
- * warnings
- cg
- cfgs
- archive
- Obtaining outputs
 - hll
 - dsm
 - cg
 - cfgs
 - archive
 - binary
- Error reporting

Fileinfo

The file-analyzing service.

- Starting a new analysis
- Optional parameters
 - output_format
 - verbose
- Checking status
 - general (running, finished, etc.)
- Obtaining output
- Error reporting

Test

The testing service.

- Authentication
- Parameter passing

CHAPTER 2

Indices

- genindex
- modindex