
SNSAPI Documentation

Release 0.8.1

uxian, hupili

April 12, 2015

1 SNSAPI Middleware	3
1.1 snsbase.py	3
1.2 snsconf.py	6
1.3 snsencrypt.py	7
1.4 snslog.py	8
1.5 snstype.py	8
1.6 utils.py	11
1.7 errors.py	13
1.8 platform.py	14
1.9 snssocket.py	14
2 SNSAPI Pluggins (Specifics for Different Platform)	17
2.1 Sina	17
2.2 Tencent	19
2.3 Renren	20
2.4 RSS	20
3 Sample Applications Written in SNSAPI	23
3.1 hellosns	23
3.2 forwarder	23
3.3 mysofa	23
3.4 clock	23
4 Indices and tables	25
Python Module Index	27

Contents:

SNSAPI Middleware

1.1 snsbase.py

snsapi base class.

All plugins are derived from this class. It provides common authenticate and communicate methods.

```
snsapi.snsbase.require_authed(func)
```

A decorator to require auth before an operation

```
class snsapi.snsbase.SNSBase(channel=None)
```

```
    fetch_code()
```

```
    request_url(url)
```

```
    _oauth2_first()
```

The first stage of oauth. Generate auth url and request.

```
    _oauth2_second()
```

The second stage of oauth. Fetch authenticated code.

```
    oauth2()
```

Authorizing using synchronized invocation of OAuth2.

Users need to collect the code in the browser's address bar to this client. `callback_url` MUST be the same one you set when you apply for an app in openSNS platform.

```
    auth()
```

General entry for authorization. It uses OAuth2 by default.

```
    auth_first()
```

```
    auth_second()
```

```
    open_browser(url)
```

```
    _parse_code(url)
```

Parse code from a URL containing `code=xx` parameter

Parameters `url` – contain code and optionally other parameters

Returns `JsonDict` containing 'code' and (optional) other URL parameters

```
    _token_filename()
```

save_token ()

access token can be saved, it stays valid for a couple of days if successfully saved, invoke `get_saved_token()` to get it back

get_saved_token ()

expire_after (*token=None*)

Calculate how long it is before token expire.

Returns

- >0: the time in seconds.
- 0: has already expired.
- -1: there is no token expire issue for this platform.

is_expired (*token=None*)

Check if the access token is expired.

It delegates the logic to 'expire_after', which is a more formal module to use. This interface is kept for backward compatibility.

is_authed ()

need_auth ()

Whether this platform requires two-stage authorization.

Note:

- Some platforms have authorization flow but we do not use it, e.g. Twitter, where we have a permanent key for developer They'll return False.
- If your platform do need authorization, please override this method in your subclass.

static new_channel (*full=False*)

Return a `JsonDict` object containing channel configurations.

Parameters **full** – Whether to return all config fields.

- False: only returns essential fields.
- True: returns all fields (essential + optional).

read_channel (*channel*)

setup_oauth_key (*app_key, app_secret*)

If you do not want to use `read_channel`, and want to set `app_key` on your own, here it is.

_http_get (*baseurl, params={}, headers=None, json_parse=True*)

Use HTTP GET to request a JSON interface

Parameters

- **baseurl** – Base URL before parameters
- **params** – a dict of params (can be unicode)
- **headers** – a dict of params (can be unicode)
- **json_parse** – whether to parse json (default True)

Returns

- Success: If `json_parse` is True, a dict of json structure is returned. Otherwise, the response of requests library is returned.

- Failure: A warning is logged. If `json_parse` is `True`, `{}` is returned. Otherwise, the response of requests library is returned. (can be `None`)

`_http_post` (*baseurl, params={}, headers=None, files=None, json_parse=True*)

Use HTTP POST to request a JSON interface.

See `_http_get` for more info.

Parameters {'name_in_form' (*files*) – (filename, data/file)}

`_unicode_encode` (*s*)

Detect if a string is unicode and encode as utf-8 if necessary

`_http_delete` (*baseurl, params={}, headers=None, json_parse=True*)

Use HTTP DELETE to request a JSON interface

Parameters

- **`baseurl`** – Base URL before parameters
- **`params`** – a dict of params (can be unicode)
- **`headers`** – a dict of params (can be unicode)
- **`json_parse`** – whether to parse json (default `True`)

Returns

- Success: If `json_parse` is `True`, a dict of json structure is returned. Otherwise, the response of requests library is returned.
- Failure: A warning is logged. If `json_parse` is `True`, `{}` is returned. Otherwise, the response of requests library is returned. (can be `None`)

`_expand_url` (*url*)

expand a shorten url

Parameters **`url`** – The url will be expanded if it is a short url, or it will return the origin url string. url should contain the protocol like “`http://`”

`_cat` (*length, text_list, delim='||'*)

Concatenate strings.

Parameters

- **`length`** – The output should not exceed length unicode characters.
- **`text_list`** – A list of text pieces. Each element is a tuple (text, priority). The `_cat` function will concatenate the texts using the order in `text_list`. If the output exceeds length, (part of) some texts will be cut according to the priority. The lower priority one tuple is assigned, the earlier it will be cut.

`like` (**al, **ad*)

A general forwarding implementation using like method.

Parameters **`message`** – The Message object. The message you want to like.

Returns Successful or not: `True` / `False`

This like function is “shallow”, namely, it has nothing to do with the actual sns website. All what it does is just set a flag to evince that the message is locally liked.

This default implementation is meaningful for sqlite or email.

If you want to have a “deep” like, just override it with your own like function

NOTE: This method require authorization before invokation.

unlike (*message*)

A general forwarding implementation using unlike method.

Parameters **message** – The Message object. The message you want to unlike.

Returns Successful or not: True / False

Same as like

forward (**al, **ad*)

A general forwarding implementation using update method.

Parameters

- **message** – The Message object. The message you want to forward.
- **text** – A unicode string. The comments you add to the message.

Returns Successful or not: True / False

NOTE: This method require authorization before invokation.

`__SNSBase__init_oauth2_client ()`

1.2 snsconf.py

snsapi Basic Hardcode Conf

See documentations of variables for more information.

For first time users, please ignore the following discussion in the same section. They are intended for SNSAPI middleware developers. I don't want to confuse you at the moement. When you are ready to refactor this piece of code, you can come back to read them discuss in the group.

This files may look weird at first glance, here's a short background story on how I get to this point:

- There are many debugging information printed on the console previously, which make stdin/stdout interface a mess.
- I just developed a wrapper for logging. Hope it can unify different log messages.
- 'snsapi' as a whole package will import all plugins at the initialization stage. This will trigger a 'xxx plugged!' message.
- Some calls to write logs happens before we have a chance to init SNSLog (Original plan is to let the upper layer init with its own preference).
- The workaround is to develop this hardcode conf files.

Guidelines to add things here:

- If something is to be configured before fully init of snsapi(which involves init those plugins), the configuration can go into this file.
- Otherwise, try best to let the upper layer configure it. Put the confs in the `../conf` folder.

class `snsapi.snsconf.SNSConf`

Hardcode Confs for SNSAPI

SNSAPI_CONSOLE_STDIN_ENCODING = 'utf-8'

For chinese version windows systems, you may want to change `SNSAPI_CONSOLE_STDOUT_ENCODING = 'utf-8'` and `SNSAPI_CONSOLE_STDIN_ENCODING = 'utf-8'` to 'gbk'. For others, check the encoding of your console and set it accordingly.

See the discussion: <https://github.com/hupili/snsapi/issues/8>

SNSAPI_CONSOLE_STDOUT_ENCODING = 'utf-8'

See SNSAPI_CONSOLE_STDIN_ENCODING.

SNSAPI_DIR_STORAGE_CONF = '/home/docs/.snsapi/conf'

SNSAPI_DIR_STORAGE_ROOT = '/home/docs/.snsapi'

SNSAPI_DIR_STORAGE_SAVE = '/home/docs/.snsapi/save'

SNSAPI_DIR_STORAGE_ROOT can be:

- `./`: if there exists `./save` and `./conf`. This is the usual case for running SNSAPI under the repo. We have the two dirs by default. In this way, you can have multiple configurations on your machine at the same time.
- `~/ .snsapi/`: if the above condition is not satisfied. This is to allow users to launch applications (e.g. `snscli.py` and `snsgui.py`) from any place in the system. The per-user configurations and saved credentials can be used.

SNSAPI_DIR_STORAGE_CONF and SNSAPI_DIR_STORAGE_SAVE are just subdir “conf” and “save” under SNSAPI_DIR_STORAGE_ROOT

SNSAPI_LOG_INIT_LEVEL = 20

Possible values:

- `SNSLog.DEBUG`
- `SNSLog.INFO`
- `SNSLog.WARNING`
- `SNSLog.ERROR`
- `SNSLog.CRITICAL`

In Release version, set to `WARNING`

SNSAPI_LOG_INIT_LOGFILE = None

- `None`: Output to `STDOUT`. Good for Debug version.
- `{Filename}`: Log to `{Filename}`. Good for Release version.

SNSAPI_LOG_INIT_VERBOSE = False

Examples,

True:

- `[DEBUG][20120829-135506][sina.py][<module>][14]SinaAPI plugged!`

False:

- `[DEBUG][20120829-142322]SinaAPI plugged!`

os = <module 'os' from '/home/docs/checkouts/readthedocs.org/user_builds/snsapi/envs/latest/lib/python2.7/os.pyc'>

exception snsapi.snsconf.SNSConfNoInstantiation

This exception is used to make sure you do not instantiate SNSConf class.

1.3 snsencrypt.py

snsapi Cryptography Tools

class `snsapi.snsencrypt.SNSCrypto`
snsapi cryptography tools

decrypt (*string*)

INPUT: hexadecimal string of encrypt output OUTPUT: any string

Reverse process of decrypt

encrypt (*string*)

INPUT: any string OUTPUT: hexadecimal string of encrypt output

The input string will first be encoded by BASE-64. This is to make sure the intermediate value is a printable string. It will be easier to change pyDes to other crypto utilities. After actual encryption delegated to other modules, the final output is also base64 encrypted, this makes it printable.

1.4 snslog.py

snsapi Log Tools

class `snsapi.snslog.SNSLog`
Provide the unified entry to write logs

The current backend is Python's logging module.

CRITICAL = 50

DEBUG = 10

ERROR = 40

INFO = 20

VERBOSE = False

WARNING = 30

static critical (*fmt, *args*)

static debug (*fmt, *args*)

static error (*fmt, *args*)

static info (*fmt, *args*)

static init (*logfile=None, level=30, verbose=True*)

Init the log basic configurations. It should be called only once over the entire execution.

If you invoke it for multiple times, only the first one effects. This is the behaviour of logging module.

static warn (*fmt, *args*)

static warning (*fmt, *args*)

exception `snsapi.snslog.SNSLogNoInstantiation`
docstring for SNSLogNoInstantiation

1.5 snstype.py

SNS type: status, user, comment

class `snsapi.snstype.AuthenticationInfo` (*auth_info=None*)

set_defaults()

class `snsapi.snstype.BooleanWrappedData` (*boolval, data=None*)

class `snsapi.snstype.Message` (*dct=None, platform=None, channel=None, conf={}*)

The Message base class for SNSAPI

Data Fields:

- **platform**: a string describing the platform where this message come from. See ‘snsapi/platform.py’ for more details.
- **raw**: the raw json or XML object returned from the platform specific API. This member is here to give upper layer developers the last chance of manipulating any available information. Having an understanding of the platform-specific returning format is essential.
- **parsed**: this member abstracts some common fields that all messages are supposed to have. e.g. ‘username’, ‘time’, ‘text’, etc.
- **ID**: a MessageID object. This ID should be enough to indentify a message across all different platforms.

For details of ID, please see the docstring of MessageID.

Mandatory fields of `parsed` are:

- **time**: a utc integer. (some platform returns parsed string)
- **userid**: a string. (called as “username” at some platform)
- **username**: a string. (called as “usernick” as some platform)
- **text**: a string. (can be ‘text’ in the returning json object, or parsed from other fields.)
- **attachments**: an array of attachments. Each attachment is: `{‘type’: TYPE, ‘format’: [FORMAT1, FORMAT2, ...], ‘data’: DATA}`. TYPE can be one of link, picture, album, video, blog. FORMAT can be link, binary, text and other. DATA is your data presented in FORMAT.

Optional fields of ‘`parsed`’ are:

- **deleted**: Bool. For some OSN.
- **reposts_count**: an integer. For some OSN.
- **comments_count**: an integer. For some OSN.
- **link**: a string. For RSS; Parsed from microblog message; Parsed from email message; etc.
- **title**: a string. For RSS; Blog channel of some OSN.
- **description**: a string. For RSS digest text; Sharing channel of some OSN; etc.
- **body**: a string. The ‘content’ of RSS, the ‘body’ of HTML, or whatever sematically meaning the body of a document.
- **text_orig**: a string. The original text, also known as “root message” in some context. e.g. the earliest status in one thread.
- **text_last**: a string. The latest text, also known as “message” in some context. e.g. the reply or forwarding comments made by the last user.
- **text_trace**: a string. Using any (can be platform-specific) method to construt the trace of this message. e.g. the forwarding / retweeting / reposting sequence. There is no unified format yet.
- **username_origin**: a string. The username who posts ‘text_orig’.

digest ()

Digest the message content. This value is useful in for example forwarding services to auto-reply services, for those applications requires message deduplication.

It corresponds to dump().

Note: different messages may be regarded as the same according to this digest function.

digest_full ()

It corresponds to dump_full()

digest_parsed ()

It corresponds to dump_parsed()

dump (tz=None)

Level 1 serialization: console output.

This level targets console output. It only digests essential information which end users can understand. e.g. the text of a status is digested whereas the ID fields is not digested.

To control the format, please rewrite dump() in derived Message class.

See also __str__(), __unicode__(), show()

dump_full ()

Level 3 serialization: complete output.

This level targets more sophisticated applications. The basic function of SNSAPI is to unify different formats. That's what the first two level of serialization do. However, app developers may want more sophisticated processing. We serialize the full Message object through this function. In this way, app developers can get all information they need. Note that knowledge of the platform specific return format is essential. We conclude their fields in:

- <https://github.com/hupili/snsapi/wiki/Status-Attributes>

This wiki page may not always be up to date. Please refer to the official API webpage for more info.

dump_parsed ()

Level 2 serialization: interface output.

This level targets both Python class interface and STDIO/STDOUT interface. The output of all kinds of Messages conform to the same format. The json object can be used to pass information in/out SNSAPI using Python class. It is also able to pretty print, so that the STDOUT result is easy to parse in any language.

parse ()

Parse self.raw and store result in self.parsed

platform = 'SNSAPI'

show ()

Level 1 serialization and print to console

See dump()

class snsapi.snstype.**MessageID** (platform=None, channel=None)

All information to locate one status is here.

It should be complete so that:

- one can invoke reply() function of plugin on this object.
- Or one can invoke reply() function of container on this object.

There are two mandatory fields:

- platform: Name of the platform (e.g. RenrenStatus)
- channel: Name of the instantiated channel (e.g. 'renren_account_1'). Same as a channel's `.jsonconf['channel_name']`.

In order to reply one status, here's the information required by each platforms:

- Renren: the `status_id` and `source_user_id`
- Sina: `status_id`
- QQ: `status_id`

NOTE: This object is mainly for SNSAPI to identify a Message. Upper layer had better not to reference fields of this object directly. If you must reference this object, please do not touch those non-mandatory fields.

```
class snsapi.snstype.MessageList (init_list=None)
    A list of Message object

    append (e)

    extend (l)

class snsapi.snstype.User (jobj=None)
```

1.6 utils.py

```
class snsapi.utils.FixedOffsetTimeZone (offset, name)
    Fixed offset in minutes east from UTC.

    See third/timezone_sample.py for more samples.

    dst (dt)

    tzname (dt)

    utcoffset (dt)
```

```
class snsapi.utils.JsonDict (jsonconf=None)
    The wrapper class for Python dict.
```

It is intended to host Json compatible objects. In the interactive CLI, the users are expected to configure SNSAPI during execution. To present the current config in a nice way. We should add indentation for the dump method.

```
get (attr, default_value=None)
    dict entry reading with fault tolerance.
```

Attr A str or a list of str.

Returns The value corresponding to the (first) key, or default val.

If attr is a list, we will try all the candidates until one 'get' is successful. If none of the candidates succeed, return a the `default_value`.

e.g. RSS format is very diverse. To my current knowledge, some formats have 'author' fields, but others do not:

- rss : no
- rss2 : yes
- atom : yes
- rdf : yes

NOTE:

- The original `default_value` is “(null)”. Now we change

to `None`. `None` is more standard in Python and it does not have problem to convert to `str` (the usual way of using our data fields). It has the JSON counterpart: `null`.

class `snsapi.utils.JsonObject`

general json object that can bind any fields but also act as a dict.

class `snsapi.utils.RunnableProcess` (*func*, **args*, ***kwargs*)

execute_func (*func*, **args*, ***kwargs*)

get_result ()

is_finished ()

class `snsapi.utils.Serialize` (**al*, ***ad*)

The common serialization SAP

static dumps (*obj*)

static loads (*string*)

exception `snsapi.utils.TimeoutException`

`snsapi.utils.console_input` (*string=None*)

To make oauth2 testable, and more reusable, we use `console_input` to wrap `raw_input`. See <http://stackoverflow.com/questions/2617057/supply-inputs-to-python-unittests>.

`snsapi.utils.console_output` (*string*)

The sister function of `console_input`!

Actually it has a much longer story. See Issue#8: the discussion of console encoding~

`snsapi.utils.html_entity_unescape` (*s*)

Escape HTML entities, such as “£” This interface always returns unicode no matter the input ‘s’ is str or unicode.

`snsapi.utils.obj2str` (*obj*)

Convert Python object to string using SNSApi convention.

Parameters *obj* – A Python object that is “serializable”. Check `Serialize` to what backend we use for serialization.

`snsapi.utils.report_time` (*func*)

`snsapi.utils.str2obj` (*string*)

Convert string to Python object using SNSApi convention.

Parameters *obj* – A string constructed by `obj2str`. Do not call this method on a string coming from an unknown source.

`snsapi.utils.str2utc` (*s*, *tc=None*)

Parameters *tc* – Timezone Correction (TC). A timezone suffix string. e.g. “ +08:00”, “ HKT”, etc. Some platforms are known to return time string without TZ (e.g. Renren). Manually do the correction.

`snsapi.utils.strip_html` (*text*)

`snsapi.utils.timeout` (*secs*)

`snsapi.utils.utc2str` (*u*, *tz=None*)

1.7 errors.py

Errors or Exceptions for SNSAPI

How to add an error type?

- Check out `Mark1` (in `errors.py`). Inherit your error type from a right class. The `#>>` comment denotes the level an error type is in.
- Check out `Makr2` (in `errors.py`). Add your new error type to the corresponding tree.

How to reference an error type?

- By convention, others should only import “`snserror`”. e.g. `from errors import snserror`, or from `snsapi import snserror`.
- Use dot expression to enter the exact type. e.g. `snserror.config.nofile`.

exception `snsapi.errors.ConfigError`

```

load
    alias of SNSPocketLoadConfigError

nofile
    alias of NoConfigFile

save
    alias of SNSPocketSaveConfigError

```

exception `snsapi.errors.MissAPPInfo`

exception `snsapi.errors.NoConfigFile` (*fname='conf/channel.json'*)

exception `snsapi.errors.NoPlatformInfo`

exception `snsapi.errors.NoSuchChannel`

exception `snsapi.errors.NoSuchPlatform`

exception `snsapi.errors.SNSAuthFail`

```

fetchcode
    alias of SNSAuthFechCodeError

```

exception `snsapi.errors.SNSAuthFechCodeError`

exception `snsapi.errors.SNSEncodingError`

exception `snsapi.errors.SNSError`

exception `snsapi.errors.SNSOperation`

```

read
    alias of SNSReadFail

```

```

write
    alias of SNSWriteFail

```

exception `snsapi.errors.SNSPocketDuplicateName` (*cname*)

exception `snsapi.errors.SNSPocketError`

exception `snsapi.errors.SNSPocketLoadConfigError` (*msg=''*)

exception `snsapi.errors.SNSPocketSaveConfigError`

exception `snsapi.errors.SNSReadFail`

exception `snsapi.errors.SNSTypeError` (*value*='')

parse

alias of `SNSTypeParseError`

exception `snsapi.errors.SNSTypeParseError` (*value*='')

exception `snsapi.errors.SNSTypeWrongInput` (*value*='')

exception `snsapi.errors.SNSWriteFail` (*value*)

class `snsapi.errors.snserror`

auth

alias of `SNSAuthFail`

config

alias of `ConfigError`

op

alias of `SNSOperation`

type

alias of `SNSTypeError`

1.8 platform.py

Platforms.

Upper layer can reference platforms from this module

1.9 snssocket.py

snssocket: the container class for snsapi's

```
class snsapi.snssocket.BackgroundOperationPocketWithSQLite (pocket, sqlite, call-  
back=<function _de-  
fault_callback at  
0x7f6b22379230>, at  
timeline_sleep=60,  
update_sleep=10)
```

forward (**args*, ***kwargs*)

home_timeline (*count*=20)

reply (**args*, ***kwargs*)

update (**args*, ***kwargs*)

update_func ()

write_timeline_to_db (*msglist*)

class `snsapi.sns pocket.SNSPocket`

The container class for snsapi's

add_channel (*jsonconf*)

auth (*channel=None*)
docstring for auth

clear_channel ()

forward (*message, text, channel=None*)
forward a message

home_timeline (*count=None, channel=None*)
Route to home_timeline method of snsapi.

Parameters **channel** – The channel name. Use None to read all channels

like (*message, channel=None*)
like a message

list_channel (*channel=None, verbose=False*)

list_platform ()

load_config (*fn_channel='/home/docs/.snsapi/conf/channel.json', fn_pocket='/home/docs/.snsapi/conf/pocket.json'*)
Read configs: * channel.conf * pocket.conf

new_channel (*pl=None, **kwarg*)

reply (*message, text, channel=None*)
Route to reply method of snsapi.

Parameters

- **channel** – The channel name. Use None to automatically select one compatible channel.
- **status** – Message or MessageID object.

Text Reply text.

save_config (*fn_channel='/home/docs/.snsapi/conf/channel.json', fn_pocket='/home/docs/.snsapi/conf/pocket.json'*)
Save configs: reverse of load_config

Configs can be modified during execution. snsapi components communicate with upper layer using Python objects. Pocket will be the unified place to handle file transactions.

unlike (*message, channel=None*)
unlike a message

update (*text, channel=None, **kwargs*)
Route to update method of snsapi.

Parameters **channel** – The channel name. Use None to update all channels

SNSAPI Pluggins (Specifics for Different Platform)

2.1 Sina

Sina Weibo client

```
class snsapi.plugin.sina.SinaWeiboBase (channel=None)
```

```
    static new_channel (full=False)
```

```
    read_channel (channel)
```

```
    need_auth ()
```

```
    auth_first ()
```

```
    auth_second ()
```

```
    weibo_request (*al, **ad)
```

General request method for Weibo V2 Api via OAuth.

Parameters

- **name** – The Api name shown on main page (http://open.weibo.com/wiki/API%E6%96%87%E6%A1%A3_V2). e.g. `friendships/create` (no “2/” prefix)
- **method** – HTTP request method: ‘GET’ or ‘POST’
- **params** – Parameters from Api doc. No need to manually put `access_token` in.

Returns The http response from SinaWeibo (a JSON compatible structure).

NOTE: This method require authorization before invocation.

```
class snsapi.plugin.sina.SinaWeiboStatusMessage (dct=None, platform=None, channel=None, conf={})
```

```
    platform = 'SinaWeiboStatus'
```

```
    parse ()
```

```
class snsapi.plugin.sina.SinaWeiboStatus (channel=None)
```

Message

alias of `SinaWeiboStatusMessage`

```
    home_timeline (*al, **ad)
```

Get home timeline

Parameters count – number of statuses

NOTE: This method require authorization before invocation.

update (**al*, ***ad*)

update a status

- parameter text: the update message
- return: success or not

NOTE: This method require authorization before invocation.

reply (**al*, ***ad*)

reply to a status

- parameter text: the comment text
- return: success or not

NOTE: This method require authorization before invocation.

forward (**al*, ***ad*)

Forward a status on SinaWeibo:

- If message is from the same platform, forward it using special interface.
- Else, route the request to a general forward method of SNSBase.
- Decorate the text with previous comment sequence.

Parameters

- **message** – An `snstype.Message` object to forward
- **text** – Append comment text

Returns Success or not

NOTE: This method require authorization before invocation.

like (**al*, ***ad*)

Like method

- Weibo doesn't provide an API for "like"
- So "favourite" function supersedes "like"
- Here "like" means "add to my favourites"
- Receive a message

NOTE: This method require authorization before invocation.

unlike (**al*, ***ad*)

Unlike method

- Weibo doesn't provide an API for "unlike"
- So "unfavourite" function supersedes "unlike"
- Here "unlike" means "remove from my favourites"
- Receive a message

NOTE: This method require authorization before invocation.

2.2 Tencent

Tencent Weibo Client

```
class snsapi.plugin.tencent.TencentWeiboStatusMessage (dct=None, platform=None, channel=None, conf={})
```

```
    platform = 'TencentWeiboStatus'
```

```
    parse ()
```

```
class snsapi.plugin.tencent.TencentWeiboStatus (channel=None)
```

```
    Message
```

```
        alias of TencentWeiboStatusMessage
```

```
    static new_channel (full=False)
```

```
    read_channel (channel)
```

```
    need_auth ()
```

```
    auth_first ()
```

```
    auth_second ()
```

```
    tencent_request (method, http_method='GET', files={}, **kwargs)
```

```
    home_timeline (*al, **ad)
```

```
        Get home timeline
```

- function : get statuses of yours and your friends'
- parameter count: number of statuses

NOTE: This method require authorization before invokation.

```
    update (*al, **ad)
```

```
        update a status
```

- parameter text: the update message
- return: success or not

NOTE: This method require authorization before invokation.

```
    reply (*al, **ad)
```

```
        reply to a status
```

- parameter text: the comment text
- return: success or not

NOTE: This method require authorization before invokation.

```
    like (*al, **ad)
```

```
        like a status
```

- parameter message: the message to be liked
- return: success or not

NOTE: This method require authorization before invokation.

```
    unlike (*al, **ad)
```

```
        unlike a status
```

- parameter message: the message to be unliked
- return: success or not

NOTE: This method require authorization before invokation.

2.3 Renren

2.4 RSS

RSS Feed

Contains:

- RSS Read-only feed platform.
- RSS Read/Write platform.
- RSS Summary platform.

class snsapi.plugin.rss.**RSSMessage** (*dct=None, platform=None, channel=None, conf={}*)

platform = 'RSS'

parse ()

dump_full ()

Override `Message.dump_full` because default `.raw` attribute of `RSSMessage` object is not JSON serializable.

Note: dumped messages are meant for the consumption of other languages. We do not concern how to convert back. If you do that, make sure call `str2obj` on `.raw` yourself. Besides, make sure the source of the string is trustful.

For the use in Python, directly serialize the message for persistent storage. Do not recommend you use any of the three level of `dump_xxx` functions. Use of `digest_xxx` is OK.

class snsapi.plugin.rss.**RSS** (*channel=None*)

Supported Methods

- **auth()** : a NULL stub.
- **home_timeline()** : read and parse RSS feed. pretend it to be a 'special' SNS platform, where you can only read your wall but can not write to it.

Message

alias of `RSSMessage`

static new_channel (*full=False*)

read_channel (*channel*)

auth ()

auth_first ()

auth_second ()

home_timeline (*count=20*)

Get home timeline

- function : get statuses of yours and your friends'

- parameter count: number of statuses

expire_after (*token=None*)

```
class snsapi.plugin.rss.RSS2RWMessage (dct=None, platform=None, channel=None, conf={})
```

platform = 'RSS2RW'

parse ()

```
class snsapi.plugin.rss.RSS2RW (channel=None)
```

Read/Write Channel for rss2

Message

alias of `RSS2RWMessage`

static new_channel (*full=False*)

read_channel (*channel*)

update (*message*)

Parameters message (Message or str) – For Message update it directly. RSS2RW guarantee the message can be read back with the same values in standard fields of `Message.parsed`. For str, we compose the virtual Message first using current time and configured author information.

```
class snsapi.plugin.rss.RSSSummaryMessage (dct=None, platform=None, channel=None, conf={})
```

platform = 'RSSSummary'

parse ()

```
class snsapi.plugin.rss.RSSSummary (channel=None)
```

Summary Channel for RSS

It provides more meaningful 'text' field.

Message

alias of `RSSSummaryMessage`

static new_channel (*full=False*)

Sample Applications Written in SNSAPI

3.1 hellosns

3.1.1 `test_read_all.py`

3.1.2 `test_write_all.py`

3.1.3 `test_read_reply.py`

3.2 forwarder

3.3 mysofa

3.4 clock

The scripts can not be autodoc-ed due to (possibly) non-ascii characters there. We'll add the doc once the problem is solved. Please read the app README instead: <https://github.com/hupili/snsapi/tree/master/app/clock>

Indices and tables

- *genindex*
- *modindex*
- *search*

S

snsapi.errors, 13
snsapi.platform, 14
snsapi.plugin.rss, 20
snsapi.plugin.sina, 17
snsapi.plugin.tencent, 19
snsapi.snsbase, 3
snsapi.snsconf, 6
snsapi.snsencrypt, 7
snsapi.snslog, 8
snsapi.snspocket, 14
snsapi.snstype, 8
snsapi.utils, 11

Symbols

_SNSBase__init_oauth2_client()
 (snsapi.snsbase.SNSBase method), 6
 _cat() (snsapi.snsbase.SNSBase method), 5
 _expand_url() (snsapi.snsbase.SNSBase method), 5
 _http_delete() (snsapi.snsbase.SNSBase method), 5
 _http_get() (snsapi.snsbase.SNSBase method), 4
 _http_post() (snsapi.snsbase.SNSBase method), 5
 _oauth2_first() (snsapi.snsbase.SNSBase method), 3
 _oauth2_second() (snsapi.snsbase.SNSBase method), 3
 _parse_code() (snsapi.snsbase.SNSBase method), 3
 _token_filename() (snsapi.snsbase.SNSBase method), 3
 _unicode_encode() (snsapi.snsbase.SNSBase method), 5

A

add_channel() (snsapi.snssocket.SNSPocket method), 15
 append() (snsapi.snstype.MessageList method), 11
 auth (snsapi.errors.snserror attribute), 14
 auth() (snsapi.plugin.rss.RSS method), 20
 auth() (snsapi.snsbase.SNSBase method), 3
 auth() (snsapi.snssocket.SNSPocket method), 15
 auth_first() (snsapi.plugin.rss.RSS method), 20
 auth_first() (snsapi.plugin.sina.SinaWeiboBase method),
 17
 auth_first() (snsapi.plugin.tencent.TencentWeiboStatus
 method), 19
 auth_first() (snsapi.snsbase.SNSBase method), 3
 auth_second() (snsapi.plugin.rss.RSS method), 20
 auth_second() (snsapi.plugin.sina.SinaWeiboBase
 method), 17
 auth_second() (snsapi.plugin.tencent.TencentWeiboStatus
 method), 19
 auth_second() (snsapi.snsbase.SNSBase method), 3
 AuthenticationInfo (class in snsapi.snstype), 8

B

BackgroundOperationPocketWithSQLite (class in
 snsapi.snssocket), 14
 BooleanWrappedData (class in snsapi.snstype), 9

C

clear_channel() (snsapi.snssocket.SNSPocket method),
 15
 config (snsapi.errors.snserror attribute), 14
 ConfigError, 13
 console_input() (in module snsapi.utils), 12
 console_output() (in module snsapi.utils), 12
 CRITICAL (snsapi.snslog.SNSLog attribute), 8
 critical() (snsapi.snslog.SNSLog static method), 8

D

DEBUG (snsapi.snslog.SNSLog attribute), 8
 debug() (snsapi.snslog.SNSLog static method), 8
 decrypt() (snsapi.snsencrypt.SNSCrypto method), 8
 digest() (snsapi.snstype.Message method), 9
 digest_full() (snsapi.snstype.Message method), 10
 digest_parsed() (snsapi.snstype.Message method), 10
 dst() (snsapi.utils.FixedOffsetTimeZone method), 11
 dump() (snsapi.snstype.Message method), 10
 dump_full() (snsapi.plugin.rss.RSSMessage method), 20
 dump_full() (snsapi.snstype.Message method), 10
 dump_parsed() (snsapi.snstype.Message method), 10
 dumps() (snsapi.utils.Serialize static method), 12

E

encrypt() (snsapi.snsencrypt.SNSCrypto method), 8
 ERROR (snsapi.snslog.SNSLog attribute), 8
 error() (snsapi.snslog.SNSLog static method), 8
 execute_func() (snsapi.utils.RunnableProcess method),
 12
 expire_after() (snsapi.plugin.rss.RSS method), 21
 expire_after() (snsapi.snsbase.SNSBase method), 4
 extend() (snsapi.snstype.MessageList method), 11

F

fetch_code() (snsapi.snsbase.SNSBase method), 3
 fetchcode (snsapi.errors.SNSAuthFail attribute), 13
 FixedOffsetTimeZone (class in snsapi.utils), 11
 forward() (snsapi.plugin.sina.SinaWeiboStatus method),
 18

forward() (snsapi.snsbase.SNSBase method), 6

forward() (snsapi.sns pocket.BackgroundOperationPocketWithSQLite method), 14

forward() (snsapi.sns pocket.SNSPocket method), 15

G

get() (snsapi.utils.JsonDict method), 11

get_result() (snsapi.utils.RunnableProcess method), 12

get_saved_token() (snsapi.snsbase.SNSBase method), 4

H

home_timeline() (snsapi.plugin.rss.RSS method), 20

home_timeline() (snsapi.plugin.sina.SinaWeiboStatus method), 17

home_timeline() (snsapi.plugin.tencent.TencentWeiboStatus method), 19

home_timeline() (snsapi.sns pocket.BackgroundOperationPocketWithSQLite method), 14

home_timeline() (snsapi.sns pocket.SNSPocket method), 15

html_entity_unescape() (in module snsapi.utils), 12

I

INFO (snsapi.snslog.SNSLog attribute), 8

info() (snsapi.snslog.SNSLog static method), 8

init() (snsapi.snslog.SNSLog static method), 8

is_authed() (snsapi.snsbase.SNSBase method), 4

is_expired() (snsapi.snsbase.SNSBase method), 4

is_finished() (snsapi.utils.RunnableProcess method), 12

J

JsonDict (class in snsapi.utils), 11

JsonObject (class in snsapi.utils), 12

L

like() (snsapi.plugin.sina.SinaWeiboStatus method), 18

like() (snsapi.plugin.tencent.TencentWeiboStatus method), 19

like() (snsapi.snsbase.SNSBase method), 5

like() (snsapi.sns pocket.SNSPocket method), 15

list_channel() (snsapi.sns pocket.SNSPocket method), 15

list_platform() (snsapi.sns pocket.SNSPocket method), 15

load (snsapi.errors.ConfigError attribute), 13

load_config() (snsapi.sns pocket.SNSPocket method), 15

loads() (snsapi.utils.Serialize static method), 12

M

Message (class in snsapi.snstype), 9

Message (snsapi.plugin.rss.RSS attribute), 20

Message (snsapi.plugin.rss.RSS2RW attribute), 21

Message (snsapi.plugin.rss.RSSSummary attribute), 21

Message (snsapi.plugin.sina.SinaWeiboStatus attribute), 17

Message (snsapi.plugin.tencent.TencentWeiboStatus attribute), 19

MessageID (class in snsapi.snstype), 10

MessageList (class in snsapi.snstype), 11

MissAPPIInfo, 13

N

need_auth() (snsapi.plugin.sina.SinaWeiboBase method), 17

need_auth() (snsapi.plugin.tencent.TencentWeiboStatus method), 19

need_auth() (snsapi.snsbase.SNSBase method), 4

new_channel() (snsapi.plugin.rss.RSS static method), 20

new_channel() (snsapi.plugin.rss.RSS2RW static method), 21

new_channel() (snsapi.plugin.rss.RSSSummary static method), 21

new_channel() (snsapi.plugin.sina.SinaWeiboBase static method), 17

new_channel() (snsapi.plugin.tencent.TencentWeiboStatus static method), 19

new_channel() (snsapi.snsbase.SNSBase static method), 4

new_channel() (snsapi.sns pocket.SNSPocket method), 15

NoConfigFile, 13

nofile (snsapi.errors.ConfigError attribute), 13

NoPlatformInfo, 13

NoSuchChannel, 13

NoSuchPlatform, 13

O

oauth2() (snsapi.snsbase.SNSBase method), 3

obj2str() (in module snsapi.utils), 12

op (snsapi.errors.snserror attribute), 14

open_brower() (snsapi.snsbase.SNSBase method), 3

os (snsapi.snsconf.SNSConf attribute), 7

P

parse (snsapi.errors.SNSTypeError attribute), 14

parse() (snsapi.plugin.rss.RSS2RWMessage method), 21

parse() (snsapi.plugin.rss.RSSMessage method), 20

parse() (snsapi.plugin.rss.RSSSummaryMessage method), 21

parse() (snsapi.plugin.sina.SinaWeiboStatusMessage method), 17

parse() (snsapi.plugin.tencent.TencentWeiboStatusMessage method), 19

parse() (snsapi.snstype.Message method), 10

platform (snsapi.plugin.rss.RSS2RWMessage attribute), 21

platform (snsapi.plugin.rss.RSSMessage attribute), 20

platform (snsapi.plugin.rss.RSSSummaryMessage attribute), 21

- platform (snsapi.plugin.sina.SinaWeiboStatusMessage attribute), 17
- platform (snsapi.plugin.tencent.TencentWeiboStatusMessage attribute), 19
- platform (snsapi.snstype.Message attribute), 10
- ## R
- read (snsapi.errors.SNSOperation attribute), 13
- read_channel() (snsapi.plugin.rss.RSS method), 20
- read_channel() (snsapi.plugin.rss.RSS2RW method), 21
- read_channel() (snsapi.plugin.sina.SinaWeiboBase method), 17
- read_channel() (snsapi.plugin.tencent.TencentWeiboStatus method), 19
- read_channel() (snsapi.snsbase.SNSBase method), 4
- reply() (snsapi.plugin.sina.SinaWeiboStatus method), 18
- reply() (snsapi.plugin.tencent.TencentWeiboStatus method), 19
- reply() (snsapi.sns pocket.BackgroundOperationPocketWithSocket method), 14
- reply() (snsapi.sns pocket.SNSPocket method), 15
- report_time() (in module snsapi.utils), 12
- request_url() (snsapi.snsbase.SNSBase method), 3
- require_authed() (in module snsapi.snsbase), 3
- RSS (class in snsapi.plugin.rss), 20
- RSS2RW (class in snsapi.plugin.rss), 21
- RSS2RWMessage (class in snsapi.plugin.rss), 21
- RSSMessage (class in snsapi.plugin.rss), 20
- RSSSummary (class in snsapi.plugin.rss), 21
- RSSSummaryMessage (class in snsapi.plugin.rss), 21
- RunnableProcess (class in snsapi.utils), 12
- ## S
- save (snsapi.errors.ConfigError attribute), 13
- save_config() (snsapi.sns pocket.SNSPocket method), 15
- save_token() (snsapi.snsbase.SNSBase method), 3
- Serialize (class in snsapi.utils), 12
- set_defaults() (snsapi.snstype.AuthenticationInfo method), 8
- setup_oauth_key() (snsapi.snsbase.SNSBase method), 4
- show() (snsapi.snstype.Message method), 10
- SinaWeiboBase (class in snsapi.plugin.sina), 17
- SinaWeiboStatus (class in snsapi.plugin.sina), 17
- SinaWeiboStatusMessage (class in snsapi.plugin.sina), 17
- snsapi.errors (module), 13
- snsapi.platform (module), 14
- snsapi.plugin.rss (module), 20
- snsapi.plugin.sina (module), 17
- snsapi.plugin.tencent (module), 19
- snsapi.snsbase (module), 3
- snsapi.snsconf (module), 6
- snsapi.snsencrypt (module), 7
- snsapi.snslog (module), 8
- snsapi.sns pocket (module), 14
- snsapi.snstype (module), 8
- snsapi.utils (module), 11
- SNSAPI_CONSOLE_STDIN_ENCODING (snsapi.snsconf.SNSConf attribute), 6
- SNSAPI_CONSOLE_STDOUT_ENCODING (snsapi.snsconf.SNSConf attribute), 7
- SNSAPI_DIR_STORAGE_CONF (snsapi.snsconf.SNSConf attribute), 7
- SNSAPI_DIR_STORAGE_ROOT (snsapi.snsconf.SNSConf attribute), 7
- SNSAPI_DIR_STORAGE_SAVE (snsapi.snsconf.SNSConf attribute), 7
- SNSAPI_LOG_INIT_LEVEL (snsapi.snsconf.SNSConf attribute), 7
- SNSAPI_LOG_INIT_LOGFILE (snsapi.snsconf.SNSConf attribute), 7
- SNSAPI_LOG_INIT_VERBOSE (snsapi.snsconf.SNSConf attribute), 7
- SNSAuthFail, 13
- SNSAuthFechCodeError, 13
- SNSBase (class in snsapi.snsbase), 3
- SNSConf (class in snsapi.snsconf), 6
- SNSConfNoInstantiation, 7
- SNSCrypto (class in snsapi.snsencrypt), 7
- SNSEncodingError, 13
- SNSError, 13
- snserror (class in snsapi.errors), 14
- SNSLog (class in snsapi.snslog), 8
- SNSLogNoInstantiation, 8
- SNSOperation, 13
- SNSPocket (class in snsapi.sns pocket), 14
- SNSPocketDuplicateName, 13
- SNSPocketError, 13
- SNSPocketLoadConfigError, 13
- SNSPocketSaveConfigError, 13
- SNSReadFail, 14
- SNSTypeError, 14
- SNSTypeParseError, 14
- SNSTypeWrongInput, 14
- SNSWriteFail, 14
- str2obj() (in module snsapi.utils), 12
- str2utc() (in module snsapi.utils), 12
- strip_html() (in module snsapi.utils), 12
- ## T
- tencent_request() (snsapi.plugin.tencent.TencentWeiboStatus method), 19
- TencentWeiboStatus (class in snsapi.plugin.tencent), 19
- TencentWeiboStatusMessage (class in snsapi.plugin.tencent), 19
- timeout() (in module snsapi.utils), 12
- TimeoutException, 12
- type (snsapi.errors.snserror attribute), 14
- tzname() (snsapi.utils.FixedOffsetTimeZone method), 11

U

- unlike() (snsapi.plugin.sina.SinaWeiboStatus method), 18
- unlike() (snsapi.plugin.tencent.TencentWeiboStatus method), 19
- unlike() (snsapi.snsbase.SNSBase method), 5
- unlike() (snsapi.sns pocket.SNSPocket method), 15
- update() (snsapi.plugin.rss.RSS2RW method), 21
- update() (snsapi.plugin.sina.SinaWeiboStatus method), 18
- update() (snsapi.plugin.tencent.TencentWeiboStatus method), 19
- update() (snsapi.sns pocket.BackgroundOperationPocketWithSQLite method), 14
- update() (snsapi.sns pocket.SNSPocket method), 15
- update_func() (snsapi.sns pocket.BackgroundOperationPocketWithSQLite method), 14
- User (class in snsapi.snstype), 11
- utc2str() (in module snsapi.utils), 12
- utcoffset() (snsapi.utils.FixedOffsetTimeZone method), 11

V

- VERBOSE (snsapi.snslog.SNSLog attribute), 8

W

- warn() (snsapi.snslog.SNSLog static method), 8
- WARNING (snsapi.snslog.SNSLog attribute), 8
- warning() (snsapi.snslog.SNSLog static method), 8
- weibo_request() (snsapi.plugin.sina.SinaWeiboBase method), 17
- write (snsapi.errors.SNSOperation attribute), 13
- write_timeline_to_db() (snsapi.sns pocket.BackgroundOperationPocketWithSQLite method), 14