
PocketMine-MP Documentation

Release 1.7dev

Intyre

Jan 16, 2019

Contents

1	Introduction	3
1.1	Supported features	3
1.2	Contact and Support	3
2	Installation	5
2.1	Setup requirements	5
2.2	Using https://get.pmp.io (Linux/macOS only)	5
2.3	Installing manually	6
2.4	Starting for the first time	6
3	Updating	9
3.1	Update using the installer (Linux/macOS only)	9
3.2	Manually update	9
4	Configuration	11
4.1	Default configuration files	11
5	FAQ	17
5.1	Installation	17
5.2	Connecting	18
5.3	Playing	21
5.4	Plugins	21
5.5	Supported MCPE Versions	22
6	Issues	25
6.1	Issue template	25
6.2	Crashdumps	26
7	Contact and Support	27
8	Links	29
8.1	Downloads	29
8.2	Other links	30

Pocket Mine

PocketMine

PocketMine-MP is a server software for the Bedrock family of Minecraft editions (formerly known as Pocket Edition, Windows 10 Edition and others). It has a Plugin API that enables a developer to extend it and add new features, or change default ones.

1.1 Supported features

- Get all your friends in one server. Or run a public server.
- Disables flying, item hack, running & more. With an On/Off switch.
- Extend the game in the way you want, add awesome features.
- Teleport players, whitelist your server, tune the server, Remote Console.
- Load different levels at once, and teleport back and forth.
- Endless features, and we continuously implement new things.

1.2 Contact and Support

- [Forums](#)
- [Community Discord](#)

2.1 Setup requirements

A computer or device with the following is required:

- 64-bit CPU
- 64-bit operating system
- 1GB RAM or better

The following are not requirements, but recommended:

- Dual-core or better CPU

Note: PocketMine-MP is notoriously bad at multi-core usage. If purchasing a machine to run PocketMine-MP on, prefer higher CPU frequency instead of lots of cores.

We officially try to support Windows, Linux and MacOS platforms. However, in general any platform which will run 64-bit PHP with the required extensions will work.

2.2 Using <https://get.pmmp.io> (Linux/MacOS only)

Warning: Only works on Linux or MacOS.

Create a directory which you want to install PocketMine-MP into, and `cd` into it.

Then use `curl` to install PocketMine-MP using the following command:

```
curl -sL https://get.pmmp.io | bash -s -
```

or, if you don't have curl, try wget:

```
wget -q -O - https://get.pmmp.io | bash -s -
```

```
[*] Found PocketMine-MP Final_1.5dev (build 1254) using API 1.12.0
[*] This development build was released on Sat Jun 20 09:45:04 CEST 2015
[*] Installing/updating PocketMine-MP on directory ./
[1/3] Cleaning...
[2/3] Downloading PocketMine-MP Final_1.5dev-1254 phar... done!
[3/3] Obtaining PHP: detecting if build is available...
[3/3] MacOS 64-bit PHP build available, downloading PHP_5.6.10_x86-64_MacOS.tar.gz...
→checking... regenerating php.ini... done
[*] Everything done! Run ./start.sh to start PocketMine-MP
```

Error: It is recommended to run it as a **normal user** as it doesn't need further permissions.

Do not run the installer as root, this is discouraged.

Note: If the installer doesn't work for you, try *installing manually*.

2.3 Installing manually

No installer available for your platform? Did the installer fail? It is not your taste? YOLO? DIY!

2.3.1 Getting PHP for your server

1. Download your flavor PHP binary (*Downloads*)
2. Extract the PHP binary into your server directory. If everything went well, you should have a *bin* folder in your server directory.
3. (Windows only) Download and install Microsoft Visual C++ Redistributable 2017 (*Downloads*)

2.3.2 Getting PocketMine-MP

1. Create a new directory for PocketMine-MP.
2. Download PocketMine-MP.phar (*Downloads*)
3. Rename the .phar to PocketMine-MP.phar.
4. Place it in the PocketMine-MP directory you just created.
5. Get the start script for your platform (*Windows CMD*, *Windows PowerShell*, *Linux/MacOS bash*)
6. (Linux/MacOS only) Make start.sh executable (chmod +x start.sh)

2.4 Starting for the first time

- Linux/MacOS: run `./start.sh`

- Windows: Double-click `start.cmd`, or open PowerShell in the server directory and run `.\start.ps1`.

The first time PocketMine-MP starts, it launches a set-up wizard. This can be disabled by running `./start.sh --no-wizard`.

```
$ ./start.sh
[*] PocketMine-MP set-up wizard
[*] Please select a language:
English => en
Español => es
ä,ä-† => zh
Pycckî,Ð,Ð¹ => ru
æ--¥ææ-èªž => ja
Deutsch => de
í•æêµì-´ => ko
Nederlands => nl
Français => fr
Italiano => it
Melayu => ms
Norsk => no
Svenska => sv
Suomi => fi
Türkçe => tr
[?] Language (en):
```

PocketMine-MP supports a few other languages. Fill in the two letters behind the language and press enter. Is your language not in the list? Add it on [Crowdin](#).

```
[*] English has been correctly selected.
Welcome to PocketMine-MP!
Before starting setting up your new server you have to accept the license.
PocketMine-MP is licensed under the LGPL License,
that you can read opening the LICENSE file on this folder.

This program is free software: you can redistribute it and/or modify
it under the terms of the GNU Lesser General Public License as published by
the Free Software Foundation, either version 3 of the License, or
(at your option) any later version.

[?] Do you accept the License? (y/N):
```

Do you accept the [License](#)?

```
[?] Do you want to skip the set-up wizard? (y/N):
```

You can skip the wizard from here and start the server with the default settings or continue.

```
[*] You are going to set up your server now.
[*] If you don't want to change the default value, just press Enter.
[*] You can edit them later on the server.properties file.
[?] Give a name to your server (Minecraft: PE Server):
[*] Do not change the default port value if this is your first server.
[?] Server port (19132):
[*] Choose between Creative (1) or Survival (0)
[?] Default Game mode (0):
[?] Max. online players (20):
[*] The spawn protection disallows placing/breaking blocks in the spawn zone except
↳for OPs
```

(continues on next page)

(continued from previous page)

```
[?] Enable spawn protection? (Y/n):
[*] An OP is the player admin of the server. OPs can run more commands than normal
↳players
[?] OP player name (example, your game name):
[!] You will be able to add an OP user later using /op <player>
[*] The white-list only allows players in it to join.
[?] Do you want to enable the white-list? (y/N):
[!] Query is a protocol used by different tools to get information of your server and
↳players logged in.
[!] If you disable it, you won't be able to use server lists.
[?] Do you want to disable Query? (y/N):
[*] RCON is a protocol to remote connect with the server console using a password.
[?] Do you want to enable RCON? (y/N):
[*] Getting your external IP and internal IP
[!] Your external IP is [your external IP]. You may have to port-forward to your
↳internal IP [your internal IP]
[!] Be sure to check it, if you have to forward and you skip that, no external
↳players will be able to join. [Press Enter]

[*] You have finished the set-up wizard correctly
[*] Check the Plugin Repository to add new features, minigames, or advanced
↳protection to your server
[*] PocketMine-MP will now start. Type /help to view the list of available commands.

[10:18:38] [Server thread/INFO]: Loading pocketmine.yml...
[10:18:38] [Server thread/INFO]: Loading server properties...
[10:18:38] [Server thread/INFO]: Selected English (eng) as the base language
[10:18:38] [Server thread/INFO]: Starting Minecraft: PE server version v1.1.0.55
[10:18:38] [Server thread/INFO]: Opening server on 0.0.0.0:19132
[10:18:38] [Server thread/INFO]: This server is running PocketMine-MP version 1.7dev
↳"[REDACTED]" (API 3.0.0-ALPHA7)
[10:18:38] [Server thread/INFO]: PocketMine-MP is distributed under the LGPL License
[10:18:38] [Server thread/INFO]: Loading recipes...
[10:18:38] [Server thread/INFO]: Loading resource packs...
[10:18:39] [Server thread/NOTICE]: Level "world" not found
[10:18:39] [Server thread/INFO]: Preparing level "world"
[10:18:39] [Server thread/NOTICE]: Spawn terrain for level "world" is being generated
↳in the background
[10:18:39] [Server thread/INFO]: Starting GS4 status listener
[10:18:39] [Server thread/INFO]: Setting query port to 19132
[10:18:39] [Server thread/INFO]: Query running on 0.0.0.0:19132
[10:18:39] [Server thread/INFO]: Default game type: Survival Mode
[10:18:39] [Server thread/INFO]: Done (59.006s)! For help, type "help" or "?"
```

The server should have started now and you should be able to join.

- *Update using the installer (Linux/MacOS only)*
- *Manually update*
 - *Update PHP binary*
 - *Updating PocketMine-MP*

3.1 Update using the installer (Linux/MacOS only)

You can also use the installer on these platforms to update your installation. Passing the `-u` flag will update the PocketMine-MP installation.

cd into your server directory. Then use `curl` or `wget` to update PocketMine-MP using the following command:

```
curl -sL https://get.pmmp.io | bash -s - -u  
wget -q -O - https://get.pmmp.io | bash -s - -u
```

3.2 Manually update

3.2.1 Update PHP binary

1. Download the PHP binary for your OS (*Downloads*)
2. Delete the `bin` directory in your server folder.
3. Extract the new PHP binary. You should see a new `bin` directory has been created.

3.2.2 Updating PocketMine-MP

Updating using .phar

This is very straightforward.

1. Delete your current PocketMine-MP.phar
2. Download the updated PocketMine-MP phar you want to use ([Downloads](#))
3. Change the name to PocketMine-MP.phar
4. Place it in the server folder

Note: Don't forget to rename the file to PocketMine-MP.phar

Updating a Git installation

If you used Git to install, updating is very simple.

cd into the server directory and run the following:

```
git pull # get the latest source from GitHub
git submodule update # update submodules to the required versions
composer install [... optional extra composer flags] # install/update dependencies
↳ managed by Composer
```

See Installing using Git for more details.

Note: Previous versions of PocketMine-MP used submodules `src/spl` and `src/raklib`, which have now been removed. These submodules need to be manually deleted in your local installation.

To do so, delete the `spl` and `raklib` directories in the `src` directory, and then re-run Composer.

4.1 Default configuration files

4.1.1 server.properties

```
#Properties Config file
#Wed Jan 16 09:32:51 GMT 2019
language=eng
motd=PocketMine-MP Server
server-port=19132
white-list=off
announce-player-achievements=on
spawn-protection=16
max-players=20
gamemode=0
force-gamemode=off
hardcore=off
pvp=on
difficulty=1
generator-settings=
level-name=world
level-seed=
level-type=DEFAULT
enable-query=on
enable-rcon=off
rcon.password=vRS+68dQ8n
auto-save=on
view-distance=8
xbox-auth=on
```

4.1.2 pocketmine.yml

```

# Main configuration file for PocketMine-MP
# These settings are the ones that cannot be included in server.properties
# Some of these settings are safe, others can break your server if modified,
↳incorrectly
# New settings/defaults won't appear automatically in this file when upgrading.

settings:
  #Whether to send all strings translated to server locale or let the device handle,
↳them
  force-language: false
  shutdown-message: "Server closed"
  #Allow listing plugins via Query
  query-plugins: true
  #Show a console message when a plugin uses deprecated API methods
  deprecated-verbose: true
  #Enable plugin and core profiling by default
  enable-profiling: false
  #Will only add results when tick measurement is below or equal to given value,
↳(default 20)
  profile-report-trigger: 20
  #Number of AsyncTask workers.
  #Used for plugin asynchronous tasks, world generation, compression and web,
↳communication.
  #Set this approximately to your number of cores.
  #If set to auto, it'll try to detect the number of cores (or use 2)
  async-workers: auto
  #Whether to allow running development builds. Dev builds might crash, break your,
↳plugins, corrupt your world and more.
  #It is recommended to avoid using development builds where possible.
  enable-dev-builds: false

memory:
  #Global soft memory limit in megabytes. Set to 0 to disable
  #This will trigger low-memory-triggers and fire an event to free memory when the,
↳usage goes over this
  global-limit: 0

  #Main thread soft memory limit in megabytes. Set to 0 to disable
  #This will trigger low-memory-triggers and fire an event to free memory when the,
↳usage goes over this
  main-limit: 0

  #Main thread hard memory limit in megabytes. Set to 0 to disable
  #This will stop the server when the limit is surpassed
  main-hard-limit: 1024

  #AsyncWorker threads' hard memory limit in megabytes. Set to 0 to disable
  #This will crash the task currently executing on the worker if the task exceeds the,
↳limit
  #NOTE: THIS LIMIT APPLIES PER WORKER, NOT TO THE WHOLE PROCESS.
  async-worker-hard-limit: 256

  #Period in ticks to check memory (default 1 second)
  check-rate: 20

```

(continues on next page)

(continued from previous page)

```

#Continue firing low-memory-triggers and event while on low memory
continuous-trigger: true

#Only if memory.continuous-trigger is enabled. Specifies the rate in memory.check-
↪rate steps (default 30 seconds)
continuous-trigger-rate: 30

garbage-collection:
  #Period in ticks to fire the garbage collector manually (default 30 minutes), set_
  ↪to 0 to disable
  #This only affects the main thread. Other threads should fire their own collections
  period: 36000

  #Fire asynchronous tasks to collect garbage from workers
  collect-async-worker: true

  #Trigger on low memory
  low-memory-trigger: true

#Settings controlling memory dump handling.
memory-dump:
  #Dump memory from async workers as well as the main thread. If you have issues with_
  ↪segfaults when dumping memory, disable this setting.
  dump-async-worker: true

max-chunks:
  #Cap maximum render distance per player when low memory is triggered. Set to 0 to_
  ↪disable cap.
  chunk-radius: 4

  #Do chunk garbage collection on trigger
  trigger-chunk-collect: true

world-caches:
  #Disallow adding to world chunk-packet caches when memory is low
  disable-chunk-cache: true
  #Clear world caches when memory is low
  low-memory-trigger: true

network:
  #Threshold for batching packets, in bytes. Only these packets will be compressed
  #Set to 0 to compress everything, -1 to disable.
  batch-threshold: 256
  #Compression level used when sending batched packets. Higher = more CPU, less_
  ↪bandwidth usage
  compression-level: 7
  #Use AsyncTasks for compression. Adds half/one tick delay, less CPU load on main_
  ↪thread
  async-compression: false
  #Experimental, only for Windows. Tries to use UPnP to automatically port forward
  upnp-forwarding: false
  #Maximum size in bytes of packets sent over the network (default 1492 bytes)._
  ↪Packets larger than this will be
  #fragmented or split into smaller parts. Clients can request MTU sizes up to but not_
  ↪more than this number.
  max-mtu-size: 1492

```

(continues on next page)

(continued from previous page)

```
debug:
  #If > 1, it will show debug messages in the console
  level: 1

player:
  #Choose whether to enable player data saving.
  save-player-data: true
  anti-cheat:
    #If false, will try to prevent speed and noclip cheats. May cause movement issues.
    allow-movement-cheats: true

level-settings:
  #The default format that levels will use when created
  default-format: pmanvil
  #Automatically change levels tick rate to maintain 20 ticks per second
  auto-tick-rate: true
  auto-tick-rate-limit: 20
  #Sets the base tick rate (1 = 20 ticks per second, 2 = 10 ticks per second, etc.)
  base-tick-rate: 1
  #Tick all players each tick even when other settings disallow this.
  always-tick-players: false

chunk-sending:
  #To change server normal render distance, change view-distance in server.properties.
  #Amount of chunks sent to players per tick
  per-tick: 4
  #Radius of chunks that need to be sent before spawning the player
  spawn-radius: 4

chunk-ticking:
  #Max amount of chunks processed each tick
  per-tick: 40
  #Radius of chunks around a player to tick
  tick-radius: 3
  light-updates: false
  clear-tick-list: true
  #IDs of blocks not to perform random ticking on.
  disable-block-ticking:
    #- 2 # grass

chunk-generation:
  #Max. amount of chunks in the waiting queue to be populated
  population-queue-size: 8

ticks-per:
  autosave: 6000

auto-report:
  #Send crash reports for processing
  enabled: true
  send-code: true
  send-settings: true
  send-phpinfo: false
  use-https: true
  host: crash.pmmp.io
```

(continues on next page)

(continued from previous page)

```
anonymous-statistics:
  #Sends anonymous statistics for data aggregation, plugin usage tracking
  enabled: false #TODO: re-enable this when we have a new stats host
  host: stats.pocketmine.net

auto-updater:
  enabled: true
  on-update:
    warn-console: true
    warn-ops: true
  #Can be development, alpha, beta or stable.
  preferred-channel: stable
  #If using a development version, it will suggest changing the channel
  suggest-channels: true
  host: update.pmmp.io

timings:
  #Choose the host to use for viewing your timings results.
  host: timings.pmmp.io

console:
  #Choose whether to enable server stats reporting on the console title.
  #NOTE: The title ticker will be disabled regardless if console colours are not
  ↪enabled.
  title-tick: true

aliases:
  #Examples:
  #showtheversion: version
  #savestop: [save-all, stop]

worlds:
  #These settings will override the generator set in server.properties and allows
  ↪loading multiple levels
  #Example:
  #world:
  # seed: 404
  # generator: FLAT:2;7,59x1,3x3,2;1;decoration(treecount=80 grasscount=45)

plugins:
  #Setting this to true will cause the legacy structure to be used where plugin data
  ↪is placed inside the --plugins dir.
  #False will place plugin data under plugin_data under --data.
  #This option exists for backwards compatibility with existing installations.
  legacy-data-dir: false
```


5.1 Installation

5.1.1 Failed loading opcache.so (or other PHP extensions)

This may happen when the installer is not used or when PocketMine-MP was moved.

To fix this issue, run the following from wherever your PHP bin directory is:

```
EXTENSION_DIR=$(find "$(pwd)/bin" -name *debug-zts*)
grep -q '^extension_dir' bin/php7/bin/php.ini && sed -i'bak' "s{^extension_dir=.*
↪{extension_dir=\"${EXTENSION_DIR}\"} bin/php7/bin/php.ini || echo "extension_dir=\"
↪${EXTENSION_DIR}\"" >> bin/php7/bin/php.ini
```

This will locate your PHP binary's extension_dir on the disk and set it into php.ini, replacing it if it already exists, and adding it if not.

5.1.2 Can't install as user root

Warning: This script is running as root, this is discouraged. It is recommended to run it as a normal user as it doesn't need further permissions.

We recommend you to install PocketMine-MP as a normal user, not as root. Create one if you don't have one.

```
useradd -d /home/pocketmine -m pocketmine
passwd pocketmine
```

5.1.3 Can I install PocketMine-MP on Windows XP?

PocketMine-MP can not be installed on Windows XP. Is it an old computer? Try Linux!

5.2 Connecting

5.2.1 Can't connect to the server after updating Minecraft

Newer versions of Minecraft Bedrock often bring breaking network changes unpredictably. If you are unable to connect after updating your version, it is likely that you need to update your server version to a newer one that supports the version you're trying to connect with.

Often, **but not always**, newer patch versions (e.g. 1.2.7, 1.2.8, 1.2.9) are compatible without any update needed. Look for the latest version which offers a version less than or equal to yours.

Run the `version` command to check the supported Minecraft version of your server.

Example:

```
for Minecraft: PE v1.2.7 (protocol version 160)
```


5.2.2 What does “Opening server on 0.0.0.0:19132” mean?

0.0.0.0 means “all IPv4 addresses on the local machine”. If a host has two ip addresses, 192.168.1.1 and 10.1.2.1, and a server running on the host listens on 0.0.0.0, it will be reachable at **both** of those IPs.

5.2.3 How do I add an external server which is not on my network?

To connect to a server by IP/address and port, you need to add it to the Servers list.






Note: A local server should show up on the Friends tab without adding the details.

5.2.4 Do I have to open ports in my firewall?

If you have a firewall set up then you need to allow access to UDP port 19132.

Note: Do you want to use **RCON**? If so, then TCP port 19132 also needs to be open.

Note: On Windows, you might get a dialog like this when you first start the server. Click “Allow access” to allow PocketMine-MP through the firewall and allow players to connect.



5.2.5 Can other users connect to my server?

Users on the same network are able to join the server. If you want other people from outside your own network to be able to join then you need to port-forward.

5.2.6 Do I have to configure port forwarding?

This is only needed when you want people from outside your network to connect. Check portforward.com or use [Google](#) to find the instructions. Use the brand and type of your router as keywords.

Note:

- UDP port: 19132 for PocketMine-MP and Query
- TCP port: 19132 for RCON

5.2.7 RakLib Thread Blocked x.x.x.x for x seconds

Timeout	Reason
5 seconds	Error on a normal MCPE packet
300 seconds	More than 5000 packets per tick from one address
600 seconds	Errors on external packet (like Query or RCON)

5.2.8 Can't connect to localhost Win10 server with Minecraft Win10 Edition

This issue occurs due to loopback restrictions on Windows 10 UWP apps. To lift this restriction, launch Windows PowerShell as an administrator and run the following:

```
CheckNetIsolation LoopbackExempt -a -n="Microsoft.MinecraftUWP_8wekyb3d8bbwe"
```

5.3 Playing

5.3.1 Why doesn't X or Y gameplay feature work on PocketMine-MP? Is it a bug?

PocketMine-MP does not have all gameplay features that Minecraft itself offers. This is because PocketMine-MP is developed by developers in their spare time who have difficulty keeping up with new Minecraft features.

Most notably, current missing features at the time of writing include mobs, redstone, minecarts and dimensions. These will be added in the future.

5.3.2 Can Minecraft: Java Edition (PC) clients connect to a PocketMine-MP server?

No, but plugins exist which add partial support for this. Look up “BigBrother” on GitHub.

5.4 Plugins

5.4.1 How do I install plugins?

PocketMine-MP plugins are usually distributed as `.phar` files (PHP Archive). Download the `.phar` file for the plugin and move it to the `plugins` folder.

5.4.2 What does “Incompatible API version” mean when loading a plugin?

This means that the version of the plugin currently installed is not compatible with the server. Check for an updated version of the plugin, ask the plugin developer to update it, or try updating it yourself.

PocketMine-MP's API frequently undergoes breaking and substantial changes. The API version exists as a way for a plugin and server to determine whether the plugin can work correctly on the server's current API.

Warning: Simply bumping the plugin's declared API version is often not enough to update a plugin. The plugin might still crash or not work as expected. Use of so-called “API updaters” is discouraged.

5.4.3 I can't get a `.phar` for a plugin. How do I create one?

You can create `.phar` files from plugin source code using the `DevTools` plugin. Instructions on how to build a `phar` from source code are given on the `README.md`.

5.4.4 Can I run a plugin from source without creating a .phar?

You can use the [DevTools](#) plugin to load source plugins (known as “folder plugins”).

Warning: It is discouraged to use either DevTools or folder plugins on a production server.

For small test plugins there is a new way, check out [this forum thread](#)

5.5 Supported MCPE Versions

To check the current PocketMine-MP supported protocol version, run the `version` command in PocketMine-MP.

Running the `version` command outputs:

```
This server is running PocketMine-MP 1.6.2dev Unleashed
implementing API version 3.0.0-ALPHA5
for Minecraft: PE v1.0.7.0 (protocol version 107)
```

The game version reported by the server is the minimum supported version. Newer **patch** versions of the game are sometimes compatible with older versions, so before asking for an updated version, try and see if you can connect to your current server first. If a version is not listed here, it usually either means that there were no protocol changes between the listed versions, so look at the newest entry before your version.

Minecraft version	Protocol version
v1.2.7.2	160
v1.2.6.55	150
v1.2.5.15	141
v1.2.5.12	140
v1.2.0.81	137
v1.2.0.31	136
v1.2.0.25	135
v1.2.0.22	134
v1.2.0.18	133
v1.2.0.11	132
v1.2.0.7	131
v1.2.0.2	130
v1.1.0.55	113
v1.1.0.9	112
v1.1.0.8	111
v1.1.0.0	110
v1.0.7.0	107
v1.0.6.0	106
v1.0.5.0	105
v1.0.4.1	102
v1.0.3.0	101
v1.0.0.0	100
v0.17.0.2	92
v0.16.0.5	91
v0.15.90.1	90
v0.15.10.0	84

Continued on next page

Table 1 – continued from previous page

Minecraft version	Protocol version
v0.15.9.0	83
v0.15.4.0	82
v0.15.0.0	81
v0.14.3.0	70
v0.14.2.0	60
v0.14.0.7	45
v0.14.0.6	44
v0.14.0.5	43
v0.14.0.4	43
v0.14.0.3	42
v0.14.0.1	41
v0.13.2.0	39
v0.13.0.4	38
v0.13.0.3	38
v0.13.0.2	37
v0.13.0.1	37
v0.11.0.14	27
v0.11.0.11	26
v0.11.0.8	25
v0.11.0.7	24
v0.11.0.5	23
v0.11.0.4	22
v0.11.0.1	21
v0.10.0.6	20
v0.10.0.1	19
v0.9.5.0	18
v0.9.0.12	17
v0.9.0.7	16
v0.9.0.2	15
v0.8.1.0	14
v0.7.4.0	12
v0.7.0.0	11
v0.6.1.0	9
v0.6.0.0	9
v0.5.0.0	8
v0.4.0.0	7
v0.3.3.0	6
v0.3.2.0	5
v0.3.0.0	4
v0.2.2.0	3
v0.2.1.0	3
v0.2.0.0	2
v0.1.3.0	
v0.1.2.0	
v0.1.1.0	
v0.1.0.0	

Did your server crash, or did you encounter a bug?

- Make sure you're using the latest available version of PocketMine-MP, as the bug might already have been fixed.
- Try and reproduce it **WITHOUT PLUGINS**, as plugins can frequently cause issues.
- Ask for help on our [forums](#) before creating an issue.

Warning: Please **do not** use our issue tracker for support requests, but instead seek assistance on the [forums](#). Support request issues will be closed as per the contribution guidelines.


Note: Make sure you read the [contribution guidelines](#) before creating an issue.

If your issue is still unresolved and you're sure the issue is caused by PocketMine-MP itself, then [make a new issue](#) on GitHub.

6.1 Issue template

An issue template is provided, showing the information that we require for an issue submission. **Do not** just delete the template - fill it with the information it asks for. Give as much information as you can about when or what happened.

Before you open an issue please review the [contributing](#) guidelines for this repository.



The screenshot shows a GitHub issue creation form. The title is "Crash (with crashdump) when an invalid port is chosen in server.properties". The form is filled with the following content:

Write | Preview | AA ▾ B i “ ‹ › ☰ ☷ ☹ ↶ @ 📎

Issue description
The server crashes and creates a [crashdump](#) if the port set in server.properties is not valid.

Steps to reproduce the issue
1. set port in server.properties to `65537` or similar
2. start the server

OS and versions
* [PocketMine-MP: 1.7dev-47](#)
* [PHP: 7.2.0RC2](#)
* Server OS: Windows 10
* Game version: [PE/Win10](#) (delete as appropriate)

Plugins
- Test on a clean server without plugins: is the issue reproducible without any plugins loaded? yes

Crashdump, backtrace or other files
<https://crash.pmmp.io/view/5555>

Attach files by dragging & dropping, [selecting them](#), or pasting from the clipboard.

📄 Styling with Markdown is supported

Submit new issue

On the right side, there are settings for Assignees (No one—assign yourself), Labels (None yet), Projects (None yet), and Milestone (No milestone).

6.2 Crashdumps

Did the server crash and generate a crash dump? When the server creates a crashdump, it attempts to send it to our crash archive (unless the user disables this in their pocketmine.yml).

If it succeeds, you will see a message like this: [18:34:15] [Server thread/EMERGENCY]: The crash dump has been automatically submitted to the Crash Archive. You can view it on <https://crash.pmmp.io/view/5555> or use the ID #5555.

When you create your issue, please include the link to your crashdump to help us diagnose the problem.

If you don't have a link but have a crashdump, you can submit it manually at <https://crash.pmmp.io/submit>

Error: Please **DO NOT** paste crashdump contents into an issue. Upload it to the [Crash Archive](#) instead.

CHAPTER 7

Contact and Support

- [Forums](#)
- [Community Discord](#)

8.1 Downloads

8.1.1 PocketMine-MP prebuilt phars

- [GitHub Releases](#) - Downloads of PocketMine-MP release phars can be found here.
- [Jenkins server](#) - Advanced users and/or developers may wish to use Jenkins to download development and/or pre-release builds (not recommended for most users).

Error: Please AVOID using development builds where possible.

8.1.2 Linux & MacOS installer script

- [Linux & MacOS install script source](#)

8.1.3 Prebuilt PHP binaries and related packages

Linux, Windows & MacOS

- [PHP 7.2](#)
- (Windows only) [Microsoft Visual C++ 2017 Redistributable](#)

Note: If there are no prebuilt binaries of the version you want available for your platform, you may be able to build your own using our [compile scripts](#).

8.2 Other links

- [PMMP GitHub organisation](#)
- [PocketMine-MP GitHub repository](#)
- [PHP compile scripts](#)
- [PMMP Website](#)
- [PMMP Forums](#)
- [PocketMine-MP Translation Project](#)