
SoftLayer API Python Client Documentation

Release latest

SoftLayer Technologies, Inc.

Feb 22, 2018

1	Installation	3
1.1	What's Included	3
1.2	Using Pip	3
1.3	Debian/Ubuntu	3
1.4	From Source	3
2	Configuration File	5
3	API Documentation	7
3.1	Getting Started	7
3.2	Managers	8
3.2.1	SoftLayer.block	8
3.2.2	SoftLayer.cdn	13
3.2.3	SoftLayer.dedicatedhost	14
3.2.4	SoftLayer.dns	16
3.2.5	SoftLayer.file	17
3.2.6	SoftLayer.firewall	22
3.2.7	SoftLayer.hardware	24
3.2.8	SoftLayer.image	28
3.2.9	SoftLayer.ipsec	29
3.2.10	SoftLayer.load_balancer	33
3.2.11	SoftLayer.messaging	35
3.2.12	SoftLayer.metadata	39
3.2.13	SoftLayer.network	40
3.2.14	SoftLayer.ordering	44
3.2.15	SoftLayer.sshkey	48
3.2.16	SoftLayer.ssl	49
3.2.17	SoftLayer.ticket	51
3.2.18	SoftLayer.vs	52
3.3	Making API Calls	60
3.4	API Reference	61
3.4.1	SoftLayer Python API Client	61
4	Command-line Interface	65
4.1	Interacting with IPSEC Tunnels	65
4.1.1	ipsec list	65
4.1.2	ipsec detail	66

4.1.3	ipsec update	67
4.1.4	ipsec configure	68
4.1.5	ipsec subnet-add	68
4.1.6	ipsec subnet-remove	68
4.1.7	ipsec translation-add	69
4.1.8	ipsec translation-remove	69
4.1.9	ipsec translation-update	69
4.2	Working with Virtual Servers	69
4.3	Ordering	74
4.3.1	order package-list	74
4.3.2	order category-list	75
4.3.3	order item-list	75
4.3.4	order preset-list	75
4.3.5	order place	75
4.4	Configuration Setup	76
4.5	Usage Examples	77
5	Contributing	81
5.1	Contribution Guide	81
5.1.1	Code Organization	81
5.1.2	Setting Up A Dev Environment	81
5.1.3	Testing	82
5.1.4	Documentation	82
5.1.5	Style	82
5.1.6	Contributing	83
5.1.7	Developer Resources	83
5.2	Command-Line Interface Developer Guide	83
5.2.1	First Example	83
5.2.2	Arguments	84
5.2.3	Accessing the API	85
5.2.4	Aborting execution	85
6	External Links	87
	Python Module Index	89

[API Docs](#) | [GitHub](#) | [Issues](#) | [Pull Requests](#) | [PyPI](#) | [Twitter](#) | [#softlayer on freenode](#)

This is the documentation to SoftLayer's Python API Bindings. These bindings use SoftLayer's [XML-RPC](#) interface in order to manage SoftLayer services.

1.1 What's Included

When you install `softlayer-python` you will get the following:

- a python package called 'SoftLayer' (casing is important) available in your python path.
- a command-line client placed in your system path named 'slcli'.

1.2 Using Pip

Install via pip:

```
$ pip install softlayer
```

1.3 Debian/Ubuntu

For Debian “jessie” (currently testing) and Ubuntu 14.04, official system packages are available. **These are typically a couple versions behind so it is recommended to install from pypi if problems are encountered.**

```
$ sudo apt-get install python-softlayer
```

1.4 From Source

The project is developed on GitHub, at <https://github.com/softlayer/softlayer-python>.

Install from source via pip (requires git):

```
$ pip install git+git://github.com/softlayer/softlayer-python.git
```

You can clone the public repository:

```
$ git clone git@github.com:softlayer/softlayer-python.git
```

Or, Download the [tarball](#):

```
$ curl -OL https://github.com/softlayer/softlayer-python/tarball/master
```

Or, download the [zipball](#):

```
$ curl -OL https://github.com/softlayer/softlayer-python/zipball/master
```

Once you have a copy of the source you can install it with one of the following commands:

```
$ python setup.py install
```

Or:

```
$ pip install .
```

For more information about working with the source, or contributing to the project, please see the [Contribution Guide](#).

Configuration File

The SoftLayer API bindings load your settings from a number of different locations.

- Input directly into `SoftLayer.create_client_from_env(...)`
- Environment variables (`SL_USERNAME`, `SL_API_KEY`)
- Config file locations (`~/.softlayer`, `/etc/softlayer.conf`)
- Or argument (`-C/path/to/config` or `-config=/path/to/config`)

The configuration file is INI-based and requires the `softlayer` section to be present. The only required fields are `username` and `api_key`. You can optionally supply the `endpoint_url` as well. This file is created automatically by the `slcli setup` command detailed here: [Configuration Setup](#).

Config Example

```
[softlayer]
username = username
api_key = oyVmeipYQCNrjVS4rF9bHWV7D75S6pa1fghF1384v7mwRCbHTfuJ8qRORIqoVnha
endpoint_url = https://api.softlayer.com/xmlrpc/v3/
timeout = 40
```


This is the primary API client to make API calls. It deals with constructing and executing XML-RPC calls against the SoftLayer API. Below are some links that will help to use the SoftLayer API.

- [SoftLayer API Documentation](#)
- [Source on GitHub](#)

```
>>> import SoftLayer
>>> client = SoftLayer.create_client_from_env(username="username", api_key="api_key")
>>> resp = client.call('Account', 'getObject')
>>> resp['companyName']
'Your Company'
```

3.1 Getting Started

You can pass in your username and api_key when creating a SoftLayer client instance. However, you can also set these in the environmental variables 'SL_USERNAME' and 'SL_API_KEY'.

Creating a client instance by passing in the username/api_key:

```
import SoftLayer
client = SoftLayer.create_client_from_env(username='YOUR_USERNAME', api_key='YOUR_API_
↪KEY')
```

Creating a client instance with environmental variables set:

```
$ export SL_USERNAME=YOUR_USERNAME
$ export SL_API_KEY=YOUR_API_KEY
$ python
>>> import SoftLayer
>>> client = SoftLayer.create_client_from_env()
```

Below is an example of creating a client instance with more options. This will create a client with the private API endpoint (only accessible from the SoftLayer private network) and a timeout of 4 minutes.

```
client = SoftLayer.create_client_from_env(username='YOUR_USERNAME',
                                         api_key='YOUR_API_KEY',
                                         endpoint_url=SoftLayer.API_PRIVATE_ENDPOINT,
                                         timeout=240)
```

3.2 Managers

For day-to-day operation, most users will find the managers to be the most convenient means for interacting with the API. Managers abstract a lot of the complexities of using the API into classes that provide a simpler interface to various services. These are higher-level interfaces to the SoftLayer API.

```
from SoftLayer import VSManger, Client
client = Client(...)
vs = VSManger(client)
vs.list_instances()
[...]
```

Available managers:

3.2.1 SoftLayer.block

Block Storage Manager

license MIT, see LICENSE for more details.

class `SoftLayer.managers.block.BlockStorageManager` (*client*)

Manages SoftLayer Block Storage volumes.

See product information here: <http://www.softlayer.com/block-storage>

Parameters *client* (`SoftLayer.API.BaseClient`) – the client instance

authorize_host_to_volume (*volume_id*, *hardware_ids=None*, *virtual_guest_ids=None*, *ip_address_ids=None*, ***kwargs*)

Authorizes hosts to Block Storage Volumes

Parameters

- **volume_id** – The Block volume to authorize hosts to
- **hardware_ids** – A List of `SoftLayer_Hardware` ids
- **virtual_guest_ids** – A List of `SoftLayer_Virtual_Guest` ids
- **ip_address_ids** – A List of `SoftLayer_Network_Subnet_IpAddress` ids

Returns Returns an array of `SoftLayer_Network_Storage_Allowed_Host` objects which now have access to the given Block volume

cancel_block_volume (*volume_id*, *reason='No longer needed'*, *immediate=False*)

Cancels the given block storage volume.

Parameters

- **volume_id** (*integer*) – The volume ID
- **reason** (*string*) – The reason for cancellation

- **immediate_flag** (*boolean*) – Cancel immediately or on anniversary date

cancel_snapshot_space (*volume_id, reason='No longer needed', immediate=False*)
Cancels snapshot space for a given volume.

Parameters

- **volume_id** (*integer*) – The volume ID
- **reason** (*string*) – The reason for cancellation
- **immediate_flag** (*boolean*) – Cancel immediately or on anniversary date

create_or_update_lun_id (*volume_id, lun_id*)
Set the LUN ID on a volume.

Parameters

- **volume_id** (*integer*) – The id of the volume
- **lun_id** (*integer*) – LUN ID to set on the volume

Returns a SoftLayer_Network_Storage_Property object

create_snapshot (*volume_id, notes="", **kwargs*)
Creates a snapshot on the given block volume.

Parameters

- **volume_id** (*integer*) – The id of the volume
- **notes** (*string*) – The notes or “name” to assign the snapshot

Returns Returns the id of the new snapshot

deauthorize_host_to_volume (*volume_id, hardware_ids=None, virtual_guest_ids=None, ip_address_ids=None, **kwargs*)
Revokes authorization of hosts to Block Storage Volumes

Parameters

- **volume_id** – The Block volume to deauthorize hosts to
- **hardware_ids** – A List of SoftLayer_Hardware ids
- **virtual_guest_ids** – A List of SoftLayer_Virtual_Guest ids
- **ip_address_ids** – A List of SoftLayer_Network_Subnet_IpAddress ids

Returns Returns an array of SoftLayer_Network_Storage_Allowed_Host objects which have access to the given Block volume

delete_snapshot (*snapshot_id*)
Deletes the specified snapshot object.

Parameters **snapshot_id** – The ID of the snapshot object to delete.

disable_snapshots (*volume_id, schedule_type*)
Disables snapshots for a specific block volume at a given schedule

Parameters

- **volume_id** (*integer*) – The id of the volume
- **schedule_type** (*string*) – ‘HOURLY’|‘DAILY’|‘WEEKLY’

Returns Returns whether successfully disabled or not

enable_snapshots (*volume_id*, *schedule_type*, *retention_count*, *minute*, *hour*, *day_of_week*,
***kwargs*)

Enables snapshots for a specific block volume at a given schedule

Parameters

- **volume_id** (*integer*) – The id of the volume
- **schedule_type** (*string*) – ‘HOURLY’|‘DAILY’|‘WEEKLY’
- **retention_count** (*integer*) – Number of snapshots to be kept
- **minute** (*integer*) – Minute when to take snapshot
- **hour** (*integer*) – Hour when to take snapshot
- **day_of_week** (*string*) – Day when to take snapshot

Returns Returns whether successfully scheduled or not

failback_from_replicant (*volume_id*, *replicant_id*)

Failback from a volume replicant.

Parameters

- **volume_id** (*integer*) – The id of the volume
- **replicant_id** (*integer*) – ID of replicant to failback from

Returns Returns whether failback was successful or not

failover_to_replicant (*volume_id*, *replicant_id*, *immediate=False*)

Failover to a volume replicant.

Parameters

- **volume_id** (*integer*) – The id of the volume
- **replicant_id** (*integer*) – ID of replicant to failover to
- **immediate** (*boolean*) – Flag indicating if failover is immediate

Returns Returns whether failover was successful or not

get_block_volume_access_list (*volume_id*, ***kwargs*)

Returns a list of authorized hosts for a specified volume.

Parameters

- **volume_id** – ID of volume.
- **kwargs** –

Returns Returns a list of authorized hosts for a specified volume.

get_block_volume_details (*volume_id*, ***kwargs*)

Returns details about the specified volume.

Parameters

- **volume_id** – ID of volume.
- **kwargs** –

Returns Returns details about the specified volume.

get_block_volume_snapshot_list (*volume_id*, ***kwargs*)

Returns a list of snapshots for the specified volume.

Parameters

- **volume_id** – ID of volume.
- **kwargs** –

Returns Returns a list of snapshots for the specified volume.

get_replication_locations (*volume_id*)

Acquires list of the datacenters to which a volume can be replicated.

Parameters **volume_id** – The ID of the primary volume to be replicated

Returns Returns an array of SoftLayer_Network_Storage objects

get_replication_partners (*volume_id*)

Acquires list of replicant volumes pertaining to the given volume.

Parameters **volume_id** – The ID of the primary volume to be replicated

Returns Returns an array of SoftLayer_Location objects

list_block_volumes (*datacenter=None, username=None, storage_type=None, **kwargs*)

Returns a list of block volumes.

Parameters

- **datacenter** – Datacenter short name (e.g.: dal09)
- **username** – Name of volume.
- **storage_type** – Type of volume: Endurance or Performance
- **kwargs** –

Returns Returns a list of block volumes.

list_volume_schedules (*volume_id*)

Lists schedules for a given volume

Parameters **volume_id** (*integer*) – The id of the volume

Returns Returns list of schedules assigned to a given volume

order_block_volume (*storage_type, location, size, os_type, iops=None, tier_level=None, snapshot_size=None, service_offering='storage_as_a_service', hourly_billing_flag=False*)

Places an order for a block volume.

Parameters

- **storage_type** – ‘performance’ or ‘endurance’
- **location** – Datacenter in which to order iSCSI volume
- **size** – Size of the desired volume, in GB
- **os_type** – OS Type to use for volume alignment, see help for list
- **iops** – Number of IOPs for a “Performance” order
- **tier_level** – Tier level to use for an “Endurance” order
- **snapshot_size** – The size of optional snapshot space, if snapshot space should also be ordered (None if not ordered)
- **service_offering** – Requested offering package to use in the order (‘storage_as_a_service’, ‘enterprise’, or ‘performance’)
- **hourly_billing_flag** – Billing type, monthly (False) or hourly (True), default to monthly.

order_duplicate_volume (*origin_volume_id, origin_snapshot_id=None, duplicate_size=None, duplicate_iops=None, duplicate_tier_level=None, duplicate_snapshot_size=None, hourly_billing_flag=False*)

Places an order for a duplicate block volume.

Parameters

- **origin_volume_id** – The ID of the origin volume to be duplicated
- **origin_snapshot_id** – Origin snapshot ID to use for duplication
- **duplicate_size** – Size/capacity for the duplicate volume
- **duplicate_iops** – The IOPS per GB for the duplicate volume
- **duplicate_tier_level** – Tier level for the duplicate volume
- **duplicate_snapshot_size** – Snapshot space size for the duplicate
- **hourly_billing_flag** – Billing type, monthly (False) or hourly (True), default to monthly.

Returns Returns a SoftLayer_Container_Product_Order_Receipt

order_modified_volume (*volume_id, new_size=None, new_iops=None, new_tier_level=None*)

Places an order for modifying an existing block volume.

Parameters

- **volume_id** – The ID of the volume to be modified
- **new_size** – The new size/capacity for the volume
- **new_iops** – The new IOPS for the volume
- **new_tier_level** – The new tier level for the volume

Returns Returns a SoftLayer_Container_Product_Order_Receipt

order_replicant_volume (*volume_id, snapshot_schedule, location, tier=None, os_type=None*)

Places an order for a replicant block volume.

Parameters

- **volume_id** – The ID of the primary volume to be replicated
- **snapshot_schedule** – The primary volume’s snapshot schedule to use for replication
- **location** – The location for the ordered replicant volume
- **tier** – The tier (IOPS per GB) of the primary volume
- **os_type** – The OS type of the primary volume

Returns Returns a SoftLayer_Container_Product_Order_Receipt

order_snapshot_space (*volume_id, capacity, tier, upgrade, **kwargs*)

Orders snapshot space for the given block volume.

Parameters

- **volume_id** (*integer*) – The id of the volume
- **capacity** (*integer*) – The capacity to order, in GB
- **tier** (*float*) – The tier level of the block volume, in IOPS per GB
- **upgrade** (*boolean*) – Flag to indicate if this order is an upgrade

Returns Returns a SoftLayer_Container_Product_Order_Receipt

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly 'identifier' can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

restore_from_snapshot (*volume_id, snapshot_id*)

Restores a specific volume from a snapshot

Parameters

- **volume_id** (*integer*) – The id of the volume
- **snapshot_id** (*integer*) – The id of the restore point

Returns Returns whether successfully restored or not

set_credential_password (*access_id, password*)

Sets the password for an access host

Parameters

- **access_id** (*integer*) – id of the access host
- **password** (*string*) – password to set

3.2.2 SoftLayer.cdn

CDN Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.cdn.CDNManager` (*client*)

Manage CDN accounts and content.

See product information here: <http://www.softlayer.com/content-delivery-network>

Parameters **client** (*SoftLayer.API.BaseClient*) – the client instance

add_origin (*account_id, media_type, origin_url, cname=None, secure=False*)

Adds an original pull mapping to an origin-pull.

Parameters

- **account_id** (*int*) – the numeric ID associated with the CDN account.
- **media_type** (*string*) – the media type/protocol associated with this origin pull mapping; valid values are HTTP, FLASH, and WM.
- **origin_url** (*string*) – the base URL from which content should be pulled.
- **cname** (*string*) – an optional CNAME that should be associated with this origin pull rule; only the hostname should be included (i.e., no 'http://', directories, etc.).
- **secure** (*boolean*) – specifies whether this is an SSL origin pull rule, if SSL is enabled on your account (defaults to false).

get_account (*account_id, **kwargs*)

Retrieves a CDN account with the specified account ID.

Parameters

- **int** (*account_id*) – the numeric ID associated with the CDN account.

- ****kwargs** (*dict*) – additional arguments to include in the object mask.

get_origins (*account_id*, ***kwargs*)

Retrieves list of origin pull mappings for a specified CDN account.

Parameters

- **int** (*account_id*) – the numeric ID associated with the CDN account.
- ****kwargs** (*dict*) – additional arguments to include in the object mask.

list_accounts ()

Lists CDN accounts for the active user.

load_content (*account_id*, *urls*)

Prefetches one or more URLs to the CDN edge nodes.

Parameters

- **account_id** (*int*) – the CDN account ID into which content should be preloaded.
- **urls** – a string or a list of strings representing the CDN URLs that should be pre-loaded.

Returns true if all load requests were successfully submitted; otherwise, returns the first error encountered.

purge_content (*account_id*, *urls*)

Purges one or more URLs from the CDN edge nodes.

Parameters

- **account_id** (*int*) – the CDN account ID from which content should be purged.
- **urls** – a string or a list of strings representing the CDN URLs that should be purged.

Returns true if all purge requests were successfully submitted; otherwise, returns the first error encountered.

remove_origin (*account_id*, *origin_id*)

Removes an origin pull mapping with the given origin pull ID.

Parameters

- **account_id** (*int*) – the CDN account ID from which the mapping should be deleted.
- **origin_id** (*int*) – the origin pull mapping ID to delete.

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

3.2.3 SoftLayer.dedicatedhost

DH Manager/helpers

license MIT, see License for more details.

class `SoftLayer.managers.dedicated_host.DedicatedHostManager` (*client*, *ordering_manager=None*)

Manages SoftLayer Dedicated Hosts.

See product information here <https://www.ibm.com/cloud/dedicated>

Parameters

- **client** (*SoftLayer.API.BaseClient*) – the client instance
- **ordering_manager** (*SoftLayer.managers.OrderingManager*) – an optional manager to handle ordering. If none is provided, one will be auto initialized.

get_create_options ()

Returns valid options for ordering a dedicated host.

get_host (*host_id*, ***kwargs*)

Get details about a dedicated host.

:param integer : the host ID :returns: A dictionary containing host information.

Example:

```
# Print out host ID 12345.
dh = mgr.get_host(12345)
print dh

# Print out only name and backendRouter for instance 12345
object_mask = "mask[name,backendRouter[id]]"
dh = mgr.get_host(12345, mask=mask)
print dh
```

get_router_options (*datacenter=None*, *flavor=None*)

Returns available backend routers for the dedicated host.

list_instances (*tags=None*, *cpus=None*, *memory=None*, *hostname=None*, *disk=None*, *datacenter=None*, ***kwargs*)

Retrieve a list of all dedicated hosts on the account

Parameters

- **tags** (*list*) – filter based on list of tags
- **cpus** (*integer*) – filter based on number of CPUS
- **memory** (*integer*) – filter based on amount of memory
- **hostname** (*string*) – filter based on hostname
- **disk** (*string*) – filter based on disk
- **datacenter** (*string*) – filter based on datacenter
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

Returns Returns a list of dictionaries representing the matching dedicated host.

place_order (*hostname*, *domain*, *location*, *flavor*, *hourly*, *router=None*)

Places an order for a dedicated host.

See `get_create_options()` for valid arguments.

Parameters

- **hostname** (*string*) – server hostname
- **domain** (*string*) – server domain name
- **location** (*string*) – location (datacenter) name

- **hourly** (*boolean*) – True if using hourly pricing (default). False for monthly.
- **router** (*int*) – an optional value for selecting a backend router

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

verify_order (*hostname, domain, location, hourly, flavor, router=None*)

Verifies an order for a dedicated host.

See [place_order\(\)](#) for a list of available options.

3.2.4 SoftLayer.dns

DNS Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.dns.DNSManager` (*client*)

Manage SoftLayer DNS.

See product information here: <http://www.softlayer.com/DOMAIN-SERVICES>

Parameters **client** (*SoftLayer.API.BaseClient*) – the client instance

create_record (*zone_id, record, record_type, data, ttl=60*)

Create a resource record on a domain.

Parameters

- **id** (*integer*) – the zone’s ID
- **record** – the name of the record to add
- **record_type** – the type of record (A, AAAA, CNAME, MX, TXT, etc.)
- **data** – the record’s value
- **ttl** (*integer*) – the TTL or time-to-live value (default: 60)

create_zone (*zone, serial=None*)

Create a zone for the specified zone.

Parameters

- **zone** – the zone name to create
- **serial** – serial value on the zone (default: `strftime(‘%Y%m%d01’)`)

delete_record (*record_id*)

Delete a resource record by its ID.

Parameters **id** (*integer*) – the record’s ID

delete_zone (*zone_id*)

Delete a zone by its ID.

Parameters **zone_id** (*integer*) – the zone ID to delete

dump_zone (*zone_id*)

Retrieve a zone dump in BIND format.

Parameters `id` (*integer*) – The zone ID to dump

edit_record (*record*)

Update an existing record with the options provided.

The provided dict must include an ‘id’ key and value corresponding to the record that should be updated.

Parameters `record` (*dict*) – the record to update

edit_zone (*zone*)

Update an existing zone with the options provided.

The provided dict must include an ‘id’ key and value corresponding to the zone that should be updated.

Parameters `zone` (*dict*) – the zone to update

get_record (*record_id*)

Get a DNS record.

Parameters `id` (*integer*) – the record’s ID

get_records (*zone_id*, *t11=None*, *data=None*, *host=None*, *record_type=None*)

List, and optionally filter, records within a zone.

Parameters

- **zone** – the zone name in which to search.
- **t11** (*int*) – time in seconds
- **data** (*str*) – the records data
- **host** (*str*) – record’s host
- **record_type** (*str*) – the type of record

Returns A list of dictionaries representing the matching records within the specified zone.

get_zone (*zone_id*, *records=True*)

Get a zone and its records.

Parameters `zone` – the zone name

Returns A dictionary containing a large amount of information about the specified zone.

list_zones (***kwargs*)

Retrieve a list of all DNS zones.

Parameters ***kwargs* (*dict*) – response-level options (mask, limit, etc.)

Returns A list of dictionaries representing the matching zones.

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters `identifier` (*string*) – identifying string

Returns list

3.2.5 SoftLayer.file

File Storage Manager

license MIT, see LICENSE for more details.

class SoftLayer.managers.file.**FileStorageManager** (*client*)

Manages file Storage volumes.

authorize_host_to_volume (*volume_id*, *hardware_ids=None*, *virtual_guest_ids=None*,
ip_address_ids=None, *subnet_ids=None*, ***kwargs*)
Authorizes hosts to File Storage Volumes

Parameters

- **volume_id** – The File volume to authorize hosts to
- **hardware_ids** – A List of SoftLayer_Hardware ids
- **virtual_guest_ids** – A List of SoftLayer_Virtual_Guest ids
- **ip_address_ids** – A List of SoftLayer_Network_Subnet_IpAddress ids
- **subnet_ids** – A List of SoftLayer_Network_Subnet ids

Returns Returns an array of SoftLayer_Network_Storage_Allowed_Host objects which now have access to the given File volume

cancel_file_volume (*volume_id*, *reason='No longer needed'*, *immediate=False*)
Cancels the given file storage volume.

Parameters

- **volume_id** (*integer*) – The volume ID
- **reason** (*string*) – The reason for cancellation
- **immediate** (*boolean*) – Cancel immediately or on anniversary date

cancel_snapshot_space (*volume_id*, *reason='No longer needed'*, *immediate=False*)
Cancels snapshot space for a given volume.

Parameters

- **volume_id** (*integer*) – The volume ID
- **reason** (*string*) – The reason for cancellation
- **immediate** (*boolean*) – Cancel immediately or on anniversary date

create_snapshot (*volume_id*, *notes=""*, ***kwargs*)
Creates a snapshot on the given file volume.

Parameters

- **volume_id** (*integer*) – The id of the volume
- **notes** (*string*) – The notes or “name” to assign the snapshot

Returns Returns the id of the new snapshot

deauthorize_host_to_volume (*volume_id*, *hardware_ids=None*, *virtual_guest_ids=None*,
ip_address_ids=None, *subnet_ids=None*, ***kwargs*)
Revokes authorization of hosts to File Storage Volumes

Parameters

- **volume_id** – The File volume to deauthorize hosts to
- **hardware_ids** – A List of SoftLayer_Hardware ids
- **virtual_guest_ids** – A List of SoftLayer_Virtual_Guest ids
- **ip_address_ids** – A List of SoftLayer_Network_Subnet_IpAddress ids

- **subnet_ids** – A List of SoftLayer_Network_Subnet ids

Returns Returns an array of SoftLayer_Network_Storage_Allowed_Host objects which have access to the given File volume

delete_snapshot (*snapshot_id*)

Deletes the specified snapshot object.

Parameters **snapshot_id** – The ID of the snapshot object to delete.

disable_snapshots (*volume_id, schedule_type*)

Disables snapshots for a specific file volume at a given schedule

Parameters

- **volume_id** (*integer*) – The id of the volume
- **schedule_type** (*string*) – ‘HOURLY’|‘DAILY’|‘WEEKLY’

Returns Returns whether successfully disabled or not

enable_snapshots (*volume_id, schedule_type, retention_count, minute, hour, day_of_week, **kwargs*)

Enables snapshots for a specific file volume at a given schedule

Parameters

- **volume_id** (*integer*) – The id of the volume
- **schedule_type** (*string*) – ‘HOURLY’|‘DAILY’|‘WEEKLY’
- **retention_count** (*integer*) – The number of snapshots to attempt to retain in this schedule
- **minute** (*integer*) – The minute of the hour at which HOURLY, DAILY, and WEEKLY snapshots should be taken
- **hour** (*integer*) – The hour of the day at which DAILY and WEEKLY snapshots should be taken
- **day_of_week** (*string|integer*) – The day of the week on which WEEKLY snapshots should be taken, either as a string (‘SUNDAY’) or integer (‘0’ is Sunday)

Returns Returns whether successfully scheduled or not

failback_from_replicant (*volume_id, replicant_id*)

Failback from a volume replicant.

Parameters

- **volume_id** (*integer*) – The ID of the volume
- **replicant_id** (*integer*) – ID of replicant to failback from

Returns Returns whether failback was successful or not

failover_to_replicant (*volume_id, replicant_id, immediate=False*)

Failover to a volume replicant.

Parameters

- **volume_id** (*integer*) – The ID of the volume
- **replicant_id** (*integer*) – ID of replicant to failover to
- **immediate** (*boolean*) – Flag indicating if failover is immediate

Returns Returns whether failover was successful or not

get_file_volume_access_list (*volume_id*, ***kwargs*)

Returns a list of authorized hosts for a specified volume.

Parameters

- **volume_id** – ID of volume.
- **kwargs** –

Returns Returns a list of authorized hosts for a specified volume.

get_file_volume_details (*volume_id*, ***kwargs*)

Returns details about the specified volume.

Parameters

- **volume_id** – ID of volume.
- **kwargs** –

Returns Returns details about the specified volume.

get_file_volume_snapshot_list (*volume_id*, ***kwargs*)

Returns a list of snapshots for the specified volume.

Parameters

- **volume_id** – ID of volume.
- **kwargs** –

Returns Returns a list of snapshots for the specified volume.

get_replication_locations (*volume_id*)

Acquires list of the datacenters to which a volume can be replicated.

Parameters **volume_id** – The ID of the primary volume to be replicated

Returns Returns an array of SoftLayer_Network_Storage objects

get_replication_partners (*volume_id*)

Acquires list of replicant volumes pertaining to the given volume.

Parameters **volume_id** – The ID of the primary volume to be replicated

Returns Returns an array of SoftLayer_Location objects

list_file_volumes (*datacenter=None*, *username=None*, *storage_type=None*, ***kwargs*)

Returns a list of file volumes.

Parameters

- **datacenter** – Datacenter short name (e.g.: dal09)
- **username** – Name of volume.
- **storage_type** – Type of volume: Endurance or Performance
- **kwargs** –

Returns Returns a list of file volumes.

list_volume_schedules (*volume_id*)

Lists schedules for a given volume

Parameters **volume_id** (*integer*) – The id of the volume

Returns Returns list of schedules assigned to a given volume

order_duplicate_volume (*origin_volume_id, origin_snapshot_id=None, duplicate_size=None, duplicate_iops=None, duplicate_tier_level=None, duplicate_snapshot_size=None, hourly_billing_flag=False*)

Places an order for a duplicate file volume.

Parameters

- **origin_volume_id** – The ID of the origin volume to be duplicated
- **origin_snapshot_id** – Origin snapshot ID to use for duplication
- **duplicate_size** – Size/capacity for the duplicate volume
- **duplicate_iops** – The IOPS per GB for the duplicate volume
- **duplicate_tier_level** – Tier level for the duplicate volume
- **duplicate_snapshot_size** – Snapshot space size for the duplicate
- **hourly_billing_flag** – Billing type, monthly (False) or hourly (True), default to monthly.

Returns Returns a SoftLayer_Container_Product_Order_Receipt

order_file_volume (*storage_type, location, size, iops=None, tier_level=None, snapshot_size=None, service_offering='storage_as_a_service', hourly_billing_flag=False*)

Places an order for a file volume.

Parameters

- **storage_type** – ‘performance’ or ‘endurance’
- **location** – Name of the datacenter in which to order the volume
- **size** – Size of the desired volume, in GB
- **iops** – Number of IOPs for a “Performance” order
- **tier_level** – Tier level to use for an “Endurance” order
- **snapshot_size** – The size of optional snapshot space, if snapshot space should also be ordered (None if not ordered)
- **service_offering** – Requested offering package to use in the order (‘storage_as_a_service’, ‘enterprise’, or ‘performance’)
- **hourly_billing_flag** – Billing type, monthly (False) or hourly (True), default to monthly.

order_modified_volume (*volume_id, new_size=None, new_iops=None, new_tier_level=None*)

Places an order for modifying an existing file volume.

Parameters

- **volume_id** – The ID of the volume to be modified
- **new_size** – The new size/capacity for the volume
- **new_iops** – The new IOPS for the volume
- **new_tier_level** – The new tier level for the volume

Returns Returns a SoftLayer_Container_Product_Order_Receipt

order_replicant_volume (*volume_id, snapshot_schedule, location, tier=None*)

Places an order for a replicant file volume.

Parameters

- **volume_id** – The ID of the primary volume to be replicated
- **snapshot_schedule** – The primary volume’s snapshot schedule to use for replication
- **location** – The location for the ordered replicant volume
- **tier** – The tier (IOPS per GB) of the primary volume

Returns Returns a SoftLayer_Container_Product_Order_Receipt

order_snapshot_space (*volume_id, capacity, tier, upgrade, **kwargs*)
Orders snapshot space for the given file volume.

Parameters

- **volume_id** (*integer*) – The ID of the volume
- **capacity** (*integer*) – The capacity to order, in GB
- **tier** (*float*) – The tier level of the file volume, in IOPS per GB
- **upgrade** (*boolean*) – Flag to indicate if this order is an upgrade

Returns Returns a SoftLayer_Container_Product_Order_Receipt

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

restore_from_snapshot (*volume_id, snapshot_id*)

Restores a specific volume from a snapshot

Parameters

- **volume_id** (*integer*) – The ID of the volume
- **snapshot_id** (*integer*) – The id of the restore point

Returns Returns whether successfully restored or not

3.2.6 SoftLayer.firewall

Firewall Manager/helpers

license MIT, see LICENSE for more details.

class SoftLayer.managers.firewall.**FirewallManager** (*client*)

Manages SoftLayer firewalls

See product information here: <http://www.softlayer.com/firewalls>

Parameters **client** (*SoftLayer.API.BaseClient*) – the client instance

add_standard_firewall (*server_id, is_virt=True*)

Creates a firewall for the specified virtual/hardware server.

Parameters

- **server_id** (*int*) – The ID of the server to create the firewall for

- **is_virt** (*bool*) – If true, will create the firewall for a virtual server, otherwise for a hardware server.

Returns A dictionary containing the standard virtual server firewall order

add_vlan_firewall (*vlan_id*, *ha_enabled=False*)

Creates a firewall for the specified vlan.

Parameters

- **vlan_id** (*int*) – The ID of the vlan to create the firewall for
- **ha_enabled** (*bool*) – If True, an HA firewall will be created

Returns A dictionary containing the VLAN firewall order

cancel_firewall (*firewall_id*, *dedicated=False*)

Cancel the specified firewall.

Parameters

- **firewall_id** (*int*) – Firewall ID to be cancelled.
- **dedicated** (*bool*) – If true, the firewall instance is dedicated, otherwise, the firewall instance is shared.

edit_dedicated_fw_rules (*firewall_id*, *rules*)

Edit the rules for dedicated firewall.

Parameters

- **firewall_id** (*integer*) – the instance ID of the dedicated firewall
- **rules** (*list*) – the rules to be pushed on the firewall as defined by SoftLayer_Network_Firewall_Update_Request_Rule

edit_standard_fw_rules (*firewall_id*, *rules*)

Edit the rules for standard firewall.

Parameters

- **firewall_id** (*integer*) – the instance ID of the standard firewall
- **rules** (*dict*) – the rules to be pushed on the firewall

get_dedicated_fw_rules (*firewall_id*)

Get the rules of a dedicated firewall.

Parameters **firewall_id** (*integer*) – the instance ID of the dedicated firewall

Returns A list of the rules.

get_dedicated_package (*ha_enabled=False*)

Retrieves the dedicated firewall package.

Parameters **ha_enabled** (*bool*) – True if HA is to be enabled on the firewall False for No HA

Returns A dictionary containing the dedicated virtual server firewall package

get_firewalls ()

Returns a list of all firewalls on the account.

Returns A list of firewalls on the current account.

get_standard_fw_rules (*firewall_id*)

Get the rules of a standard firewall.

Parameters `firewall_id` (*integer*) – the instance ID of the standard firewall

Returns A list of the rules.

get_standard_package (*server_id*, *is_virt=True*)

Retrieves the standard firewall package for the virtual server.

Parameters

- **server_id** (*int*) – The ID of the server to create the firewall for
- **is_virt** (*bool*) – True if the ID provided is for a virtual server, False for a server

Returns A dictionary containing the standard virtual server firewall package

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

`SoftLayer.managers.firewall.has_firewall` (*vlan*)

Helper to determine whether or not a VLAN has a firewall.

Parameters **vlan** (*dict*) – A dictionary representing a VLAN

Returns True if the VLAN has a firewall, false if it doesn't.

3.2.7 SoftLayer.hardware

Hardware Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.hardware.HardwareManager` (*client*, *ordering_manager=None*)

Manage SoftLayer hardware servers.

Example:

```
# Initialize the Manager.
# env variables. These can also be specified in ~/.softlayer,
# or passed directly to SoftLayer.Client()
# SL_USERNAME = YOUR_USERNAME
# SL_API_KEY = YOUR_API_KEY
import SoftLayer
client = SoftLayer.Client()
mgr = SoftLayer.HardwareManager(client)
```

See product information here: <http://www.softlayer.com/bare-metal-servers>

Parameters

- **client** (*SoftLayer.API.BaseClient*) – the client instance
- **ordering_manager** (*SoftLayer.managers.OrderingManager*) – an optional manager to handle ordering. If none is provided, one will be auto initialized.

cancel_hardware (*hardware_id*, *reason='unneeded'*, *comment=""*, *immediate=False*)

Cancels the specified dedicated server.

Example:

```
# Cancels hardware id 1234
result = mgr.cancel_hardware(hardware_id=1234)
```

Parameters

- **hardware_id** (*int*) – The ID of the hardware to be cancelled.
- **reason** (*string*) – The reason code for the cancellation. This should come from `get_cancellation_reasons()`.
- **comment** (*string*) – An optional comment to include with the cancellation.

change_port_speed (*hardware_id, public, speed*)

Allows you to change the port speed of a server's NICs.

Parameters

- **hardware_id** (*int*) – The ID of the server
- **public** (*bool*) – Flag to indicate which interface to change. True (default) means the public interface. False indicates the private interface.
- **speed** (*int*) – The port speed to set.

Warning: A port speed of 0 will disable the interface.

Example:

```
#change the Public interface to 10Mbps on instance 12345
result = mgr.change_port_speed(hardware_id=12345,
                               public=True, speed=10)
# result will be True or an Exception
```

edit (*hardware_id, userdata=None, hostname=None, domain=None, notes=None, tags=None*)

Edit hostname, domain name, notes, user data of the hardware.

Parameters set to None will be ignored and not attempted to be updated.

Parameters

- **hardware_id** (*integer*) – the instance ID to edit
- **userdata** (*string*) – user data on the hardware to edit. If none exist it will be created
- **hostname** (*string*) – valid hostname
- **domain** (*string*) – valid domain name
- **notes** (*string*) – notes about this particular hardware
- **tags** (*string*) – tags to set on the hardware as a comma separated list. Use the empty string to remove all tags.

Example:

```
# Change the hostname on instance 12345 to 'something'
result = mgr.edit(hardware_id=12345 , hostname="something")
#result will be True or an Exception
```

get_cancellation_reasons ()

Returns a dictionary of valid cancellation reasons.

These can be used when cancelling a dedicated server via `cancel_hardware()`.

get_create_options (*args, **kwargs)

Returns valid options for ordering hardware.

get_hardware (*args, **kwargs)

Get details about a hardware device.

Parameters `id` (*integer*) – the hardware ID

Returns A dictionary containing a large amount of information about the specified server.

Example:

```
object_mask = "mask[id,networkVlans[vlanNumber]]"
# Object masks are optional
result = mgr.get_hardware(hardware_id=1234,mask=object_mask)
```

list_hardware (*args, **kwargs)

List all hardware (servers and bare metal computing instances).

param list tags filter based on tags

param integer cpus filter based on number of CPUS

param integer memory filter based on amount of memory in gigabytes

param string hostname filter based on hostname

param string domain filter based on domain

param string datacenter filter based on datacenter

param integer nic_speed filter based on network speed (in MBPS)

param string public_ip filter based on public ip address

param string private_ip filter based on private ip address

param dict **kwargs response-level options (mask, limit, etc.)

returns Returns a list of dictionaries representing the matching hardware. This list will contain both dedicated servers and bare metal computing instances

Example:

```
# Using a custom object-mask. Will get ONLY what is specified
# These will stem from the SoftLayer_Hardware_Server datatype
object_mask = "mask[hostname,monitoringRobot[robotStatus]]"
result = mgr.list_hardware(mask=object_mask)
```

place_order (**kwargs)

Places an order for a piece of hardware.

See `get_create_options()` for valid arguments.

Parameters

- **size** (*string*) – server size name or presetId
- **hostname** (*string*) – server hostname
- **domain** (*string*) – server domain name

- **location** (*string*) – location (datacenter) name
- **os** (*string*) – operating system name
- **port_speed** (*int*) – Port speed in Mbps
- **ssh_keys** (*list*) – list of ssh key ids
- **post_uri** (*string*) – The URI of the post-install script to run after reload
- **hourly** (*boolean*) – True if using hourly pricing (default). False for monthly.
- **no_public** (*boolean*) – True if this server should only have private interfaces
- **extras** (*list*) – List of extra feature names

reload (*hardware_id*, *post_uri=None*, *ssh_keys=None*)

Perform an OS reload of a server with its current configuration.

Parameters

- **hardware_id** (*integer*) – the instance ID to reload
- **post_url** (*string*) – The URI of the post-install script to run after reload
- **ssh_keys** (*list*) – The SSH keys to add to the root user

rescue (*hardware_id*)

Reboot a server into the a rescue kernel.

Parameters **instance_id** (*integer*) – the server ID to rescue

Example:

```
result = mgr.rescue(1234)
```

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly 'identifier' can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

update_firmware (*hardware_id*, *ipmi=True*, *raid_controller=True*, *bios=True*, *hard_drive=True*)

Update hardware firmware.

This will cause the server to be unavailable for ~20 minutes.

Parameters

- **hardware_id** (*int*) – The ID of the hardware to have its firmware updated.
- **ipmi** (*bool*) – Update the ipmi firmware.
- **raid_controller** (*bool*) – Update the raid controller firmware.
- **bios** (*bool*) – Update the bios firmware.
- **hard_drive** (*bool*) – Update the hard drive firmware.

Example:

```
# Check the servers active transactions to see progress
result = mgr.update_firmware(hardware_id=1234)
```

verify_order (***kwargs*)

Verifies an order for a piece of hardware.

See *place_order()* for a list of available options.

wait_for_ready (*instance_id, limit=14400, delay=10, pending=False*)

Determine if a Server is ready.

A server is ready when no transactions are running on it.

Parameters

- **instance_id** (*int*) – The instance ID with the pending transaction
- **limit** (*int*) – The maximum amount of seconds to wait.
- **delay** (*int*) – The number of seconds to sleep before checks. Defaults to 10.

3.2.8 SoftLayer.image

Image Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.image.ImageManager` (*client*)

Manages SoftLayer server images.

See product information here: <https://knowledge.softlayer.com/topic/image-templates>

Parameters **client** (*SoftLayer.API.BaseClient*) – the client instance

delete_image (*image_id*)

Deletes the specified image.

Parameters **image_id** (*int*) – The ID of the image.

edit (*image_id, name=None, note=None, tag=None*)

Edit image related details.

Parameters

- **image_id** (*int*) – The ID of the image
- **name** (*string*) – Name of the Image.
- **note** (*string*) – Note of the image.
- **tag** (*string*) – Tags of the image to be updated to.

export_image_to_uri (*image_id, uri*)

Export image into the given object storage

Parameters

- **image_id** (*int*) – The ID of the image
- **uri** (*string*) – The URI for object storage of the format `swift://<objectStorageAccount>@<cluster>/<container>/<objectPath>`

get_image (*image_id, **kwargs*)

Get details about an image.

Parameters

- **image** (*int*) – The ID of the image.
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

import_image_from_uri (*name, uri, os_code=None, note=None*)

Import a new image from object storage.

Parameters

- **name** (*string*) – Name of the new image
- **uri** (*string*) – The URI for an object storage object (.vhd/.iso file) of the format: `swift://<objectStorageAccount>@<cluster>/<container>/<objectPath>`
- **os_code** (*string*) – The reference code of the operating system
- **note** (*string*) – Note to add to the image

list_private_images (*guid=None, name=None, **kwargs*)

List all private images.

Parameters

- **guid** (*string*) – filter based on GUID
- **name** (*string*) – filter based on name
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

list_public_images (*guid=None, name=None, **kwargs*)

List all public images.

Parameters

- **guid** (*string*) – filter based on GUID
- **name** (*string*) – filter based on name
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

3.2.9 SoftLayer.ipsec

IPSec VPN Manager

license MIT, see LICENSE for more details.

class `SoftLayer.managers.ipsec.IPSECManager` (*client*)

Manage SoftLayer IPSEC VPN tunnel contexts.

This provides helpers to manage IPSEC contexts, private and remote subnets, and NAT translations.

Parameters

- **client** (*SoftLayer.API.BaseClient*) – the client instance
- **account** (*SoftLayer.API.BaseClient*) – account service client
- **context** (*SoftLayer.API.BaseClient*) – tunnel context client
- **customer_subnet** (*SoftLayer.API.BaseClient*) – remote subnet client

add_internal_subnet (*context_id, subnet_id*)

Add an internal subnet to a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **subnet_id** (*int*) – The id-value representing the internal subnet.

Return bool True if internal subnet addition was successful.

add_remote_subnet (*context_id, subnet_id*)

Adds a remote subnet to a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **subnet_id** (*int*) – The id-value representing the remote subnet.

Return bool True if remote subnet addition was successful.

add_service_subnet (*context_id, subnet_id*)

Adds a service subnet to a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **subnet_id** (*int*) – The id-value representing the service subnet.

Return bool True if service subnet addition was successful.

apply_configuration (*context_id*)

Requests network configuration for a tunnel context.

Parameters **context_id** (*int*) – The id-value representing the context instance.

Return bool True if the configuration request was successfully queued.

create_remote_subnet (*account_id, identifier, cidr*)

Creates a remote subnet on the given account.

Parameters

- **account_id** (*string*) – The account identifier.
- **identifier** (*string*) – The network identifier of the remote subnet.
- **cidr** (*string*) – The CIDR value of the remote subnet.

Return dict Mapping of properties for the new remote subnet.

create_translation (*context_id, static_ip, remote_ip, notes*)

Creates an address translation on a tunnel context/

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **static_ip** (*string*) – The IP address value representing the internal side of the translation entry,
- **remote_ip** (*string*) – The IP address value representing the remote side of the translation entry,
- **notes** (*string*) – The notes to supply with the translation entry,

Return dict Mapping of properties for the new translation entry.

delete_remote_subnet (*subnet_id*)

Deletes a remote subnet from the current account.

Parameters **subnet_id** (*string*) – The id-value representing the remote subnet.

Return bool True if subnet deletion was successful.

get_translation (*context_id, translation_id*)

Retrieves a translation entry for the given id values.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **translation_id** (*int*) – The id-value representing the translation instance.

Return dict Mapping of properties for the translation entry.

Raises *SoftLayerAPIError* – If a translation cannot be found.

get_translations (*context_id*)

Retrieves all translation entries for a tunnel context.

Parameters **context_id** (*int*) – The id-value representing the context instance.

Return list(dict) Translations associated with the given context

get_tunnel_context (*context_id, **kwargs*)

Retrieves the network tunnel context instance.

Parameters **context_id** (*int*) – The id-value representing the context instance.

Return dict Mapping of properties for the tunnel context.

Raises *SoftLayerAPIError* – If a context cannot be found.

get_tunnel_contexts (***kwargs*)

Retrieves network tunnel module context instances.

Return list(dict) Contexts associated with the current account.

remove_internal_subnet (*context_id, subnet_id*)

Remove an internal subnet from a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **subnet_id** (*int*) – The id-value representing the internal subnet.

Return bool True if internal subnet removal was successful.

remove_remote_subnet (*context_id, subnet_id*)

Removes a remote subnet from a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **subnet_id** (*int*) – The id-value representing the remote subnet.

Return bool True if remote subnet removal was successful.

remove_service_subnet (*context_id, subnet_id*)

Removes a service subnet from a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.

- **subnet_id** (*int*) – The id-value representing the service subnet.

Return bool True if service subnet removal was successful.

remove_translation (*context_id, translation_id*)

Removes a translation entry from a tunnel context.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **translation_id** (*int*) – The id-value representing the translation.

Return bool True if translation entry removal was successful.

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

update_translation (*context_id, translation_id, static_ip=None, remote_ip=None, notes=None*)

Updates an address translation entry using the given values.

Parameters

- **context_id** (*int*) – The id-value representing the context instance.
- **template** (*dict*) – A key-value mapping of translation properties.
- **static_ip** (*string*) – The static IP address value to update.
- **remote_ip** (*string*) – The remote IP address value to update.
- **notes** (*string*) – The notes value to update.

Return bool True if the update was successful.

update_tunnel_context (*context_id, friendly_name=None, remote_peer=None, preshared_key=None, phase1_auth=None, phase1_crypto=None, phase1_dh=None, phase1_key_ttl=None, phase2_auth=None, phase2_crypto=None, phase2_dh=None, phase2_forward_secrecy=None, phase2_key_ttl=None*)

Updates a tunnel context using the given values.

Parameters

- **context_id** (*string*) – The id-value representing the context.
- **friendly_name** (*string*) – The friendly name value to update.
- **remote_peer** (*string*) – The remote peer IP address value to update.
- **preshared_key** (*string*) – The preshared key value to update.
- **phase1_auth** (*string*) – The phase 1 authentication value to update.
- **phase1_crypto** (*string*) – The phase 1 encryption value to update.
- **phase1_dh** (*string*) – The phase 1 diffie hellman group value to update.
- **phase1_key_ttl** (*string*) – The phase 1 key life value to update.
- **phase2_auth** (*string*) – The phase 2 authentication value to update.
- **phase2_crypto** (*string*) – The phase 2 encryption value to update.

- **phase2_df** (*string*) – The phase 2 diffie hellman group value to update.
- **phase2_forward_secrecy** (*string*) – The phase 2 perfect forward secrecy value to update.
- **phase2_key_ttl** (*string*) – The phase 2 key life value to update.

Return bool True if the update was successful.

3.2.10 SoftLayer.load_balancer

Load Balancer Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.load_balancer.LoadBalancerManager` (*client*)
Manages SoftLayer load balancers.

See product information here: <http://www.softlayer.com/load-balancing>

Parameters **client** (*SoftLayer.API.BaseClient*) – the client instance

add_local_lb (*price_item_id, datacenter*)

Creates a local load balancer in the specified data center.

Parameters

- **price_item_id** (*int*) – The price item ID for the load balancer
- **datacenter** (*string*) – The datacenter to create the loadbalancer in

Returns A dictionary containing the product order

add_service (*loadbal_id, service_group_id, ip_address_id, port=80, enabled=True, hc_type=21, weight=1*)

Adds a new service to the service group.

Parameters

- **loadbal_id** (*int*) – The id of the loadbal where the service resides
- **service_group_id** (*int*) – The group to add the service to
- **ip_address id** (*int*) – The ip address ID of the service
- **port** (*int*) – the port of the service
- **enabled** (*bool*) – Enable or disable the service
- **hc_type** (*int*) – The health check type
- **weight** (*int*) – the weight to give to the service

add_service_group (*lb_id, allocation=100, port=80, routing_type=2, routing_method=10*)

Adds a new service group to the load balancer.

Parameters

- **loadbal_id** (*int*) – The id of the loadbal where the service resides
- **allocation** (*int*) – percent of connections to allocate toward the group
- **port** (*int*) – the port of the service group
- **routing_type** (*int*) – the routing type to set on the service group
- **routing_method** (*int*) – The routing method to set on the group

cancel_lb (*loadbal_id*)

Cancels the specified load balancer.

Parameters **loadbal_id** (*int*) – Load Balancer ID to be cancelled.

delete_service (*service_id*)

Deletes a service from the loadbal_id.

Parameters **service_id** (*int*) – The id of the service to delete

delete_service_group (*group_id*)

Deletes a service group from the loadbal_id.

Parameters **group_id** (*int*) – The id of the service group to delete

edit_service (*loadbal_id*, *service_id*, *ip_address_id=None*, *port=None*, *enabled=None*,
hc_type=None, *weight=None*)

Edits an existing service properties.

Parameters

- **loadbal_id** (*int*) – The id of the loadbal where the service resides
- **service_id** (*int*) – The id of the service to edit
- **ip_address** (*string*) – The ip address of the service
- **port** (*int*) – the port of the service
- **enabled** (*bool*) – enable or disable the search
- **hc_type** (*int*) – The health check type
- **weight** (*int*) – the weight to give to the service

edit_service_group (*loadbal_id*, *group_id*, *allocation=None*, *port=None*, *routing_type=None*,
routing_method=None)

Edit an existing service group.

Parameters

- **loadbal_id** (*int*) – The id of the loadbal where the service resides
- **group_id** (*int*) – The id of the service group
- **allocation** (*int*) – the % of connections to allocate to the group
- **port** (*int*) – the port of the service group
- **routing_type** (*int*) – the routing type to set on the service group
- **routing_method** (*int*) – The routing method to set on the group

get_hc_types ()

Retrieves the health check type values.

Returns A dictionary containing the health check types

get_lb_pkgs ()

Retrieves the local load balancer packages.

Returns A dictionary containing the load balancer packages

get_local_lb (*loadbal_id*, ***kwargs*)

Returns a specified local load balancer given the id.

Parameters **loadbal_id** (*int*) – The id of the load balancer to retrieve

Returns A dictionary containing the details of the load balancer

get_local_lbs ()

Returns a list of all local load balancers on the account.

Returns A list of all local load balancers on the current account.

get_routing_methods ()

Retrieves the load balancer routing methods.

Returns A dictionary containing the load balancer routing methods

get_routing_types ()

Retrieves the load balancer routing types.

Returns A dictionary containing the load balancer routing types

reset_service_group (*loadbal_id*, *group_id*)

Resets all the connections on the service group.

Parameters

- **loadbal_id** (*int*) – The id of the loadbal
- **group_id** (*int*) – The id of the service group to reset

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

toggle_service_status (*service_id*)

Toggles the service status.

Parameters **service_id** (*int*) – The id of the service to delete

3.2.11 SoftLayer.messaging

Manager for the SoftLayer Message Queue service

license MIT, see LICENSE for more details.

class `SoftLayer.managers.messaging.MessagingConnection` (*account_id*, *endpoint=**None*) *end-*

Message Queue Service Connection.

Parameters

- **account_id** – Message Queue Account id
- **endpoint** – Endpoint URL

authenticate (*username*, *api_key*, *auth_token=**None*)

Authenticate this connection using the given credentials.

Parameters

- **username** – SoftLayer username
- **api_key** – SoftLayer API Key
- **auth_token** – (optional) Starting auth token

create_queue (*queue_name*, ***kwargs*)

Create Queue.

Parameters

- **queue_name** – Queue Name
- ****kwargs** (*dict*) – queue options

create_subscription (*topic_name*, *subscription_type*, ***kwargs*)

Create Subscription.

Parameters

- **topic_name** – Topic Name
- **subscription_type** – type ('queue' or 'http')
- ****kwargs** (*dict*) – Subscription options

create_topic (*topic_name*, ***kwargs*)

Create Topic.

Parameters

- **topic_name** – Topic Name
- ****kwargs** (*dict*) – Topic options

delete_message (*queue_name*, *message_id*)

Delete a message.

Parameters

- **queue_name** – Queue Name
- **message_id** – Message id

delete_queue (*queue_name*, *force=False*)

Delete Queue.

Parameters

- **queue_name** – Queue Name
- **force** – (optional) Force queue to be deleted even if there are pending messages

delete_subscription (*topic_name*, *subscription_id*)

Delete a subscription.

Parameters

- **topic_name** – Topic Name
- **subscription_id** – Subscription id

delete_topic (*topic_name*, *force=False*)

Delete Topic.

Parameters

- **topic_name** – Topic Name
- **force** – (optional) Force topic to be deleted even if there are attached subscribers

get_queue (*queue_name*)

Get queue details.

Parameters **queue_name** – Queue Name

get_queues (*tags=None*)

Get listing of queues.

Parameters **tags** (*list*) – (optional) list of tags to filter by

get_subscriptions (*topic_name*)

Listing of subscriptions on a topic.

Parameters **topic_name** – Topic Name

get_topic (*topic_name*)

Get topic details.

Parameters **topic_name** – Topic Name

get_topics (*tags=None*)

Get listing of topics.

Parameters **tags** (*list*) – (optional) list of tags to filter by

modify_queue (*queue_name, **kwargs*)

Modify Queue.

Parameters

- **queue_name** – Queue Name
- ****kwargs** (*dict*) – queue options

modify_topic (*topic_name, **kwargs*)

Modify Topic.

Parameters

- **topic_name** – Topic Name
- ****kwargs** (*dict*) – Topic options

pop_message (*queue_name*)

Pop a single message from a queue.

If no messages are returned this returns None

Parameters **queue_name** – Queue Name

pop_messages (*queue_name, count=1*)

Pop messages from a queue.

Parameters

- **queue_name** – Queue Name
- **count** – (optional) number of messages to retrieve

push_queue_message (*queue_name, body, **kwargs*)

Create Queue Message.

Parameters

- **queue_name** – Queue Name
- **body** – Message body
- ****kwargs** (*dict*) – Message options

push_topic_message (*topic_name, body, **kwargs*)

Create Topic Message.

Parameters

- **topic_name** – Topic Name
- **body** – Message body
- ****kwargs** (*dict*) – Topic message options

stats (*period='hour'*)
Get account stats.

Parameters **period** – ‘hour’, ‘day’, ‘week’, ‘month’

class SoftLayer.managers.messaging.**MessagingManager** (*client*)
Manage SoftLayer Message Queue accounts.

See product information here: <http://www.softlayer.com/message-queue>

Parameters **client** (*SoftLayer.API.BaseClient*) – the client instance

get_connection (*account_id, datacenter=None, network=None*)
Get connection to Message Queue Service.

Parameters

- **account_id** – Message Queue Account id
- **datacenter** – Datacenter code
- **network** – network (‘public’ or ‘private’)

get_endpoint (*datacenter=None, network=None*)
Get a message queue endpoint based on datacenter/network type.

Parameters

- **datacenter** – datacenter code
- **network** – network (‘public’ or ‘private’)

get_endpoints ()
Get all known message queue endpoints.

list_accounts (***kwargs*)
List message queue accounts.

Parameters ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

ping (*datacenter=None, network=None*)
Ping a message queue endpoint.

class SoftLayer.managers.messaging.**QueueAuth** (*endpoint, username, api_key, auth_token=None*)
SoftLayer Message Queue authentication for requests.

Parameters

- **endpoint** – endpoint URL
- **username** – SoftLayer username
- **api_key** – SoftLayer API Key
- **auth_token** – (optional) Starting auth token

auth ()
Authenticate.

handle_error (*resp*, ***_*)
Handle errors.

3.2.12 SoftLayer.metadata

Metadata Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.metadata.MetadataManager` (*client=None*, *timeout=5*)
Provides an interface for the SoftLayer metadata service.

See product information here: http://sldn.softlayer.com/reference/services/SoftLayer_Resource_Metadata

This provides metadata about the resource it is called from. See `METADATA_ATTRIBUTES` for full list of attributes.

Usage:

```
>>> import SoftLayer
>>> client = SoftLayer.create_client_from_env()
>>> from SoftLayer import MetadataManager
>>> meta = MetadataManager(client)
>>> meta.get('datacenter')
'dal105'
>>> meta.get('fqdn')
'test.example.com'
```

Parameters *client* (`SoftLayer.API.BaseClient`) – the client instance

get (*name*, *param=None*)
Retrieve a metadata attribute.

Parameters

- **name** (*string*) – name of the attribute to retrieve. See *attrs*
- **param** – Required parameter for some attributes

private_network (***kwargs*)
Returns details about the private network.

Parameters

- **router** (*boolean*) – True to return router details
- **vlan** (*boolean*) – True to return vlan details
- **vlan_ids** (*boolean*) – True to return `vlan_ids`

public_network (***kwargs*)
Returns details about the public network.

Parameters

- **router** (*boolean*) – True to return router details
- **vlan** (*boolean*) – True to return vlan details
- **vlan_ids** (*boolean*) – True to return `vlan_ids`

`metadata.METADATA_ATTRIBUTES = ['datacenter', 'domain', 'backend_mac', 'primary_ip', 'prim`

3.2.13 SoftLayer.network

Network Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.network.NetworkManager` (*client*)

Manage SoftLayer network objects: VLANs, subnets, IPs and rwhois

See product information here: <http://www.softlayer.com/networking>

Parameters `client` (*SoftLayer.API.BaseClient*) – the client instance

add_global_ip (*version=4, test_order=False*)

Adds a global IP address to the account.

Parameters

- **version** (*int*) – Specifies whether this is IPv4 or IPv6
- **test_order** (*bool*) – If true, this will only verify the order.

add_securitygroup_rule (*group_id, remote_ip=None, remote_group=None, direction=None, ethertype=None, port_max=None, port_min=None, protocol=None*)

Add a rule to a security group

Parameters

- **group_id** (*int*) – The ID of the security group to add this rule to
- **remote_ip** (*str*) – The remote IP or CIDR to enforce the rule on
- **remote_group** (*int*) – The remote security group ID to enforce the rule on
- **direction** (*str*) – The direction to enforce (egress or ingress)
- **ethertype** (*str*) – The ethertype to enforce (IPv4 or IPv6)
- **port_max** (*int*) – The upper port bound to enforce (icmp code if the protocol is icmp)
- **port_min** (*int*) – The lower port bound to enforce (icmp type if the protocol is icmp)
- **protocol** (*str*) – The protocol to enforce (icmp, udp, tcp)

add_securitygroup_rules (*group_id, rules*)

Add rules to a security group

Parameters

- **group_id** (*int*) – The ID of the security group to add the rules to
- **rules** (*list*) – The list of rule dictionaries to add

add_subnet (*subnet_type, quantity=None, vlan_id=None, version=4, test_order=False*)

Orders a new subnet

Parameters

- **subnet_type** (*str*) – Type of subnet to add: private, public, global
- **quantity** (*int*) – Number of IPs in the subnet
- **vlan_id** (*int*) – VLAN id for the subnet to be placed into
- **version** (*int*) – 4 for IPv4, 6 for IPv6
- **test_order** (*bool*) – If true, this will only verify the order.

assign_global_ip (*global_ip_id, target*)

Assigns a global IP address to a specified target.

Parameters

- **global_ip_id** (*int*) – The ID of the global IP being assigned
- **target** (*string*) – The IP address to assign

attach_securitygroup_component (*group_id, component_id*)

Attaches a network component to a security group.

Parameters

- **group_id** (*int*) – The ID of the security group
- **component_id** (*int*) – The ID of the network component to attach

attach_securitygroup_components (*group_id, component_ids*)

Attaches network components to a security group.

Parameters

- **group_id** (*int*) – The ID of the security group
- **component_ids** (*list*) – The IDs of the network components to attach

cancel_global_ip (*global_ip_id*)

Cancels the specified global IP address.

Parameters **id** (*int*) – The ID of the global IP to be cancelled.

cancel_subnet (*subnet_id*)

Cancels the specified subnet.

Parameters **subnet_id** (*int*) – The ID of the subnet to be cancelled.

create_securitygroup (*name=None, description=None*)

Creates a security group.

Parameters

- **name** (*string*) – The name of the security group
- **description** (*string*) – The description of the security group

delete_securitygroup (*group_id*)

Deletes the specified security group.

Parameters **group_id** (*int*) – The ID of the security group

detach_securitygroup_component (*group_id, component_id*)

Detaches a network component from a security group.

Parameters

- **group_id** (*int*) – The ID of the security group
- **component_id** (*int*) – The ID of the component to detach

detach_securitygroup_components (*group_id, component_ids*)

Detaches network components from a security group.

Parameters

- **group_id** (*int*) – The ID of the security group
- **component_ids** (*list*) – The IDs of the network components to detach

edit_rwhois (*abuse_email=None, address1=None, address2=None, city=None, company_name=None, country=None, first_name=None, last_name=None, postal_code=None, private_residence=None, state=None*)
Edit rwhois record.

edit_securitygroup (*group_id, name=None, description=None*)
Edit security group details.

Parameters

- **group_id** (*int*) – The ID of the security group
- **name** (*string*) – The name of the security group
- **description** (*string*) – The description of the security group

edit_securitygroup_rule (*group_id, rule_id, remote_ip=None, remote_group=None, direction=None, ethertype=None, port_max=None, port_min=None, protocol=None*)

Edit a security group rule.

Parameters

- **group_id** (*int*) – The ID of the security group the rule belongs to
- **rule_id** (*int*) – The ID of the rule to edit
- **remote_ip** (*str*) – The remote IP or CIDR to enforce the rule on
- **remote_group** (*int*) – The remote security group ID to enforce the rule on
- **direction** (*str*) – The direction to enforce (egress or ingress)
- **ethertype** (*str*) – The ethertype to enforce (IPv4 or IPv6)
- **port_max** (*str*) – The upper port bound to enforce
- **port_min** (*str*) – The lower port bound to enforce
- **protocol** (*str*) – The protocol to enforce (icmp, udp, tcp)

get_nas_credentials (*identifier, **kwargs*)
Returns a list of IDs of VLANs which match the given VLAN name.

Parameters **instance_id** (*integer*) – the instance ID

Returns A dictionary containing a large amount of information about the specified instance.

get_rwhois ()
Returns the RWhois information about the current account.

Returns A dictionary containing the account's RWhois information.

get_securitygroup (*group_id, **kwargs*)
Returns the information about the given security group.

Parameters **id** (*string*) – The ID for the security group

Returns A diction of information about the security group

get_subnet (*subnet_id, **kwargs*)
Returns information about a single subnet.

Parameters **id** (*string*) – Either the ID for the subnet or its network identifier

Returns A dictionary of information about the subnet

get_vlan (*vlan_id*)

Returns information about a single VLAN.

Parameters **id** (*int*) – The unique identifier for the VLAN

Returns A dictionary containing a large amount of information about the specified VLAN.

ip_lookup (*ip_address*)

Looks up an IP address and returns network information about it.

Parameters **ip_address** (*string*) – An IP address. Can be IPv4 or IPv6

Returns A dictionary of information about the IP

list_global_ips (*version=None, identifier=None, **kwargs*)

Returns a list of all global IP address records on the account.

Parameters

- **version** (*int*) – Only returns IPs of this version (4 or 6)
- **identifier** (*string*) – If specified, the list will only contain the global ips matching this network identifier.

list_securitygroup_rules (*group_id*)

List security group rules associated with a security group.

Parameters **group_id** (*int*) – The security group to list rules for

list_securitygroups (***kwargs*)

List security groups.

list_subnets (*identifier=None, datacenter=None, version=0, subnet_type=None, network_space=None, **kwargs*)

Display a list of all subnets on the account.

This provides a quick overview of all subnets including information about data center residence and the number of devices attached.

Parameters

- **identifier** (*string*) – If specified, the list will only contain the subnet matching this network identifier.
- **datacenter** (*string*) – If specified, the list will only contain subnets in the specified data center.
- **version** (*int*) – Only returns subnets of this version (4 or 6).
- **subnet_type** (*string*) – If specified, it will only returns subnets of this type.
- **network_space** (*string*) – If specified, it will only returns subnets with the given address space label.
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

list_vlans (*datacenter=None, vlan_number=None, name=None, **kwargs*)

Display a list of all VLANs on the account.

This provides a quick overview of all VLANs including information about data center residence and the number of devices attached.

Parameters

- **datacenter** (*string*) – If specified, the list will only contain VLANs in the specified data center.

- **vlan_number** (*int*) – If specified, the list will only contain the VLAN matching this VLAN number.
- **name** (*int*) – If specified, the list will only contain the VLAN matching this VLAN name.
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

remove_securitygroup_rule (*group_id*, *rule_id*)

Remove a rule from a security group.

Parameters

- **group_id** (*int*) – The ID of the security group
- **rule_id** (*int*) – The ID of the rule to remove

remove_securitygroup_rules (*group_id*, *rules*)

Remove rules from a security group.

Parameters

- **group_id** (*int*) – The ID of the security group
- **rules** (*list*) – The list of IDs to remove

resolve_global_ip_ids (*identifier*)

Resolve global ip ids.

resolve_subnet_ids (*identifier*)

Resolve subnet ids.

resolve_vlan_ids (*identifier*)

Resolve VLAN ids.

summary_by_datacenter ()

Summary of the networks on the account, grouped by data center.

The resultant dictionary is primarily useful for statistical purposes. It contains count information rather than raw data. If you want raw information, see the `list_vlans()` method instead.

Returns A dictionary keyed by data center with the data containing a set of counts for subnets, hardware, virtual servers, and other objects residing within that data center.

unassign_global_ip (*global_ip_id*)

Unassigns a global IP address from a target.

Parameters **id** (*int*) – The ID of the global IP being unassigned

3.2.14 SoftLayer.ordering

Ordering Manager

license MIT, see LICENSE for more details.

class `SoftLayer.managers.ordering.OrderingManager` (*client*)

Manager to help ordering via the SoftLayer API.

Parameters **client** (`SoftLayer.API.BaseClient`) – the client instance

static filter_outlet_packages (*packages*)

Remove packages designated as OUTLET.

Those type of packages must be handled in a different way, and they are not supported at the moment.

Parameters packages – Dictionary of packages. Name and description keys must be present in each of them.

generate_order (*package_keyname, location, item_keynames, complex_type=None, hourly=True, preset_keyname=None, extras=None, quantity=1*)
Generates an order with the given package and prices.

This function takes in parameters needed for an order and generates an order dictionary. This dictionary can then be used in either verify or placeOrder().

Parameters

- **package_keyname** (*str*) – The keyname for the package being ordered
- **location** (*str*) – The datacenter location string for ordering (Ex: DALLAS13)
- **item_keynames** (*list*) – The list of item keyname strings to order. To see list of possible keynames for a package, use list_items() (or *slcli order item-list*)
- **complex_type** (*str*) – The complex type to send with the order. Typically begins with *SoftLayer_Container_Product_Order_*.
- **hourly** (*bool*) – If true, uses hourly billing, otherwise uses monthly billing
- **preset_keyname** (*string*) – If needed, specifies a preset to use for that package. To see a list of possible keynames for a package, use list_preset() (or *slcli order preset-list*)
- **extras** (*dict*) – The extra data for the order in dictionary format. Example: A VSI order requires hostname and domain to be set, so extras will look like the following: {'virtualGuests': [{'hostname': 'test', 'domain': 'softlayer.com'}]}
- **quantity** (*int*) – The number of resources to order

generate_order_template (*quote_id, extra, quantity=1*)
Generate a complete order template.

Parameters

- **quote_id** (*int*) – ID of target quote
- **extra** (*list*) – List of dictionaries that have extra details about the order such as hostname or domain names for virtual servers or hardware nodes
- **quantity** (*int*) – Number of ~things~ to order

static get_only_active_packages (*packages*)
Return only active packages.

If a package is active, it is eligible for ordering This will inspect the 'isActive' property on the provided packages

Parameters packages – Dictionary of packages, isActive key must be present

get_order_container (*quote_id*)
Generate an order container from a quote object.

Parameters quote_id – ID number of target quote

get_package_by_key (*package_keyname, mask=None*)
Get a single package with a given key.

If no packages are found, returns None

Parameters

- **package_keyname** – string representing the package key name we are interested in.

- **mask** (*string*) – Mask to specify the properties we want to retrieve

get_package_by_type (*package_type*, *mask=None*)

Get a single package of a given type.

Syntactic sugar to retrieve a single package of a given type. If multiple packages share the given type, this will return the first one returned by the API. If no packages are found, returns None

Parameters **package_type** (*string*) – representing the package type key name we are interested in

get_package_id_by_type (*package_type*)

Return the package ID of a Product Package with a given type.

Parameters **package_type** (*string*) – representing the package type key name we are interested in

Raises **ValueError** – when no package of the given type is found

get_packages_of_type (*package_types*, *mask=None*)

Get packages that match a certain type.

Each ordering package has a type, so return all packages that match the types we are looking for

Parameters

- **package_types** (*list*) – List of strings representing the package type keynames we are interested in.
- **mask** (*string*) – Mask to specify the properties we want to retrieve

get_preset_by_key (*package_keyname*, *preset_keyname*, *mask=None*)

Gets a single preset with the given key.

get_price_id_list (*package_keyname*, *item_keynames*)

Converts a list of item keynames to a list of price IDs.

This function is used to convert a list of item keynames into a list of price IDs that are used in the Product_Order verifyOrder() and placeOrder() functions.

Parameters

- **package_keyname** (*str*) – The package associated with the prices
- **item_keynames** (*list*) – A list of item keyname strings

Returns A list of price IDs associated with the given item keynames in the given package

get_quote_details (*quote_id*)

Retrieve quote details.

Parameters **quote_id** – ID number of target quote

get_quotes ()

Retrieve a list of quotes.

Returns a list of SoftLayer_Billing_Order_Quote

list_categories (*package_keyname*, ***kwargs*)

List the categories for the given package.

Parameters **package_keyname** (*str*) – The package for which to get the categories.

Returns List of categories associated with the package

list_items (*package_keyname*, ***kwargs*)

List the items for the given package.

Parameters `package_keyname` (*str*) – The package for which to get the items.

Returns List of items in the package

list_packages (***kwargs*)

List active packages.

Returns List of active packages.

list_presets (*package_keyname, **kwargs*)

Gets active presets for the given package.

Parameters `package_keyname` (*str*) – The package for which to get presets

Returns A list of package presets that can be used for ordering

order_quote (*quote_id, extra, quantity=1*)

Places an order using a quote

Parameters

- **quote_id** (*int*) – ID for the target quote
- **hostnames** (*list*) – hostnames of the servers
- **domain** (*string*) – domain of the new server
- **quantity** (*int*) – Quantity to override default

package_locations (*package_keyname*)

List datacenter locations for a package keyname

Parameters `package_keyname` (*str*) – The package for which to get the items.

Returns List of locations a package is orderable in

place_order (*package_keyname, location, item_keynames, complex_type=None, hourly=True, preset_keyname=None, extras=None, quantity=1*)

Places an order with the given package and prices.

This function takes in parameters needed for an order and places the order.

Parameters

- **package_keyname** (*str*) – The keyname for the package being ordered
- **location** (*str*) – The datacenter location string for ordering (Ex: DALLAS13)
- **item_keynames** (*list*) – The list of item keyname strings to order. To see list of possible keynames for a package, use `list_items()` (or `slcli order item-list`)
- **complex_type** (*str*) – The complex type to send with the order. Typically begins with `SoftLayer_Container_Product_Order_`.
- **hourly** (*bool*) – If true, uses hourly billing, otherwise uses monthly billing
- **preset_keyname** (*string*) – If needed, specifies a preset to use for that package. To see a list of possible keynames for a package, use `list_preset()` (or `slcli order preset-list`)
- **extras** (*dict*) – The extra data for the order in dictionary format. Example: A VSI order requires hostname and domain to be set, so extras will look like the following: `{'virtualGuests': [{'hostname': 'test', 'domain': 'softlayer.com'}]}`
- **quantity** (*int*) – The number of resources to order

verify_order (*package_keyname*, *location*, *item_keynames*, *complex_type=None*, *hourly=True*, *preset_keyname=None*, *extras=None*, *quantity=1*)

Verifies an order with the given package and prices.

This function takes in parameters needed for an order and verifies the order to ensure the given items are compatible with the given package.

Parameters

- **package_keyname** (*str*) – The keyname for the package being ordered
- **location** (*str*) – The datacenter location string for ordering (Ex: DALLAS13)
- **item_keynames** (*list*) – The list of item keyname strings to order. To see list of possible keynames for a package, use `list_items()` (or `slcli order item-list`)
- **complex_type** (*str*) – The complex type to send with the order. Typically begins with `SoftLayer_Container_Product_Order_`.
- **hourly** (*bool*) – If true, uses hourly billing, otherwise uses monthly billing
- **preset_keyname** (*string*) – If needed, specifies a preset to use for that package. To see a list of possible keynames for a package, use `list_preset()` (or `slcli order preset-list`)
- **extras** (*dict*) – The extra data for the order in dictionary format. Example: A VSI order requires hostname and domain to be set, so extras will look like the following: `'virtualGuests': [{ 'hostname': 'test', 'domain': 'softlayer.com' }]`
- **quantity** (*int*) – The number of resources to order

verify_quote (*quote_id*, *extra*, *quantity=1*)

Verifies that a quote order is valid.

Parameters

- **quote_id** (*int*) – ID for the target quote
- **hostnames** (*list*) – hostnames of the servers
- **domain** (*string*) – domain of the new servers
- **quantity** (*int*) – Quantity to override default

3.2.15 SoftLayer.sshkey

SSH Key Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.sshkey.SshKeyManager` (*client*)

Manages account SSH keys in SoftLayer.

See product information here: <https://knowledge.softlayer.com/procedure/ssh-keys>

Parameters **client** (`SoftLayer.API.BaseClient`) – the client instance

add_key (*key*, *label*, *notes=None*)

Adds a new SSH key to the account.

Parameters

- **key** (*string*) – The SSH key to add
- **label** (*string*) – The label for the key
- **notes** (*string*) – Additional notes for the key

Returns A dictionary of the new key’s information.

delete_key (*key_id*)

Permanently deletes an SSH key from the account.

Parameters **key_id** (*int*) – The ID of the key to delete

edit_key (*key_id*, *label=None*, *notes=None*)

Edits information about an SSH key.

Parameters

- **key_id** (*int*) – The ID of the key to edit
- **label** (*string*) – The new label for the key
- **notes** (*string*) – Notes to set or change on the key

Returns A Boolean indicating success or failure

get_key (*key_id*)

Returns full information about a single SSH key.

Parameters **key_id** (*int*) – The ID of the key to retrieve

Returns A dictionary of information about the key

list_keys (*label=None*)

Lists all SSH keys on the account.

Parameters **label** (*string*) – Filter list based on SSH key label

Returns A list of dictionaries with information about each key

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

3.2.16 SoftLayer.ssl

SSL Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.ssl.SSLManager` (*client*)

Manages SSL certificates in SoftLayer.

See product information here: <http://www.softlayer.com/ssl-certificates>

Example:

```
# Initialize the Manager.
# env variables. These can also be specified in ~/.softlayer,
# or passed directly to SoftLayer.Client()
# SL_USERNAME = YOUR_USERNAME
# SL_API_KEY = YOUR_API_KEY
import SoftLayer
client = SoftLayer.Client()
mgr = SoftLayer.SSLManager(client)
```

Parameters `client` (*SoftLayer.API.BaseClient*) – the client instance

add_certificate (*certificate*)

Creates a new certificate.

Parameters `certificate` (*dict*) – A dictionary representing the parts of the certificate. See developer.softlayer.com for more info.

Example:

```
cert = ??
result = mgr.add_certificate(certificate=cert)
```

edit_certificate (*certificate*)

Updates a certificate with the included options.

The provided dict must include an 'id' key and value corresponding to the certificate ID that should be updated.

Parameters `certificate` (*dict*) – the certificate to update.

Example:

```
# Updates the cert id 1234
cert['id'] = 1234
cert['certificate'] = ??
result = mgr.edit_certificate(certificate=cert)
```

get_certificate (*cert_id*)

Gets a certificate with the ID specified.

Parameters `cert_id` (*integer*) – the certificate ID to retrieve

Example:

```
cert = mgr.get_certificate(cert_id=1234)
print(cert)
```

list_certs (*method='all'*)

List all certificates.

Parameters `method` (*string*) – The type of certificates to list. Options are 'all', 'expired', and 'valid'.

Returns A list of dictionaries representing the requested SSL certs.

Example:

```
# Get all valid SSL certs
certs = mgr.list_certs(method='valid')
print(certs)
```

remove_certificate (*cert_id*)

Removes a certificate.

Parameters `cert_id` (*integer*) – a certificate ID to remove

Example:

```
# Removes certificate with id 1234
result = mgr.remove_certificate(cert_id = 1234)
```

3.2.17 SoftLayer.ticket

Ticket Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.ticket.TicketManager` (*client*)

Manages SoftLayer support tickets.

See product information here: <http://www.softlayer.com/support>

Parameters `client` (*SoftLayer.API.BaseClient*) – the client instance

attach_hardware (*ticket_id=None, hardware_id=None*)

Attach hardware to a ticket.

Parameters

- **ticket_id** (*integer*) – the id of the ticket to attach to
- **hardware_id** (*integer*) – the id of the hardware to attach

Returns dict – The new ticket attachment

attach_virtual_server (*ticket_id=None, virtual_id=None*)

Attach a virtual server to a ticket.

Parameters

- **ticket_id** (*integer*) – the id of the ticket to attach to
- **virtual_id** (*integer*) – the id of the virtual server to attach

Returns dict – The new ticket attachment

create_ticket (*title=None, body=None, subject=None*)

Create a new ticket.

Parameters

- **title** (*string*) – title for the new ticket
- **body** (*string*) – body for the new ticket
- **subject** (*integer*) – id of the subject to be assigned to the ticket

detach_hardware (*ticket_id=None, hardware_id=None*)

Detach hardware from a ticket.

Parameters

- **ticket_id** – the id of the ticket to detach from
- **hardware_id** – the id of the hardware to detach

Returns bool – Whether the detachment was successful

detach_virtual_server (*ticket_id=None, virtual_id=None*)

Detach a virtual server from a ticket.

Parameters

- **ticket_id** – the id of the ticket to detach from
- **virtual_id** – the id of the virtual server to detach

Returns bool – Whether the detachment was successful

get_ticket (*ticket_id*)

Get details about a ticket.

Parameters **ticket_id** (*integer*) – the ticket ID

Returns dict – information about the specified ticket

list_subjects ()

List all ticket subjects.

list_tickets (*open_status=True, closed_status=True*)

List all tickets.

Parameters

- **open_status** (*boolean*) – include open tickets
- **closed_status** (*boolean*) – include closed tickets

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

update_ticket (*ticket_id=None, body=None*)

Update a ticket.

Parameters

- **ticket_id** (*integer*) – the id of the ticket to update
- **body** (*string*) – entry to update in the ticket

upload_attachment (*ticket_id=None, file_path=None, file_name=None*)

Upload an attachment to a ticket.

Parameters

- **ticket_id** (*integer*) – the id of the ticket to upload the attachment to
- **file_path** (*string*) – The path of the attachment to be uploaded
- **file_name** (*string*) – The name of the attachment shown in the ticket

Returns dict – The uploaded attachment

3.2.18 SoftLayer.vs

VS Manager/helpers

license MIT, see LICENSE for more details.

class `SoftLayer.managers.vs.VSManager` (*client, ordering_manager=None*)

Manages SoftLayer Virtual Servers.

See product information here: <http://www.softlayer.com/virtual-servers>

Example:


```
# Initialize the VSManager.
# env variables. These can also be specified in ~/.softlayer,
# or passed directly to SoftLayer.Client()
# SL_USERNAME = YOUR_USERNAME
# SL_API_KEY = YOUR_API_KEY
import SoftLayer
client = SoftLayer.Client()
mgr = SoftLayer.VSManager(client)
```

Parameters

- **client** (*SoftLayer.API.BaseClient*) – the client instance
- **ordering_manager** (*SoftLayer.managers.OrderingManager*) – an optional manager to handle ordering. If none is provided, one will be auto initialized.

cancel_instance (*instance_id*)

Cancel an instance immediately, deleting all its data.

Parameters **instance_id** (*integer*) – the instance ID to cancel

Example:

```
# Cancels instance 12345
mgr.cancel_instance(12345)
```

capture (*instance_id, name, additional_disks=False, notes=None*)

Capture one or all disks from a VS to a SoftLayer image.

Parameters set to None will be ignored and not attempted to be updated.

Parameters

- **instance_id** (*integer*) – the instance ID to edit
- **name** (*string*) – name assigned to the image
- **additional_disks** (*bool*) – set to true to include all additional attached storage devices
- **notes** (*string*) – notes about this particular image

Returns dictionary – information about the capture transaction.

Example:: name = “Testing Images” notes = “Some notes about this image” result = mgr.capture(instance_id=12345, name=name, notes=notes)

change_port_speed (*instance_id, public, speed*)

Allows you to change the port speed of a virtual server’s NICs.

Example:

```
#change the Public interface to 10Mbps on instance 12345
result = mgr.change_port_speed(instance_id=12345,
                               public=True, speed=10)
# result will be True or an Exception
```

Parameters

- **instance_id** (*int*) – The ID of the VS

- **public** (*bool*) – Flag to indicate which interface to change. True (default) means the public interface. False indicates the private interface.
- **speed** (*int*) – The port speed to set.

Warning: A port speed of 0 will disable the interface.

create_instance (**kwargs)

Creates a new virtual server instance.

Warning: This will add charges to your account

Example:

```
new_vsi = {
    'domain': u'test01.labs.sftlyr.ws',
    'hostname': u'minion05',
    'datacenter': u'hkg02',
    'dedicated': False,
    'private': False,
    'cpus': 1,
    'os_code' : u'UBUNTU_LATEST',
    'hourly': True,
    'ssh_keys': [1234],
    'disks': ('100', '25'),
    'local_disk': True,
    'memory': 1024,
    'tags': 'test, pleaseCancel',
    'public_security_groups': [12, 15]
}

vsi = mgr.create_instance(**new_vsi)
# vsi will have the newly created vsi details if done properly.
print vsi
```

Parameters

- **cpus** (*int*) – The number of virtual CPUs to include in the instance.
- **memory** (*int*) – The amount of RAM to order.
- **hourly** (*bool*) – Flag to indicate if this server should be billed hourly (default) or monthly.
- **hostname** (*string*) – The hostname to use for the new server.
- **domain** (*string*) – The domain to use for the new server.
- **local_disk** (*bool*) – Flag to indicate if this should be a local disk (default) or a SAN disk.
- **datacenter** (*string*) – The short name of the data center in which the VS should reside.
- **os_code** (*string*) – The operating system to use. Cannot be specified if *image_id* is specified.

- **image_id** (*int*) – The ID of the image to load onto the server. Cannot be specified if `os_code` is specified.
- **dedicated** (*bool*) – Flag to indicate if this should be housed on a dedicated or shared host (default). This will incur a fee on your account.
- **public_vlan** (*int*) – The ID of the public VLAN on which you want this VS placed.
- **public_security_groups** (*list*) – The list of security group IDs to apply to the public interface
- **private_security_groups** (*list*) – The list of security group IDs to apply to the private interface
- **private_vlan** (*int*) – The ID of the private VLAN on which you want this VS placed.
- **disks** (*list*) – A list of disk capacities for this server.
- **post_uri** (*string*) – The URI of the post-install script to run after reload
- **private** (*bool*) – If true, the VS will be provisioned only with access to the private network. Defaults to false
- **ssh_keys** (*list*) – The SSH keys to add to the root user
- **nic_speed** (*int*) – The port speed to set
- **tags** (*string*) – tags to set on the VS as a comma separated list
- **flavor** (*string*) – The key name of the public virtual server flavor being ordered.
- **host_id** (*int*) – The host id of a dedicated host to provision a dedicated host virtual server on.

create_instances (*config_list*)

Creates multiple virtual server instances.

This takes a list of dictionaries using the same arguments as `create_instance()`.

Warning: This will add charges to your account

Example:

```
# Define the instance we want to create.
new_vsi = {
    'domain': u'test01.labs.sftlyr.ws',
    'hostname': u'multi-test',
    'datacenter': u'hkg02',
    'dedicated': False,
    'private': False,
    'cpus': 1,
    'os_code' : u'UBUNTU_LATEST',
    'hourly': True,
    'ssh_keys': [87634],
    'disks': ('100', '25'),
    'local_disk': True,
    'memory': 1024,
    'tags': 'test, pleaseCancel',
    'public_security_groups': [12, 15]
}
```

```
# using .copy() so we can make changes to individual nodes
instances = [new_vsi.copy(), new_vsi.copy(), new_vsi.copy()]

# give each its own hostname, not required.
instances[0]['hostname'] = "multi-test01"
instances[1]['hostname'] = "multi-test02"
instances[2]['hostname'] = "multi-test03"

vsi = mgr.create_instances(config_list=instances)
#vsi will be a dictionary of all the new virtual servers
print vsi
```

edit (*instance_id*, *userdata=None*, *hostname=None*, *domain=None*, *notes=None*, *tags=None*)

Edit hostname, domain name, notes, and/or the user data of a VS.

Parameters set to None will be ignored and not attempted to be updated.

Parameters

- **instance_id** (*integer*) – the instance ID to edit
- **userdata** (*string*) – user data on VS to edit. If none exist it will be created
- **hostname** (*string*) – valid hostname
- **domain** (*string*) – valid domain namem
- **notes** (*string*) – notes about this particular VS
- **tags** (*string*) – tags to set on the VS as a comma separated list. Use the empty string to remove all tags.

Returns bool – True or an Exception

Example:: # Change the hostname on instance 12345 to ‘something’ result = mgr.edit(instance_id=12345, hostname=”something”) #result will be True or an Exception

get_create_options (**args*, ***kwargs*)

Retrieves the available options for creating a VS.

Returns A dictionary of creation options.

Example:

```
# Prints out the create option dictionary
options = mgr.get_create_options()
print(options)
```

get_instance (**args*, ***kwargs*)

Get details about a virtual server instance.

Parameters **instance_id** (*integer*) – the instance ID

Returns A dictionary containing a large amount of information about the specified instance.

Example:

```
# Print out instance ID 12345.
vsi = mgr.get_instance(12345)
print vsi

# Print out only FQDN and primaryIP for instance 12345
```

```
object_mask = "mask[fullyQualifiedDomainName,primaryIpAddress]"
vsi = mgr.get_instance(12345, mask=mask)
print vsi
```

list_instances (*args, **kwargs)

Retrieve a list of all virtual servers on the account.

Example:

```
# Print out a list of hourly instances in the DAL05 data center.

for vsi in mgr.list_instances(hourly=True, datacenter='dal05'):
    print vsi['fullyQualifiedDomainName'], vsi['primaryIpAddress']

# Using a custom object-mask. Will get ONLY what is specified
object_mask = "mask[hostname,monitoringRobot[robotStatus]]"
for vsi in mgr.list_instances(mask=object_mask, hourly=True):
    print vsi
```

Parameters

- **hourly** (*boolean*) – include hourly instances
- **monthly** (*boolean*) – include monthly instances
- **tags** (*list*) – filter based on list of tags
- **cpus** (*integer*) – filter based on number of CPUS
- **memory** (*integer*) – filter based on amount of memory
- **hostname** (*string*) – filter based on hostname
- **domain** (*string*) – filter based on domain
- **local_disk** (*string*) – filter based on local_disk
- **datacenter** (*string*) – filter based on datacenter
- **nic_speed** (*integer*) – filter based on network speed (in MBPS)
- **public_ip** (*string*) – filter based on public ip address
- **private_ip** (*string*) – filter based on private ip address
- ****kwargs** (*dict*) – response-level options (mask, limit, etc.)

Returns Returns a list of dictionaries representing the matching virtual servers

reload_instance (*instance_id*, *post_uri=None*, *ssh_keys=None*, *image_id=None*)

Perform an OS reload of an instance.

Parameters

- **instance_id** (*integer*) – the instance ID to reload
- **post_url** (*string*) – The URI of the post-install script to run after reload
- **ssh_keys** (*list*) – The SSH keys to add to the root user
- **image_id** (*int*) – The ID of the image to load onto the server

Warning: This will reformat the primary drive. Post-provision script MUST be HTTPS for it to be executed.

Example:

```
# Reload instance ID 12345 then run a custom post-provision script.
# Post-provision script MUST be HTTPS for it to be executed.
post_uri = 'https://somehost.com/bootstrap.sh'
vsi = mgr.reload_instance(12345, post_uri=post_url)
```

rescue (*instance_id*)

Reboot a VSI into the Xen rescue kernel.

Parameters **instance_id** (*integer*) – the instance ID to rescue

Returns bool – True or an Exception

Example:: # Puts instance 12345 into rescue mode result = mgr.rescue(instance_id=12345)

resolve_ids (*identifier*)

Takes a string and tries to resolve to a list of matching ids.

What exactly ‘identifier’ can be depends on the resolvers

Parameters **identifier** (*string*) – identifying string

Returns list

set_tags (**args, **kwargs*)

Sets tags on a guest with a retry decorator

Just calls guest.setTags, but if it fails from an APIError will retry

upgrade (*instance_id, cpus=None, memory=None, nic_speed=None, public=True*)

Upgrades a VS instance.

Example:

```
# Upgrade instance 12345 to 4 CPUs and 4 GB of memory
import SoftLayer
client = SoftLayer.create_client_from_env()
mgr = SoftLayer.VSManager(client)
mgr.upgrade(12345, cpus=4, memory=4)
```

Parameters

- **instance_id** (*int*) – Instance id of the VS to be upgraded
- **cpus** (*int*) – The number of virtual CPUs to upgrade to of a VS instance.
- **memory** (*int*) – RAM of the VS to be upgraded to.
- **nic_speed** (*int*) – The port speed to set
- **public** (*bool*) – CPU will be in Private/Public Node.

Returns bool

verify_create_instance (***kwargs*)

Verifies an instance creation command.

Without actually placing an order. See `create_instance()` for a list of available options.

Example:

```
new_vsi = {
    'domain': u'test01.labs.sftlyr.ws',
    'hostname': u'minion05',
    'datacenter': u'hkg02',
    'dedicated': False,
    'private': False,
    'cpus': 1,
    'os_code' : u'UBUNTU_LATEST',
    'hourly': True,
    'ssh_keys': [1234],
    'disks': ('100', '25'),
    'local_disk': True,
    'memory': 1024
}

vsi = mgr.verify_create_instance(**new_vsi)
# vsi will be a SoftLayer_Container_Product_Order_Virtual_Guest
# if your order is correct. Otherwise you will get an exception
print vsi
```

wait_for_ready (*instance_id*, *limit=3600*, *delay=10*, *pending=False*)

Determine if a VS is ready and available.

In some cases though, that can mean that no transactions are running. The default arguments imply a VS is operational and ready for use by having network connectivity and remote access is available. Setting `pending=True` will ensure future API calls against this instance will not error due to pending transactions such as OS Reloads and cancellations.

Parameters

- **instance_id** (*int*) – The instance ID with the pending transaction
- **limit** (*int*) – The maximum amount of seconds to wait.
- **delay** (*int*) – The number of seconds to sleep before checks. Defaults to 10.
- **pending** (*bool*) – Wait for pending transactions not related to provisioning or reloads such as monitoring.

Example:

```
# Will return once vsi 12345 is ready, or after 10 checks
ready = mgr.wait_for_ready(12345, 10)
```

wait_for_transaction (**args*, ***kwargs*)

Waits on a VS transaction for the specified amount of time.

This is really just a wrapper for `wait_for_ready(pending=True)`. Provided for backwards compatibility.

Parameters

- **instance_id** (*int*) – The instance ID with the pending transaction
- **limit** (*int*) – The maximum amount of time to wait.
- **delay** (*int*) – The number of seconds to sleep before checks. Defaults to 10.

If you need more power or functionality than the managers provide, you can make direct API calls as well.

3.3 Making API Calls

For full control over your account and services, you can directly call the SoftLayer API. The SoftLayer API client for python leverages SoftLayer's XML-RPC API. It supports authentication, object masks, object filters, limits, offsets, and retrieving objects by id. The following section assumes you have an initialized client named 'client'.

The best way to test our setup is to call the `getObject` method on the `SoftLayer_Account` service.

```
client.call('Account', 'getObject')
```

For a more complex example we'll retrieve a support ticket with id 123456 along with the ticket's updates, the user it's assigned to, the servers attached to it, and the datacenter those servers are in. To retrieve our extra information using an `object mask`.

Retrieve a ticket using object masks.

```
ticket = client.call('Ticket', 'getObject',
                    id=123456, mask="updates, assignedUser, attachedHardware.datacenter")
```

Now add an update to the ticket with `Ticket.addUpdate`. This uses a parameter, which translate to positional arguments in the order that they appear in the API docs.

```
update = client.call('Ticket', 'addUpdate', {'entry' : 'Hello!'}, id=123456)
```

Let's get a listing of virtual guests using the domain `example.com`

```
client.call('Account', 'getVirtualGuests',
            filter={'virtualGuests': {'domain': {'operation': 'example.com'}}})
```

This call gets tickets created between the beginning of March 1, 2013 and March 15, 2013.

```
client.call('Account', 'getTickets',
            filter={
                'tickets': {
                    'createDate': {
                        'operation': 'betweenDate',
                        'options': [
                            {'name': 'startDate', 'value': ['03/01/2013 0:0:0']},
                            {'name': 'endDate', 'value': ['03/15/2013 23:59:59']}
                        ]
                    }
                }
            })
```

SoftLayer's XML-RPC API also allows for pagination.

```
client.call('Account', 'getVirtualGuests', limit=10, offset=0) # Page 1
client.call('Account', 'getVirtualGuests', limit=10, offset=10) # Page 2
```

Here's how to create a new Cloud Compute Instance using `SoftLayer_Virtual_Guest.createObject`. Be warned, this call actually creates an hourly virtual server so this will have billing implications.

```
client.call('Virtual_Guest', 'createObject', {
    'hostname': 'myhostname',
    'domain': 'example.com',
    'startCpus': 1,
    'maxMemory': 1024,
```



```

    'hourlyBillingFlag': 'true',
    'operatingSystemReferenceCode': 'UBUNTU_LATEST',
    'localDiskFlag': 'false'
})

```

3.4 API Reference

3.4.1 SoftLayer Python API Client

SoftLayer API bindings

Usage:

```

>>> import SoftLayer
>>> client = SoftLayer.create_client_from_env(username="username",
                                             api_key="api_key")
>>> resp = client.call('Account', 'getObject')
>>> resp['companyName']
'Your Company'

```

license MIT, see LICENSE for more details.

class `SoftLayer.BaseClient` (*auth=None, transport=None*)

Base SoftLayer API client.

Parameters

- **auth** – auth driver that looks like `SoftLayer.auth.AuthenticationBase`
- **transport** – An object that's callable with this signature: `transport(SoftLayer.transports.Request)`

authenticate_with_password (*username, password, security_question_id=None, security_question_answer=None*)

Performs Username/Password Authentication

Parameters

- **username** (*string*) – your SoftLayer username
- **password** (*string*) – your SoftLayer password
- **security_question_id** (*int*) – The security question id to answer
- **security_question_answer** (*string*) – The answer to the security question

call (*service, method, *args, **kwargs*)

Make a SoftLayer API call.

Parameters

- **method** – the method to call on the service
- ***args** – (optional) arguments for the remote call
- **id** – (optional) id for the resource
- **mask** – (optional) object mask
- **filter** (*dict*) – (optional) filter dict
- **headers** (*dict*) – (optional) optional XML-RPC headers

- **compress** (*boolean*) – (optional) Enable/Disable HTTP compression
- **raw_headers** (*dict*) – (optional) HTTP transport headers
- **limit** (*int*) – (optional) return at most this many results
- **offset** (*int*) – (optional) offset results by this many
- **iter** (*boolean*) – (optional) if True, returns a generator with the results
- **verify** (*bool*) – verify SSL cert
- **cert** – client certificate path

Usage:

```
>>> import SoftLayer
>>> client = SoftLayer.create_client_from_env()
>>> client.call('Account', 'getVirtualGuests', mask="id", limit=10)
[...]
```

iter_call (*service, method, *args, **kwargs*)

A generator that deals with paginating through results.

Parameters

- **service** – the name of the SoftLayer API service
- **method** – the method to call on the service
- **chunk** (*integer*) – result size for each API call (defaults to 100)
- ***args** – same optional arguments that `Service.call` takes
- ****kwargs** – same optional keyword arguments that `Service.call` takes

`SoftLayer.create_client_from_env` (*username=None, api_key=None, endpoint_url=None, timeout=None, auth=None, config_file=None, proxy=None, user_agent=None, transport=None, verify=True*)

Creates a SoftLayer API client using your environment.

Settings are loaded via keyword arguments, environmental variables and config file.

Parameters

- **username** – an optional API username if you wish to bypass the package’s built-in username
- **api_key** – an optional API key if you wish to bypass the package’s built in API key
- **endpoint_url** – the API endpoint base URL you wish to connect to. Set this to `API_PRIVATE_ENDPOINT` to connect via SoftLayer’s private network.
- **proxy** – proxy to be used to make API calls
- **timeout** (*integer*) – timeout for API requests
- **auth** – an object which responds to `get_headers()` to be inserted into the xml-rpc headers. Example: `BasicAuthentication`
- **config_file** – A path to a configuration file used to load settings
- **user_agent** – an optional User Agent to report when making API calls if you wish to bypass the packages built in User Agent string

- **transport** – An object that’s callable with this signature: `transport(SoftLayer.transports.Request)`
- **verify** (*bool*) – decide to verify the server’s SSL/TLS cert. DO NOT SET TO FALSE WITHOUT UNDERSTANDING THE IMPLICATIONS.

Usage:

```
>>> import SoftLayer
>>> client = SoftLayer.create_client_from_env()
>>> resp = client.call('Account', 'getObject')
>>> resp['companyName']
'Your Company'
```

`SoftLayer.Client` (***kwargs*)

Get a SoftLayer API Client using environmental settings.

Deprecated in favor of `create_client_from_env()`

class `SoftLayer.BasicAuthentication` (*username, api_key*)

Token-based authentication class.

Parameters

- **str** (*api_key*) – a user’s username
- **str** – a user’s API key

get_request (*request*)

Sets token-based auth headers.

exception `SoftLayer.SoftLayerError`

The base SoftLayer error.

exception `SoftLayer.SoftLayerAPIError` (*fault_code, fault_string, *args*)

`SoftLayerAPIError` is an exception raised during API errors.

Provides `faultCode` and `faultString` properties.

class `SoftLayer.SoftLayerListResult` (*items, total_count*)

A SoftLayer API list result.

Command-line Interface

The SoftLayer command line interface is available via the `slcli` command available in your *PATH*. The `slcli` command is a reference implementation of SoftLayer API bindings for python and how to efficiently make API calls. See the *Usage Examples* section to see how to discover all of the functionality not fully documented here.

4.1 Interacting with IPSEC Tunnels

The IPSEC *Command-line Interface* commands can be used to configure an existing IPSEC tunnel context. Subnets in the SoftLayer private network can be associated to the tunnel context along with user-defined remote subnets. Address translation entries may also be defined to provide NAT functionality from static subnet IP addresses associated with the tunnel context to user-defined remote subnet IP addresses.

Note: Most CLI actions that affect an IPSEC tunnel context do not result in configuration changes to SoftLayer network devices. A separate `configure` command is available to issue a device configuration request.

To see more information about the IPSEC tunnel context module and API interaction, see *IPSEC Module* documentation.

4.1.1 ipsec list

A list of all IPSEC tunnel contexts associated with the current user's account can be retrieved via the `ipsec list` command. This provides a brief overview of all tunnel contexts and can be used to retrieve an individual context's identifier, which all other CLI commands require.

```
$ slcli ipsec list
:.....:
↪:.....:
: id :   name   : friendly name : internal peer IP address : remote peer IP address_
↪:         created          :
:.....:
↪:.....:
```

```

: 445 : ipsec038 : ipsec tunnel : 173.192.250.79 : 158.85.80.22
↔: 2012-03-05T14:07:34-06:00 :
:.....:
↔:.....:

```

4.1.2 ipsec detail

More detailed information can be retrieved for an individual context using the `ipsec detail` command. Using the detail command, information about associated internal subnets, remote subnets, static subnets, service subnets and address translations may also be retrieved using multiple instances of the `-i|--include` option.

```

$ slcli ipsec detail 445 -i at -i is -i rs -i sr -i ss
Context Details:
:.....:
:          name : value          :
:.....:
:          id : 445          :
:          name : ipsec038      :
:          friendly name : ipsec tunnel  :
:          internal peer IP address : 173.192.250.79 :
:          remote peer IP address : 158.85.80.22   :
:          advanced configuration flag : 0              :
:          preshared key : secret         :
:          phase 1 authentication : MD5            :
:          phase 1 diffie hellman group : 0             :
:          phase 1 encryption : DES            :
:          phase 1 key life : 240           :
:          phase 2 authentication : MD5            :
:          phase 2 diffie hellman group : 1             :
:          phase 2 encryption : DES            :
:          phase 2 key life : 240           :
:          phase 2 perfect forward secrecy : 1            :
:          created : 2012-03-05T14:07:34-06:00 :
:          modified : 2017-05-17T12:01:33-06:00 :
:.....:
Address Translations:
:.....:
↔:.....:
:  id : static IP address : static IP address id : remote IP address : remote IP
↔address id :      note          :
:.....:
↔:.....:
: 15920 : 10.1.249.86 : 9791681 : 158.85.80.22 : 98828
↔      : windows server :
: 15918 : 10.1.249.84 : 9791679 : 158.85.80.20 : 98824
↔      : unix server   :
:.....:
↔:.....:
Internal Subnets:
:.....:
:  id : network identifier : cidr : note :
:.....:
: 180767 : 10.28.67.128 : 26 :
:.....:
Remote Subnets:
:.....:

```

```

: id : network identifier : cidr : note :
:.....:.....:.....:.....:
: 7852 : 158.85.80.20 : 30 : :
:.....:.....:.....:.....:
Static Subnets:
:.....:.....:.....:.....:
: id : network identifier : cidr : note :
:.....:.....:.....:.....:
: 231807 : 10.1.249.84 : 30 : :
:.....:.....:.....:.....:
Service Subnets:
:.....:.....:.....:.....:
: id : network identifier : cidr : note :
:.....:.....:.....:.....:
: 162079 : 10.0.80.0 : 25 : :
:.....:.....:.....:.....:

```

4.1.3 ipsec update

Most values listed in the tunnel context detail printout can be modified using the `ipsec update` command. The following is given when executing with the `-h|--help` option and highlights all properties that may be modified.

```

$ slcli ipsec update -h
Usage: slcli ipsec update [OPTIONS] CONTEXT_ID

Update tunnel context properties.

Updates are made atomically, so either all are accepted or none are.

Key life values must be in the range 120-172800.

Phase 2 perfect forward secrecy must be in the range 0-1.

A separate configuration request should be made to realize changes on
network devices.

Options:
  --friendly-name TEXT           Friendly name value
  --remote-peer TEXT             Remote peer IP address value
  --preshared-key TEXT          Preshared key value
  --p1-auth, --phase1-auth [MD5|SHA1|SHA256]
                                Phase 1 authentication value
  --p1-crypto, --phase1-crypto [DES|3DES|AES128|AES192|AES256]
                                Phase 1 encryption value
  --p1-dh, --phase1-dh [0|1|2|5] Phase 1 diffie hellman group value
  --p1-key-ttl, --phase1-key-ttl INTEGER RANGE
                                Phase 1 key life value
  --p2-auth, --phase2-auth [MD5|SHA1|SHA256]
                                Phase 2 authentication value
  --p2-crypto, --phase2-crypto [DES|3DES|AES128|AES192|AES256]
                                Phase 2 encryption value
  --p2-dh, --phase2-dh [0|1|2|5] Phase 2 diffie hellman group value
  --p2-forward-secretcy, --phase2-forward-secretcy INTEGER RANGE
                                Phase 2 perfect forward secrecy value
  --p2-key-ttl, --phase2-key-ttl INTEGER RANGE
                                Phase 2 key life value

```

```
-h, --help
```

```
Show this message and exit.
```

4.1.4 ipsec configure

A request to configure SoftLayer network devices for a given tunnel context can be issued using the `ipsec configure` command.

Note: Once a configuration request is received, the IPSEC tunnel context will be placed into an unmodifiable state, and further changes against the tunnel context will be prevented. Once configuration changes have been made, the tunnel context may again be modified. The unmodifiable state of a tunnel context is indicated by an *advanced configuration flag* value of 1.

4.1.5 ipsec subnet-add

Internal, remote and service subnets can be associated to an IPSEC tunnel context using the `ipsec subnet-add` command. Additionally, remote subnets can be created using this same command, which will then be associated to the targeted tunnel context.

Note: The targeted subnet type must be specified. A subnet id must be provided when associating internal and service subnets. Either a subnet id or a network identifier must be provided when associating remote subnets. If a network identifier is provided when associating a remote subnet, that subnet will first be created and then associated to the tunnel context.

The following is an example of associating an internal subnet to a tunnel context.

```
$ slcli ipsec subnet-add 445 --subnet-id 180767 --subnet-type internal
Added internal subnet #180767
```

The following is an example of creating and associating a remote subnet to a tunnel context.

```
$ slcli ipsec subnet-add 445 --subnet-type remote --network 50.100.0.0/26
Created subnet 50.100.0.0/26 #21268
Added remote subnet #21268
```

4.1.6 ipsec subnet-remove

Internal, remote and service subnets can be disassociated from an IPSEC tunnel context via the `ipsec subnet-remove` command.

Note: The targeted subnet id and type must be specified. When disassociating remote subnets, that subnet record will also be deleted.

The following is an example of disassociating an internal subnet from a tunnel context.

```
$ slcli ipsec subnet-remove 445 --subnet-id 180767 --subnet-type internal
Removed internal subnet #180767
```


4.1.7 ipsec translation-add

Address translation entries can be added to a tunnel context to provide NAT functionality from a statically routed subnet associated with the tunnel context to a remote subnet. This action is performed with the `ipsec translation-add` command.

Note: Both static and remote IP address values must be specified. An optional note value may also be provided.

The following is an example of adding a new address translation entry.

```
$ slcli ipsec translation-add 445 --static-ip 10.1.249.87 --remote-ip 50.100.0.10 --
↳note 'email server'
Created translation from 10.1.249.87 to 50.100.0.10 #15922
```

4.1.8 ipsec translation-remove

Address translation entries can be removed using the `ipsec translation-remove` command.

The following is an example of removing an address translation entry.

```
$ slcli ipsec translation-remove 445 --translation-id 15922
Removed translation #15922
```

4.1.9 ipsec translation-update

Address translation entries may also be modified using the `ipsec translation-update` command.

The following is an example of updating an existing address translation entry.

```
$ slcli ipsec translation-update 445 --translation-id 15924 --static-ip 10.1.249.86 --
↳remote-ip 50.100.0.8 --note 'new email server'
Updated translation #15924
```

4.2 Working with Virtual Servers

Using the SoftLayer portal to order virtual servers is fine, but for a number of reasons it's often more convenient to use the command line. For this, you can use SoftLayer's command-line client to make administrative tasks quicker and easier. This page gives an intro to working with SoftLayer virtual servers using SoftLayer's command-line client.

Note: The following assumes that the client is already *configured with valid SoftLayer credentials*.

First, let's list the current virtual servers with `slcli vs list`.

```
$ slcli vs list
:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....
↳.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....
: id : datacenter : host : cores : memory : primary_ip : ↵
↳backend_ip : active_transaction : owner :
```

```
:.....:
↩.....:
:.....:
↩.....:
```

We don't have any virtual servers yet! Let's fix that. Before we can create a virtual server (VS), we need to know what options are available to us: RAM, CPU, operating systems, disk sizes, disk types, datacenters, and so on. Luckily, there's a simple command to show all options: *slcli vs create-options*.

```
$ slcli vs create-options
:.....:
↩.....:
:          Name : Value
↩          :
:.....:
↩.....:
:   datacenter : ams01,dal101,dal105,dal106,dal109,hkg02,hou02,lon02,mel101,par01,sea01,
↩sjc01,sng01,tor01,wdc01 :
:  cpus (private) : 1,2,4,8
↩          :
:  cpus (standard) : 1,2,4,8,12,16
↩          :
:      memory : 1024,2048,4096,6144,8192,12288,16384,32768,49152,65536
↩          :
:   os (CENTOS) : CENTOS_5_32
↩          :
:               : CENTOS_5_64
↩          :
:               : CENTOS_6_32
↩          :
:               : CENTOS_6_64
↩          :
:               : CENTOS_7_64
↩          :
:               : CENTOS_LATEST
↩          :
:               : CENTOS_LATEST_32
↩          :
:               : CENTOS_LATEST_64
↩          :
:  os (CLOUDLINUX) : CLOUDLINUX_5_32
↩          :
:               : CLOUDLINUX_5_64
↩          :
:               : CLOUDLINUX_6_32
↩          :
:               : CLOUDLINUX_6_64
↩          :
:               : CLOUDLINUX_LATEST
↩          :
:               : CLOUDLINUX_LATEST_32
↩          :
:               : CLOUDLINUX_LATEST_64
↩          :
:   os (DEBIAN) : DEBIAN_6_32
↩          :
:               : DEBIAN_6_64
↩          :
```

```

:           : DEBIAN_7_32                                     U
↪           :           :
:           : DEBIAN_7_64                                     U
↪           :           :
:           : DEBIAN_LATEST                                   U
↪           :           :
:           : DEBIAN_LATEST_32                               U
↪           :           :
:           : DEBIAN_LATEST_64                               U
↪           :           :
: os (REDHAT) : REDHAT_5_32                                   U
↪           :           :
:           : REDHAT_5_64                                     U
↪           :           :
:           : REDHAT_6_32                                     U
↪           :           :
:           : REDHAT_6_64                                     U
↪           :           :
:           : REDHAT_LATEST                                   U
↪           :           :
:           : REDHAT_LATEST_32                               U
↪           :           :
:           : REDHAT_LATEST_64                               U
↪           :           :
: os (UBUNTU) : UBUNTU_10_32                                  U
↪           :           :
:           : UBUNTU_10_64                                    U
↪           :           :
:           : UBUNTU_12_32                                    U
↪           :           :
:           : UBUNTU_12_64                                    U
↪           :           :
:           : UBUNTU_14_32                                    U
↪           :           :
:           : UBUNTU_14_64                                    U
↪           :           :
:           : UBUNTU_LATEST                                   U
↪           :           :
:           : UBUNTU_LATEST_32                               U
↪           :           :
:           : UBUNTU_LATEST_64                               U
↪           :           :
: os (VYATTACE) : VYATTACE_6.5_64                               U
↪           :           :
:           : VYATTACE_6.6_64                               U
↪           :           :
:           : VYATTACE_LATEST                                   U
↪           :           :
:           : VYATTACE_LATEST_64                             U
↪           :           :
: os (WIN) : WIN_2003-DC-SP2-1_32                            U
↪           :           :
:           : WIN_2003-DC-SP2-1_64                            U
↪           :           :
:           : WIN_2003-ENT-SP2-5_32                            U
↪           :           :
:           : WIN_2003-ENT-SP2-5_64                            U
↪           :           :

```

```

:           : WIN_2003-STD-SP2-5_32            
↪           :           :
:           : WIN_2003-STD-SP2-5_64            
↪           :           :
:           : WIN_2008-DC-R2_64              
↪           :           :
:           : WIN_2008-DC-SP2_64             
↪           :           :
:           : WIN_2008-ENT-R2_64             
↪           :           :
:           : WIN_2008-ENT-SP2_32            
↪           :           :
:           : WIN_2008-ENT-SP2_64            
↪           :           :
:           : WIN_2008-STD-R2-SP1_64         
↪           :           :
:           : WIN_2008-STD-R2_64             
↪           :           :
:           : WIN_2008-STD-SP2_32            
↪           :           :
:           : WIN_2008-STD-SP2_64            
↪           :           :
:           : WIN_2012-DC_64                 
↪           :           :
:           : WIN_2012-STD_64                
↪           :           :
:           : WIN_LATEST                      
↪           :           :
:           : WIN_LATEST_32                   
↪           :           :
:           : WIN_LATEST_64                  
↪           :           :
: local disk(0) : 25,100                     
↪           :           :
: local disk(2) : 25,100,150,200,300         
↪           :           :
: san disk(0)   : 25,100                      
↪           :           :
: san disk(2)   : 10,20,25,30,40,50,75,100,125,150,175,200,250,300,350,400,500,750,
↪1000,1500,2000 :
: san disk(3)   : 10,20,25,30,40,50,75,100,125,150,175,200,250,300,350,400,500,750,
↪1000,1500,2000 :
: san disk(4)   : 10,20,25,30,40,50,75,100,125,150,175,200,250,300,350,400,500,750,
↪1000,1500,2000 :
: san disk(5)   : 10,20,25,30,40,50,75,100,125,150,175,200,250,300,350,400,500,750,
↪1000,1500,2000 :
:           nic : 10,100,1000                 
↪           :           :
:.....:.....
↪.....:.....

```

Here's the command to create a 2-core virtual server with 1GiB memory, running Ubuntu 14.04 LTS, and that is billed on an hourly basis in the San Jose 1 datacenter using the command `slcli vs create`.

```

$ slcli vs create --hostname=example --domain=softlayer.com --cpu 2 --memory 1024 -o_
↪UBUNTU_14_64 --datacenter=sjc01 --billing=hourly
This action will incur charges on your account. Continue? [y/N]: y
:.....:.....

```

```

:   name : value
:.....:
:   id : 1234567
: created : 2013-06-13T08:29:44-06:00
:   guid : 6e013cde-a863-46ee-8s9a-f806dba97c89
:.....:

```

After the last command, the virtual server is now being built. It should instantly appear in your virtual server list now.

```

$ slcli vs list
:.....:
↪.....:
:   id : datacenter :          host          : cores : memory :   primary_ip   :
↪backend_ip : active_transaction :
:.....:
↪.....:
: 1234567 :   sjc01   : example.softlayer.com :    2   :   1G   : 108.168.200.11 : 10.
↪54.80.200 :   Assign Host   :
:.....:
↪.....:

```

Cool. You may ask, “It’s creating... but how do I know when it’s done?” Well, here’s how:

```

$ slcli vs ready 'example' --wait=600
READY

```

When the previous command returns, you’ll know that the virtual server has finished the provisioning process and is ready to use. This is *very* useful for chaining commands together.

Now that you have your virtual server, let’s get access to it. To do that, use the `slcli vs detail` command. From the example below, you can see that the username is ‘root’ and password is ‘ABCDEFGH’.

Warning: Be careful when using the `-passwords` flag. This will print the virtual server’s password on the screen. Make sure no one is looking over your shoulder. It’s also advisable to change your root password soon after creating your virtual server, or to create a user with sudo access and disable SSH-based login directly to the root account.

```

$ slcli vs detail example --passwords
:.....:
:   Name : Value
:.....:
:   id : 1234567
:   hostname : example.softlayer.com
:   status : Active
:   state : Running
:   datacenter : sjc01
:   cores : 2
:   memory : 1G
:   public_ip : 108.168.200.11
:   private_ip : 10.54.80.200
:   os : Ubuntu
: private_only : False
: private_cpu : False
:   created : 2013-06-13T08:29:44-06:00
:   modified : 2013-06-13T08:31:57-06:00

```

```
:      users : root ABCDEFGH      :
:.....:.....:.....:.....:.....:
```

There are many other commands to help manage virtual servers. To see them all, use `slcli help vs`.

```
$ slcli vs
Usage: slcli vs [OPTIONS] COMMAND [ARGS]...

Virtual Servers.

Options:
  --help  Show this message and exit.

Commands:
  cancel          Cancel virtual servers.
  capture         Capture SoftLayer image.
  create          Order/create virtual servers.
  create-options  Virtual server order options.
  credentials     List virtual server credentials.
  detail         Get details for a virtual server.
  dns-sync       Sync DNS records.
  edit           Edit a virtual server's details.
  list           List virtual servers.
  network        Manage network settings.
  pause          Pauses an active virtual server.
  power_off      Power off an active virtual server.
  power_on       Power on a virtual server.
  ready          Check if a virtual server is ready.
  reboot         Reboot an active virtual server.
  reload         Reload operating system on a virtual server.
  rescue         Reboot into a rescue image.
  resume         Resumes a paused virtual server.
  upgrade        Upgrade a virtual server.
```

4.3 Ordering

The Order *Command-line Interface* commands can be used to build an order for any product in the SoftLayer catalog.

The basic flow for ordering goes something like this...

1. package-list
2. category-list <package key name>
3. item-list <package key name>
4. place <package key name> <item key names> <location>

4.3.1 order package-list

This command will list all of the packages that are available to be ordered. This is the starting point for placing any order. Find the package keyName you want to order, and use it for the next steps.

Note:

- CLOUD_SERVER: These are Virtual Servers

- BARE_METAL_INSTANCE: Hourly Bare Metal
- BARE_METAL_SERVER: Other monthly server types
- #_PROC_#_DRIVES: Packages in this format will contain only this CPU model and Drive bays
- ADDITIONAL_PRODUCTS: Additional IPs, Vlans, SSL certs and other things are in here
- NETWORK_GATEWAY_APPLIANCE: Vyattas

Bluemix services listed here may still need to be ordered through the Bluemix CLI/Portal

4.3.2 order category-list

Shows all the available categories for a certain package, useful in finding the required categories. Categories that are required will need to have a corresponding item included with any orders

These are all the required categories for BARE_METAL_SERVER

```
$ slcli order category-list BARE_METAL_SERVER
:.....:
:      name      :      categoryCode      : isRequired :
:.....:
:      Server      :      server      :      Y      :
:      Operating System      :      os      :      Y      :
:      RAM      :      ram      :      Y      :
:      Disk Controller      :      disk_controller      :      Y      :
:      First Hard Drive      :      disk0      :      Y      :
:      Public Bandwidth      :      bandwidth      :      Y      :
:      Uplink Port Speeds      :      port_speed      :      Y      :
:      Remote Management      :      remote_management      :      Y      :
:      Primary IP Addresses      :      pri_ip_addresses      :      Y      :
:      VPN Management - Private Network      :      vpn_management      :      Y      :
:.....:
```

4.3.3 order item-list

Shows all the prices for a given package. Collect all the items you want included on your server. Don't forget to include the required category items. If forgotten, `order place` will tell you about it.

4.3.4 order preset-list

Some packages have presets which makes ordering significantly simpler. These will have set CPU / RAM / Disk allotments. You still need to specify required items

4.3.5 order place

Now that you have the package you want, the prices needed, and found a location, it is time to place an order.

`order place <preset>`

```
$ slcli --really order place --preset D2620V4_64GB_2X1TB_SATA_RAID_1 BARE_METAL_
↪SERVER TORONTO \
  OS_UBUNTU_16_04_LTS_XENIAL_XERUS_64_BIT \
  BANDWIDTH_0_GB_2 \
  1_GBPS_PRIVATE_NETWORK_UPLINK \
  REBOOT_KVM_OVER_IP 1_IP_ADDRESS \
  UNLIMITED_SSL_VPN_USERS_1_PPTP_VPN_USER_PER_ACCOUNT \
  --extras '{"hardware": [{"hostname": "testOrder", "domain": "cgallo.com"}]}' \
  --complex-type SoftLayer_Container_Product_Order_Hardware_Server
```

order place <Virtual Server>

```
$ slcli order place --billing hourly CLOUD_SERVER DALLAS13 \
  GUEST_CORES_4 \
  RAM_16_GB \
  REBOOT_REMOTE_CONSOLE \
  1_GBPS_PUBLIC_PRIVATE_NETWORK_UPLINKS \
  BANDWIDTH_0_GB_2 \
  1_IP_ADDRESS \
  GUEST_DISK_100_GB_SAN \
  OS_UBUNTU_16_04_LTS_XENIAL_XERUS_MINIMAL_64_BIT_FOR_VSI \
  MONITORING_HOST_PING \
  NOTIFICATION_EMAIL_AND_TICKET \
  AUTOMATED_NOTIFICATION \
  UNLIMITED_SSL_VPN_USERS_1_PPTP_VPN_USER_PER_ACCOUNT \
  NESSUS_VULNERABILITY_ASSESSMENT_REPORTING \
  --extras '{"virtualGuests": [{"hostname": "test", "domain": "softlayer.com"}]}' \
  --complex-type SoftLayer_Container_Product_Order_Virtual_Guest
```

4.4 Configuration Setup

To update the configuration, you can use *slcli setup*.

```
$ slcli setup
Username []: username
API Key or Password []:
Endpoint (public|private|custom): public
:.....:
:      Name : Value                               :
:.....:
:      Username : username                                     :
:      API Key  : oyVmeipYQCNrjVS4rF9bHWV7D75S6pa1fghF1384v7mwrCbHTfuJ8qRORIqoVnha :
:      Endpoint URL : https://api.softlayer.com/xmlrpc/v3/           :
:.....:
Are you sure you want to write settings to "/home/me/.softlayer"? [y/N]: y
```

To check the configuration, you can use *slcli config show*.

```
$ slcli config show
:.....:
:      Name : Value                               :
:.....:
:      Username : username                                     :
:.....:
```



```

:      API Key : oyVmeipYQCNrjVS4rF9bHWV7D75S6pa1fghF1384v7mwRCbHTfuJ8qRORIQoVnha :
: Endpoint URL : https://api.softlayer.com/xmlrpc/v3/                               :
:.....:.....:

```

To see more about the config file format, see [Configuration File](#).

4.5 Usage Examples

To discover the available commands, simply type `slcli`.

```

$ slcli
Usage: slcli [OPTIONS] COMMAND [ARGS]...

  SoftLayer Command-line Client

Options:
  --format [table|raw|json|jsonraw]
                                Output format [default: table]
  -C, --config PATH             Config file location [default:
                                ~/.softlayer]
  -v, --verbose                 Sets the debug noise level, specify multiple
                                times for more verbosity.
  --proxy TEXT                  HTTP[S] proxy to be use to make API calls
  -y, --really / --not-really   Confirm all prompt actions
  --demo / --no-demo            Use demo data instead of actually making API
                                calls
  --version                     Show the version and exit.
  -h, --help                    Show this message and exit.

Commands:
  block           Block Storage.
  call-api        Call arbitrary API endpoints.
  cdn             Content Delivery Network.
  config          CLI configuration.
  dns            Domain Name System.
  file           File Storage.
  firewall       Firewalls.
  globalip       Global IP addresses.
  hardware       Hardware servers.
  image          Compute images.
  loadbal        Load balancers.
  messaging      Message queue service.
  metadata       Find details about this machine.
  nas            Network Attached Storage.
  object-storage Object Storage.
  report         Reports.
  rwhois         Referral Whois.
  setup          Edit configuration.
  shell          Enters a shell for slcli.
  sshkey         SSH Keys.
  ssl            SSL Certificates.
  subnet        Network subnets.
  summary       Account summary.
  ticket        Support tickets.
  virtual       Virtual Servers.
  vlan          Network VLANs.

```

```
To use most commands your SoftLayer username and api_key need to be
configured. The easiest way to do that is to use: 'slcli setup'
```

As you can see, there are a number of commands/sections. To look at the list of subcommands for virtual servers type *slcli vs*. For example:

```
$ slcli vs
Usage: slcli vs [OPTIONS] COMMAND [ARGS]...

Virtual Servers.

Options:
  --help  Show this message and exit.

Commands:
  cancel          Cancel virtual servers.
  capture         Capture SoftLayer image.
  create          Order/create virtual servers.
  create-options  Virtual server order options.
  credentials     List virtual server credentials.
  detail          Get details for a virtual server.
  dns-sync        Sync DNS records.
  edit            Edit a virtual server's details.
  list            List virtual servers.
  network         Manage network settings.
  pause           Pauses an active virtual server.
  power_off       Power off an active virtual server.
  power_on        Power on a virtual server.
  ready           Check if a virtual server is ready.
  reboot          Reboot an active virtual server.
  reload          Reload operating system on a virtual server.
  rescue          Reboot into a rescue image.
  resume          Resumes a paused virtual server.
  upgrade         Upgrade a virtual server.
```

Finally, we can make an actual call. Let's list out the virtual servers on our account by using *slcli vs list*.

```
$ slcli vs list
:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....
↪.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:
:  id  : datacenter :      host      : cores : memory :  primary_ip  :  ↵
↪backend_ip : active_transaction :
:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....
↪.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:
: 1234567 :   sjc01    : test.example.com :    4   :    4G   :    12.34.56   :  65.
↪43.21   :             :                   :        :         :                :
:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....
↪.....:.....:.....:.....:.....:.....:.....:.....:.....:.....:.....
```

Most commands will take in additional options/arguments. To see all available actions, use *-help*.

```
$ slcli vs list --help
Usage: slcli vs list [OPTIONS]

List virtual servers.

Options:
```

```
--sortby [guid|hostname|primary_ip|backend_ip|datacenter]
                                     Column to sort by
-c, --cpu INTEGER                     Number of CPU cores
-D, --domain TEXT                     Domain portion of the FQDN
-d, --datacenter TEXT                 Datacenter shortname
-H, --hostname TEXT                  Host portion of the FQDN
-m, --memory INTEGER                 Memory in mebibytes
-n, --network TEXT                   Network port speed in Mbps
--hourly                             Show only hourly instances
--monthly                             Show only monthly instances
--tags TEXT                           Show instances that have one of these comma-
                                     separated tags
--help                                Show this message and exit.
```


5.1 Contribution Guide

This page explains how to get started contributing code to the SoftLayer API Python Bindings project.

5.1.1 Code Organization

- **docs** - Where The source to this documentation lives.
- **SoftLayer** - All the source lives under here.
 - **API** - Primary API client.
 - **CLI** - Code for the command-line interface.
 - **managers** - API Managers. Abstractions to help use the API.

5.1.2 Setting Up A Dev Environment

Before working with the SoftLayer Python API client source, we strongly recommend that you know how to use Python's virtual environment, [virtualenv](#). Virtualenv allows you to create isolated Python environments that are individually tailored to particular development projects. Each environment can have its own set of libraries and even its own Python interpreter. This keeps them fully isolated, reducing the possibility of library conflicts between different projects.

After you have virtualenv, you should set up a virtual environment and activate it whenever you are working on softlayer-python. The commands needed to setup an environment and activate it might look something like this:

```
virtualenv --no-site-packages softlayer_env
source softlayer_env/bin/activate
```

Please refer to the virtualenv documentation for more information about creating, and working with virtual environments.

Once you have an appropriate environment, you will then download the SoftLayer API Python Bindings source code by following the [installation instructions](#). Change into `softlayer-python` source directory and run the following to install the pre-requisites that you'll need in order to run the test suites:

```
pip install -r tools/test-requirements.txt
```

5.1.3 Testing

The project has a mix of functional and unit tests. Before submitting changes to be integrated into the project, you should validate your code using `tox`. Simply issue the `tox` command from the root of the source tree:

```
tox
```

In addition to testing different versions of Python, `tox` checks for common mistakes in the code using `Flake8` and `pylint`. You should eliminate the linting errors that are reported before submitting your code. You can run only the linting checks by using this command:

```
tox -eanalysis
```

The project's configuration instructs `tox` to test against many different versions of Python. A `tox` test will use as many of those as it can find on your local computer. Rather than installing all those versions, we recommend that you point the [Travis](#) continuous integration tool at your GitHub fork. Travis will run the test against the full suite of Python versions every time you push new code.

Using `tox` to run tests in multiple environments can be very time consuming. If you wish to quickly run the tests in your own environment, you may do so using `py.test`. The command to do that is:

```
py.test tests
```

5.1.4 Documentation

The project is documented in `reStructuredText` and built using `Sphinx`. If you have `fabric` installed, you simply need to run the following to build the docs:

```
fab make_html
```

The documentation will be built in `docs/_build/html`. If you don't have `fabric`, use the following commands.

```
cd docs
make html
```

The primary docs are built at [Read the Docs](#).

5.1.5 Style

This project tries to follow [PEP 8](#) and most of the style suggestions that `pyflakes` recommends. Run `Flake8` regularly. `Flake8`, with project-specific exceptions, can be run by using `tox`:

```
tox -e analysis
```

5.1.6 Contributing

Contributing to the Python API bindings follows the [fork-pull-request model](#) on [GitHub](#). The project uses GitHub's [issue tracker](#) and [pull requests](#) to manage source control, bug fixes and new feature development regarding the API bindings and the CLI. In order to contribute, we require that you sign a contributor agreement:

- Sign our contributor agreement (CLA) You can find the [CLA](#) [here](#).
- If you're contributing on behalf of your employer we'll need a signed copy of our corporate contributor agreement (CCLA) as well. You can find the [CCLA](#) [here](#).

5.1.7 Developer Resources

5.2 Command-Line Interface Developer Guide

The SoftLayer CLI can be used to manage many different SoftLayer services directly from the command line.

The command line parsing is currently based on [click](#), which is a command parsing library along with some additions to dynamically load modules from a routes-like file and from [entry points](#).

5.2.1 First Example

For the first example, we can create `slcli table-example` by creating the following file at `SoftLayer/CLI/table_example.py`:

```

"""A formatting table example."""
from SoftLayer.CLI import environment
from SoftLayer.CLI import formatting

import click

@click.command()
@environment.pass_env
def cli(env):
    """This returns a table that highlights how tables are output"""
    # create a table with two columns: col1, col2
    table = formatting.Table(['col1', 'col2'])

    # align the data facing each other
    # valid values are r, c, l for right, center, left
    # note, these are suggestions based on the format chosen by the user
    table.align['col1'] = 'r'
    table.align['col2'] = 'l'

    # add rows
    table.add_row(['test', 'test'])
    table.add_row(['test2', 'test2'])

    env.fout(table)

```

Then we need to register it so that `slcli table-example` will know to route to this new module. We do that by adding `ALL_ROUTES` in `SoftLayer/CLI/routes.py` to include the following:

```
...
('table-example', 'SoftLayer.CLI.table_example:cli'),
...
```

Which gives us

```
$ slcli table-example
:.....:.....:
:  col1 : col2  :
:.....:.....:
:  test : test   :
: test2 : test2  :
:.....:.....:

$ slcli --format=raw table-example
test  test
test2 test2
```

Formatting of the data represented in the table is actually controlled upstream from the `CLIRunnable`'s making supporting more data formats in the future easier.

5.2.2 Arguments

A command usually isn't very useful without context or arguments of some kind. With click, you have a large array of argument and option types at your disposal. Additionally, with the SoftLayer CLI, we have global options and context which is stored in `SoftLayer.CLI.environment.Environment` and is attainable through a decorator located at `SoftLayer.CLI.environment.pass_env`. An example of options and the environment is shown below. It also shows how output should be done using `env.out` instead of printing. This is used for testing and to have a consistent way to print things onto the screen.

```
from SoftLayer.CLI import environment

import click

@click.command()
@click.option("--number",
              required=True,
              type=click.INT,
              help="print different output")
@click.option("--choice",
              type=click.Choice(['this', 'that']),
              help="print different output")
@click.option("--test", help="print different output")
@environment.pass_env
def cli(env, number, choice, test):
    """Argument parsing example"""

    if test:
        env.out("Just testing, move along...")
    else:
        env.out("This is fo'realz!")

    if choice == 'this':
        env.out("Selected this")
    elif choice == 'that':
```



```
env.out("Selected that")

env.out("This is a number: %d" % number)
```

Refer to the click library documentation for more options.

5.2.3 Accessing the API

A `SoftLayer` client is stood up for every command and is available through `SoftLayer.CLI.environment.Environment.client`. The example below shows how to make a simple API call to the `SoftLayer_Account::getObject`.

```
from SoftLayer.CLI import environment

import click

@click.command()
@environment.pass_env
def cli(env):
    """Using the SoftLayer API client"""

    account = env.client['Account'].getObject()
    return account['companyName']
```

5.2.4 Aborting execution

When a confirmation fails, you probably want to stop execution and give a non-zero exit code. To do that, raise a `SoftLayer.CLI.exceptions.CLIAbort` exception with the message for the user as the first parameter. This will prevent any further execution and properly return the right error code.

```
raise CLIAbort("Aborting. Failed confirmation")
```


CHAPTER 6

External Links

- [SoftLayer API Documentation](#)
- [Source on GitHub](#)
- [Issues](#)
- [Pull Requests](#)
- [PyPI](#)
- [Twitter](#)
- [#softlayer on freenode](#)

S

`SoftLayer`, [61](#)
`SoftLayer.managers.block`, [8](#)
`SoftLayer.managers.cdn`, [13](#)
`SoftLayer.managers.dedicated_host`, [14](#)
`SoftLayer.managers.dns`, [16](#)
`SoftLayer.managers.file`, [17](#)
`SoftLayer.managers.firewall`, [22](#)
`SoftLayer.managers.hardware`, [24](#)
`SoftLayer.managers.image`, [28](#)
`SoftLayer.managers.ipsec`, [29](#)
`SoftLayer.managers.load_balancer`, [33](#)
`SoftLayer.managers.messaging`, [35](#)
`SoftLayer.managers.metadata`, [39](#)
`SoftLayer.managers.network`, [39](#)
`SoftLayer.managers.ordering`, [44](#)
`SoftLayer.managers.sshkey`, [48](#)
`SoftLayer.managers.ssl`, [49](#)
`SoftLayer.managers.ticket`, [50](#)
`SoftLayer.managers.vs`, [52](#)

A

- add_certificate() (SoftLayer.managers.ssl.SSLManager method), 50
- add_global_ip() (SoftLayer.managers.network.NetworkManager method), 40
- add_internal_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 29
- add_key() (SoftLayer.managers.sshkey.SshKeyManager method), 48
- add_local_lb() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 33
- add_origin() (SoftLayer.managers.cdn.CDNManager method), 13
- add_remote_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 30
- add_securitygroup_rule() (SoftLayer.managers.network.NetworkManager method), 40
- add_securitygroup_rules() (SoftLayer.managers.network.NetworkManager method), 40
- add_service() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 33
- add_service_group() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 33
- add_service_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 30
- add_standard_firewall() (SoftLayer.managers.firewall.FirewallManager method), 22
- add_subnet() (SoftLayer.managers.network.NetworkManager method), 40
- add_vlan_firewall() (SoftLayer.managers.firewall.FirewallManager method), 23
- apply_configuration() (SoftLayer.managers.ipsec.IPSECManger method), 30
- assign_global_ip() (SoftLayer.managers.network.NetworkManager method), 40
- attach_hardware() (SoftLayer.managers.ticket.TicketManager method), 51
- attach_securitygroup_component() (SoftLayer.managers.network.NetworkManager method), 41
- attach_securitygroup_components() (SoftLayer.managers.network.NetworkManager method), 41
- attach_virtual_server() (SoftLayer.managers.ticket.TicketManager method), 51
- auth() (SoftLayer.managers.messaging.QueueAuth method), 38
- authenticate() (SoftLayer.managers.messaging.MessagingConnection method), 35
- authenticate_with_password() (SoftLayer.BaseClient method), 61
- authorize_host_to_volume() (SoftLayer.managers.block.BlockStorageManager method), 8
- authorize_host_to_volume() (SoftLayer.managers.file.FileStorageManager method), 18

B

- BaseClient (class in SoftLayer), 61
- BasicAuthentication (class in SoftLayer), 63
- BlockStorageManager (class in SoftLayer.managers.block), 8

C

- call() (SoftLayer.BaseClient method), 61

cancel_block_volume() (SoftLayer.managers.block.BlockStorageManager method), 8

cancel_file_volume() (SoftLayer.managers.file.FileStorageManager method), 18

cancel_firewall() (SoftLayer.managers.firewall.FirewallManager method), 23

cancel_global_ip() (SoftLayer.managers.network.NetworkManager method), 41

cancel_hardware() (SoftLayer.managers.hardware.HardwareManager method), 24

cancel_instance() (SoftLayer.managers.vs.VSManager method), 53

cancel_lb() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 33

cancel_snapshot_space() (SoftLayer.managers.block.BlockStorageManager method), 9

cancel_snapshot_space() (SoftLayer.managers.file.FileStorageManager method), 18

cancel_subnet() (SoftLayer.managers.network.NetworkManager method), 41

capture() (SoftLayer.managers.vs.VSManager method), 53

CDNManager (class in SoftLayer.managers.cdn), 13

change_port_speed() (SoftLayer.managers.hardware.HardwareManager method), 25

change_port_speed() (SoftLayer.managers.vs.VSManager method), 53

Client() (in module SoftLayer), 63

create_client_from_env() (in module SoftLayer), 62

create_instance() (SoftLayer.managers.vs.VSManager method), 54

create_instances() (SoftLayer.managers.vs.VSManager method), 55

create_or_update_lun_id() (SoftLayer.managers.block.BlockStorageManager method), 9

create_queue() (SoftLayer.managers.messaging.MessagingConnection method), 35

create_record() (SoftLayer.managers.dns.DNSManager method), 16

create_remote_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 30

create_securitygroup() (SoftLayer.managers.network.NetworkManager method), 41

create_snapshot() (SoftLayer.managers.block.BlockStorageManager method), 9

create_snapshot() (SoftLayer.managers.file.FileStorageManager method), 18

create_subscription() (SoftLayer.managers.messaging.MessagingConnection method), 36

create_ticket() (SoftLayer.managers.ticket.TicketManager method), 51

create_topic() (SoftLayer.managers.messaging.MessagingConnection method), 36

create_translation() (SoftLayer.managers.ipsec.IPSECManger method), 30

create_zone() (SoftLayer.managers.dns.DNSManager method), 16

D

deauthorize_host_to_volume() (SoftLayer.managers.block.BlockStorageManager method), 9

deauthorize_host_to_volume() (SoftLayer.managers.file.FileStorageManager method), 18

DedicatedHostManager (class in SoftLayer.managers.dedicated_host), 14

delete_image() (SoftLayer.managers.image.ImageManager method), 28

delete_key() (SoftLayer.managers.sshkey.SshKeyManager method), 49

delete_message() (SoftLayer.managers.messaging.MessagingConnection method), 36

delete_queue() (SoftLayer.managers.messaging.MessagingConnection method), 36

delete_record() (SoftLayer.managers.dns.DNSManager method), 16

delete_remote_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 30

delete_securitygroup() (SoftLayer.managers.network.NetworkManager method), 41

delete_service() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34

delete_service_group() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34

delete_snapshot() (SoftLayer.managers.block.BlockStorageManager method), 9

- delete_snapshot() (SoftLayer.managers.file.FileStorageManager method), 19
- delete_subscription() (SoftLayer.managers.messaging.MessagingConnection method), 36
- delete_topic() (SoftLayer.managers.messaging.MessagingConnection method), 36
- delete_zone() (SoftLayer.managers.dns.DNSManager method), 16
- detach_hardware() (SoftLayer.managers.ticket.TicketManager method), 51
- detach_securitygroup_component() (SoftLayer.managers.network.NetworkManager method), 41
- detach_securitygroup_components() (SoftLayer.managers.network.NetworkManager method), 41
- detach_virtual_server() (SoftLayer.managers.ticket.TicketManager method), 51
- disable_snapshots() (SoftLayer.managers.block.BlockStorageManager method), 9
- disable_snapshots() (SoftLayer.managers.file.FileStorageManager method), 19
- DNSManager (class in SoftLayer.managers.dns), 16
- dump_zone() (SoftLayer.managers.dns.DNSManager method), 16
- ## E
- edit() (SoftLayer.managers.hardware.HardwareManager method), 25
- edit() (SoftLayer.managers.image.ImageManager method), 28
- edit() (SoftLayer.managers.vs.VSManager method), 56
- edit_certificate() (SoftLayer.managers.ssl.SSLManager method), 50
- edit_dedicated_fw_rules() (SoftLayer.managers.firewall.FirewallManager method), 23
- edit_key() (SoftLayer.managers.sshkey.SshKeyManager method), 49
- edit_record() (SoftLayer.managers.dns.DNSManager method), 17
- edit_rwhois() (SoftLayer.managers.network.NetworkManager method), 41
- edit_securitygroup() (SoftLayer.managers.network.NetworkManager method), 42
- edit_securitygroup_rule() (SoftLayer.managers.network.NetworkManager method), 42
- edit_service() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34
- edit_service_group() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34
- edit_standard_fw_rules() (SoftLayer.managers.firewall.FirewallManager method), 23
- edit_zone() (SoftLayer.managers.dns.DNSManager method), 17
- enable_snapshots() (SoftLayer.managers.block.BlockStorageManager method), 9
- enable_snapshots() (SoftLayer.managers.file.FileStorageManager method), 19
- export_image_to_uri() (SoftLayer.managers.image.ImageManager method), 28
- ## F
- failback_from_replicant() (SoftLayer.managers.block.BlockStorageManager method), 10
- failback_from_replicant() (SoftLayer.managers.file.FileStorageManager method), 19
- failover_to_replicant() (SoftLayer.managers.block.BlockStorageManager method), 10
- failover_to_replicant() (SoftLayer.managers.file.FileStorageManager method), 19
- FileStorageManager (class in SoftLayer.managers.file), 17
- filter_outlet_packages() (SoftLayer.managers.ordering.OrderingManager static method), 44
- FirewallManager (class in SoftLayer.managers.firewall), 22
- ## G
- generate_order() (SoftLayer.managers.ordering.OrderingManager method), 45
- generate_order_template() (SoftLayer.managers.ordering.OrderingManager method), 45
- get() (SoftLayer.managers.metadata.MetadataManager method), 39
- get_account() (SoftLayer.managers.cdn.CDNManager method), 13
- get_block_volume_access_list() (SoftLayer.managers.block.BlockStorageManager method), 42

method), 10

get_block_volume_details() (SoftLayer.managers.block.BlockStorageManager method), 10

get_block_volume_snapshot_list() (SoftLayer.managers.block.BlockStorageManager method), 10

get_cancellation_reasons() (SoftLayer.managers.hardware.HardwareManager method), 25

get_certificate() (SoftLayer.managers.ssl.SSLManager method), 50

get_connection() (SoftLayer.managers.messaging.MessagingManager method), 38

get_create_options() (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 15

get_create_options() (SoftLayer.managers.hardware.HardwareManager method), 26

get_create_options() (SoftLayer.managers.vs.VSManager method), 56

get_dedicated_fw_rules() (SoftLayer.managers.firewall.FirewallManager method), 23

get_dedicated_package() (SoftLayer.managers.firewall.FirewallManager method), 23

get_endpoint() (SoftLayer.managers.messaging.MessagingManager method), 38

get_endpoints() (SoftLayer.managers.messaging.MessagingManager method), 38

get_file_volume_access_list() (SoftLayer.managers.file.FileStorageManager method), 19

get_file_volume_details() (SoftLayer.managers.file.FileStorageManager method), 20

get_file_volume_snapshot_list() (SoftLayer.managers.file.FileStorageManager method), 20

get_firewalls() (SoftLayer.managers.firewall.FirewallManager method), 23

get_hardware() (SoftLayer.managers.hardware.HardwareManager method), 26

get_hc_types() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34

get_host() (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 15

get_image() (SoftLayer.managers.image.ImageManager method), 28

get_instance() (SoftLayer.managers.vs.VSManager method), 56

get_key() (SoftLayer.managers.sshkey.SshKeyManager method), 49

get_lb_pkgs() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34

get_local_lb() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34

get_local_lbs() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 34

get_nas_credentials() (SoftLayer.managers.network.NetworkManager method), 42

get_only_active_packages() (SoftLayer.managers.ordering.OrderingManager static method), 45

get_order_container() (SoftLayer.managers.ordering.OrderingManager method), 45

get_origins() (SoftLayer.managers.cdn.CDNManager method), 14

get_package_by_key() (SoftLayer.managers.ordering.OrderingManager method), 45

get_package_by_type() (SoftLayer.managers.ordering.OrderingManager method), 46

get_package_id_by_type() (SoftLayer.managers.ordering.OrderingManager method), 46

get_packages_of_type() (SoftLayer.managers.ordering.OrderingManager method), 46

get_packages_by_key() (SoftLayer.managers.ordering.OrderingManager method), 46

get_price_id_list() (SoftLayer.managers.ordering.OrderingManager method), 46

get_queue() (SoftLayer.managers.messaging.MessagingConnection method), 36

get_queues() (SoftLayer.managers.messaging.MessagingConnection method), 36

get_quote_details() (SoftLayer.managers.ordering.OrderingManager method), 46

get_quotes() (SoftLayer.managers.ordering.OrderingManager method), 46

get_records() (SoftLayer.managers.dns.DNSManager method), 17

get_records() (SoftLayer.managers.dns.DNSManager method), 17

get_replication_locations() (SoftLayer.managers.block.BlockStorageManager method), 11

- [get_replication_locations\(\)](#) (SoftLayer.managers.file.FileStorageManager method), 20
[get_replication_partners\(\)](#) (SoftLayer.managers.block.BlockStorageManager method), 11
[get_replication_partners\(\)](#) (SoftLayer.managers.file.FileStorageManager method), 20
[get_request\(\)](#) (SoftLayer.BasicAuthentication method), 63
[get_router_options\(\)](#) (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 15
[get_routing_methods\(\)](#) (SoftLayer.managers.load_balancer.LoadBalancerManager method), 35
[get_routing_types\(\)](#) (SoftLayer.managers.load_balancer.LoadBalancerManager method), 35
[get_rwhois\(\)](#) (SoftLayer.managers.network.NetworkManager method), 42
[get_securitygroup\(\)](#) (SoftLayer.managers.network.NetworkManager method), 42
[get_standard_fw1_rules\(\)](#) (SoftLayer.managers.firewall.FirewallManager method), 23
[get_standard_package\(\)](#) (SoftLayer.managers.firewall.FirewallManager method), 24
[get_subnet\(\)](#) (SoftLayer.managers.network.NetworkManager method), 42
[get_subscriptions\(\)](#) (SoftLayer.managers.messaging.MessagingConnection method), 37
[get_ticket\(\)](#) (SoftLayer.managers.ticket.TicketManager method), 51
[get_topic\(\)](#) (SoftLayer.managers.messaging.MessagingConnection method), 37
[get_topics\(\)](#) (SoftLayer.managers.messaging.MessagingConnection method), 37
[get_translation\(\)](#) (SoftLayer.managers.ipsec.IPSECMANAGER method), 31
[get_translations\(\)](#) (SoftLayer.managers.ipsec.IPSECMANAGER method), 31
[get_tunnel_context\(\)](#) (SoftLayer.managers.ipsec.IPSECMANAGER method), 31
[get_tunnel_contexts\(\)](#) (SoftLayer.managers.ipsec.IPSECMANAGER method), 31
[get_vlan\(\)](#) (SoftLayer.managers.network.NetworkManager method), 42
[get_zone\(\)](#) (SoftLayer.managers.dns.DNSManager method), 17
H
[handle_error\(\)](#) (SoftLayer.managers.messaging.QueueAuth method), 38
[HardwareManager](#) (class in SoftLayer.managers.hardware), 24
[has_firewall\(\)](#) (in module SoftLayer.managers.firewall), 24
I
[ImageManager](#) (class in SoftLayer.managers.image), 28
[import_image_from_uri\(\)](#) (SoftLayer.managers.image.ImageManager method), 29
[ip_lookup\(\)](#) (SoftLayer.managers.network.NetworkManager method), 43
[IPSECMANAGER](#) (class in SoftLayer.managers.ipsec), 29
[inter_call\(\)](#) (SoftLayer.BaseClient method), 62
L
[list_accounts\(\)](#) (SoftLayer.managers.cdn.CDNManager method), 14
[list_accounts\(\)](#) (SoftLayer.managers.messaging.MessagingManager method), 38
[list_block_volumes\(\)](#) (SoftLayer.managers.block.BlockStorageManager method), 11
[list_categories\(\)](#) (SoftLayer.managers.ordering.OrderingManager method), 46
[list_certs\(\)](#) (SoftLayer.managers.ssl.SSLManager method), 50
[list_file_volumes\(\)](#) (SoftLayer.managers.file.FileStorageManager method), 20
[list_global_ips\(\)](#) (SoftLayer.managers.network.NetworkManager method), 43
[list_hardware\(\)](#) (SoftLayer.managers.hardware.HardwareManager method), 26
[list_instances\(\)](#) (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 15
[list_instances\(\)](#) (SoftLayer.managers.vs.VSManager method), 57
[list_items\(\)](#) (SoftLayer.managers.ordering.OrderingManager method), 46
[list_keys\(\)](#) (SoftLayer.managers.sshkey.SshKeyManager method), 49
[list_packages\(\)](#) (SoftLayer.managers.ordering.OrderingManager method), 47
[list_presets\(\)](#) (SoftLayer.managers.ordering.OrderingManager method), 47

list_private_images() (SoftLayer.managers.image.ImageManager method), 29

list_public_images() (SoftLayer.managers.image.ImageManager method), 29

list_securitygroup_rules() (SoftLayer.managers.network.NetworkManager method), 43

list_securitygroups() (SoftLayer.managers.network.NetworkManager method), 43

list_subjects() (SoftLayer.managers.ticket.TicketManager method), 52

list_subnets() (SoftLayer.managers.network.NetworkManager method), 43

list_tickets() (SoftLayer.managers.ticket.TicketManager method), 52

list_vlans() (SoftLayer.managers.network.NetworkManager method), 43

list_volume_schedules() (SoftLayer.managers.block.BlockStorageManager method), 11

list_volume_schedules() (SoftLayer.managers.file.FileStorageManager method), 20

list_zones() (SoftLayer.managers.dns.DNSManager method), 17

load_content() (SoftLayer.managers.cdn.CDNManager method), 14

LoadBalancerManager (class in SoftLayer.managers.load_balancer), 33

method), 11

order_duplicate_volume() (SoftLayer.managers.block.BlockStorageManager method), 12

order_duplicate_volume() (SoftLayer.managers.file.FileStorageManager method), 20

order_file_volume() (SoftLayer.managers.file.FileStorageManager method), 21

order_modified_volume() (SoftLayer.managers.block.BlockStorageManager method), 12

order_modified_volume() (SoftLayer.managers.file.FileStorageManager method), 21

order_quote() (SoftLayer.managers.ordering.OrderingManager method), 47

order_replicant_volume() (SoftLayer.managers.block.BlockStorageManager method), 12

order_replicant_volume() (SoftLayer.managers.file.FileStorageManager method), 21

order_snapshot_space() (SoftLayer.managers.block.BlockStorageManager method), 12

order_snapshot_space() (SoftLayer.managers.file.FileStorageManager method), 22

OrderingManager (class in SoftLayer.managers.ordering), 44

M

MessagingConnection (class in SoftLayer.managers.messaging), 35

MessagingManager (class in SoftLayer.managers.messaging), 38

METADATA_ATTRIBUTES (SoftLayer.managers.metadata attribute), 39

MetadataManager (class in SoftLayer.managers.metadata), 39

modify_queue() (SoftLayer.managers.messaging.MessagingConnection method), 37

modify_topic() (SoftLayer.managers.messaging.MessagingConnection method), 37

N

NetworkManager (class in SoftLayer.managers.network), 40

O

order_block_volume() (SoftLayer.managers.block.BlockStorageManager

P

package_locations() (SoftLayer.managers.ordering.OrderingManager method), 47

ping() (SoftLayer.managers.messaging.MessagingManager method), 38

place_order() (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 15

place_order() (SoftLayer.managers.hardware.HardwareManager method), 26

place_order() (SoftLayer.managers.ordering.OrderingManager method), 47

pop_message() (SoftLayer.managers.messaging.MessagingConnection method), 37

pop_messages() (SoftLayer.managers.messaging.MessagingConnection method), 37

private_network() (SoftLayer.managers.metadata.MetadataManager method), 39

public_network() (SoftLayer.managers.metadata.MetadataManager

- method), 39
- purge_content() (SoftLayer.managers.cdn.CDNManager method), 14
- push_queue_message() (SoftLayer.managers.messaging.MessagingConnection method), 37
- push_topic_message() (SoftLayer.managers.messaging.MessagingConnection method), 37
- Python Enhancement Proposals
PEP 8, 82
- ## Q
- QueueAuth (class in SoftLayer.managers.messaging), 38
- ## R
- reload() (SoftLayer.managers.hardware.HardwareManager method), 27
- reload_instance() (SoftLayer.managers.vs.VSManager method), 57
- remove_certificate() (SoftLayer.managers.ssl.SSLManager method), 50
- remove_internal_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 31
- remove_origin() (SoftLayer.managers.cdn.CDNManager method), 14
- remove_remote_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 31
- remove_securitygroup_rule() (SoftLayer.managers.network.NetworkManager method), 44
- remove_securitygroup_rules() (SoftLayer.managers.network.NetworkManager method), 44
- remove_service_subnet() (SoftLayer.managers.ipsec.IPSECManger method), 31
- remove_translation() (SoftLayer.managers.ipsec.IPSECManger method), 32
- rescue() (SoftLayer.managers.hardware.HardwareManager method), 27
- rescue() (SoftLayer.managers.vs.VSManager method), 58
- reset_service_group() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 35
- resolve_global_ip_ids() (SoftLayer.managers.network.NetworkManager method), 44
- resolve_ids() (SoftLayer.managers.block.BlockStorageManager method), 13
- resolve_ids() (SoftLayer.managers.cdn.CDNManager method), 14
- resolve_ids() (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 16
- resolve_ids() (SoftLayer.managers.dns.DNSManager method), 17
- resolve_ids() (SoftLayer.managers.file.FileStorageManager method), 22
- resolve_ids() (SoftLayer.managers.firewall.FirewallManager method), 24
- resolve_ids() (SoftLayer.managers.hardware.HardwareManager method), 27
- resolve_ids() (SoftLayer.managers.image.ImageManager method), 29
- resolve_ids() (SoftLayer.managers.ipsec.IPSECManger method), 32
- resolve_ids() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 35
- resolve_ids() (SoftLayer.managers.sshkey.SshKeyManager method), 49
- resolve_ids() (SoftLayer.managers.ticket.TicketManager method), 52
- resolve_ids() (SoftLayer.managers.vs.VSManager method), 58
- resolve_subnet_ids() (SoftLayer.managers.network.NetworkManager method), 44
- resolve_vlan_ids() (SoftLayer.managers.network.NetworkManager method), 44
- restore_from_snapshot() (SoftLayer.managers.block.BlockStorageManager method), 13
- restore_from_snapshot() (SoftLayer.managers.file.FileStorageManager method), 22
- ## S
- set_credential_password() (SoftLayer.managers.block.BlockStorageManager method), 13
- set_tags() (SoftLayer.managers.vs.VSManager method), 58
- SoftLayer (module), 61
- SoftLayer.managers.block (module), 8
- SoftLayer.managers.cdn (module), 13
- SoftLayer.managers.dedicated_host (module), 14
- SoftLayer.managers.dns (module), 16
- SoftLayer.managers.file (module), 17
- SoftLayer.managers.firewall (module), 22
- SoftLayer.managers.hardware (module), 24
- SoftLayer.managers.image (module), 28
- SoftLayer.managers.ipsec (module), 29
- SoftLayer.managers.load_balancer (module), 33

SoftLayer.managers.messaging (module), 35
 SoftLayer.managers.metadata (module), 39
 SoftLayer.managers.network (module), 39
 SoftLayer.managers.ordering (module), 44
 SoftLayer.managers.sshkey (module), 48
 SoftLayer.managers.ssl (module), 49
 SoftLayer.managers.ticket (module), 50
 SoftLayer.managers.vs (module), 52
 SoftLayerAPIError, 63
 SoftLayerError, 63
 SoftLayerListResult (class in SoftLayer), 63
 SshKeyManager (class in SoftLayer.managers.sshkey), 48
 SSLManager (class in SoftLayer.managers.ssl), 49
 stats() (SoftLayer.managers.messaging.MessagingConnection method), 38
 summary_by_datacenter() (SoftLayer.managers.network.NetworkManager method), 44

T

TicketManager (class in SoftLayer.managers.ticket), 51
 toggle_service_status() (SoftLayer.managers.load_balancer.LoadBalancerManager method), 35

U

unassign_global_ip() (SoftLayer.managers.network.NetworkManager method), 44
 update_firmware() (SoftLayer.managers.hardware.HardwareManager method), 27
 update_ticket() (SoftLayer.managers.ticket.TicketManager method), 52
 update_translation() (SoftLayer.managers.ipsec.IPSECManager method), 32
 update_tunnel_context() (SoftLayer.managers.ipsec.IPSECManager method), 32
 upgrade() (SoftLayer.managers.vs.VSManager method), 58
 upload_attachment() (SoftLayer.managers.ticket.TicketManager method), 52

V

verify_create_instance() (SoftLayer.managers.vs.VSManager method), 58
 verify_order() (SoftLayer.managers.dedicated_host.DedicatedHostManager method), 16

verify_order() (SoftLayer.managers.hardware.HardwareManager method), 27
 verify_order() (SoftLayer.managers.ordering.OrderingManager method), 47
 verify_quote() (SoftLayer.managers.ordering.OrderingManager method), 48
 VSManager (class in SoftLayer.managers.vs), 52

W

wait_for_ready() (SoftLayer.managers.hardware.HardwareManager method), 28
 wait_for_ready() (SoftLayer.managers.vs.VSManager method), 59
 wait_for_transaction() (SoftLayer.managers.vs.VSManager method), 59