Maya Math Nodes Documentation

Serguei Kalentchouk

Jan 10, 2019

User Documentation

CHAPTER 1

Node Reference

1.1 Overview

The nodes are designed with the following principles in mind:

- nodes perform a single operation
- nodes have a single output attribute
- nodes are strongly typed

Note: In order to achieve consistency and streamlined workflow, there are a few nodes that duplicate existing Maya functionality.

The node library tries to adhere to the following set of rules when it comes to choosing the node and attribute names:

- node names are prefixed with `math_`
- nodes are named with affirmative action verbs, ex: `Add`, `Multiply`
- the *get* action verb is implied, ex: `GetDotProduct` is `DotProduct`
- nodes are assumed to operate on doubles by default, ex: `Add`, `Multiply`
- mixed type operations are reflected in the name, ex: `AddVector`, `MultiplyVectorByMatrix`
- conversion nodes have following format *OutputFromSource*, ex: `RotationFromMatrix`
- attributes are generally named `input` and `output`
- if multiple inputs are required they are enumerated, ex: `input1`, `input2`
- for clarity other attribute names are allowed, ex: `translation`, `alpha`, `axis`, `min`

1.2 Node List

1.2.1 Absolute

description Computes absolute value

type variants AbsoluteAngle, AbsoluteInt

expression abs(x)

1.2.2 Acos

description Computes arccosine

expression acos(x)

1.2.3 Add

description Computes sum of two values

type variants AddAngle, AddInt, AddVector

expression x + y

1.2.4 AndBool

description Gets logical *and* of two values

type variants AndInt

expression x & b

1.2.5 AngleBetweenVectors

description Computes angle between two vectors

expression anglebetween(x, y)

1.2.6 Asin

description Computes arcsine

expression asin(x)

1.2.7 Atan

description Computes arctangent

expression atan(x)

1.2.8 Atan2

description Computes arctangent of *x / y*

expression atan(x, y)

1.2.9 Average

description Computes average value

type variants AverageAngle, AverageInt, AverageMatrix, AverageQuaternion, AverageRotation, AverageVector

expression average([x, y, . . .])

1.2.10 AxisFromMatrix

description Gets basis vector from matrix for a given axis

expression axis(x, axis)

1.2.11 Ceil

description Computes the smallest integer value greater than or equal to input

type variants CeilAngle

expression ceil(x)

1.2.12 Clamp

description Computes the value within the given min and max range

type variants ClampAngle, ClampInt

expression clamp(x, min, max)

1.2.13 Compare

description Compute how the two values compare to each other

type variants CompareAngle, CompareInt

expression compare(x, y)

1.2.14 CosAngle

description Computes the cosine of angle

expression cos(x)

1.2.15 CrossProduct

description Computes the cross product of two vectors

expression cross(x, y)

1.2.16 DebugLog

description Pass-through node that will log the value to Maya Script Editor

type variants DebugLogAngle, DebugLogInt, DebugLogMatrix, DebugLogQuaternion, DebugLogVector

1.2.17 Divide

description Computes the quotient of two values

type variants DivideAngle, DivideAngleByInt, DivideByInt

expression x / y

1.2.18 DotProduct

description Computes the dot product of two vectors

expression dot(x, y)

1.2.19 DistancePoints

description Computes the distance between two points or matrices

type variants DistanceTransforms

expression distance(x, y)

1.2.20 Floor

description Computes the largest integer value less than or equal to input

expression floor(x)

1.2.21 Inverse*

description Computes the inverse of value

type variants InverseMatrix, InverseQuaternion, InverseRotation

expression inverse(x)

1.2.22 Lerp

description Computes linear interpolation between two values

type variants LerpAngle, LerpMatrix, LerpVector

expression lerp(x, y, alpha)

1.2.23 MatrixFrom*

description Computes a rotation matrix from input

type variants MatrixFromRotation, MatrixFromQuaternion

expression mat(x, rot_order)

1.2.24 MatrixFromDirection

description Computes a rotation matrix from direction and up vector

expression direction(dir_vec, up_vec)

1.2.25 MatrixFromTRS

description Computes a matrix from translation, rotation and scale

expression trs(translation, rotation, scale)

1.2.26 Max

description Gets the largest of the two values

type variants MaxAngle, MaxInt

expression max(x, y)

1.2.27 MaxElement

description Gets the largest value in array

type variants MaxAngleElement, MaxIntElement

expression maxelement([x, y, . . .])

1.2.28 Min

description Gets the smallest of the two values

type variants MaxAngle, MaxInt

expression min(x, y)

1.2.29 MinElement

description Gets the smallest value in array

type variants MinAngleElement, MinIntElement

expression minelement([x, y, . . .])

1.2.30 ModulusInt

description Computes the remainder of the two values

expression x % y

1.2.31 Multiply

description Computes the product of two values

type variants MultiplyAngle, MultiplyAngleByInt, MultiplyByInt, MultiplyInt, MultiplyMatrix, MultiplyQuaternion, MultiplyRotation, MultiplyVector, MultiplyVectorByMatrix

expression x * y

1.2.32 Negate

description Computes the negation of value

type variants NegateAngle, NegateInt, NegateVector

expression negate(x)

1.2.33 NormalizeVector

description Computes normalized vector

expression normalize(x)

1.2.34 NormalizeArray

description Normalize array of values

expression normalizearray([x, y, . . .])

1.2.35 NormalizeWeightsArray

description Normalize array of weight values

expression normalizeweights([x, y, . . .])

1.2.36 NotBool

description Logical *not*

expression !x

1.2.37 OrBool

description Gets logical *or* of two values

type variants OrInt

expression x | y

1.2.38 Power

description Computes the value raised to power of the exponent

expression power(x, exp)

1.2.39 QuaternionFrom*

description Gets quaternion from matrix or rotation

type variants QuaternionFromMatrix, QuaternionFromRotation

expression quat(x, rot_order)

1.2.40 Remap

description Remap value from old range to new range

type variants RemapAngle, RemapInt

expression remap(x, low1, high1, low2, high2)

1.2.41 Round

description Computes rounded value

type variants RoundAngle

expression round(x)

1.2.42 RotationFrom*

description Gets rotation from matrix or quaternion

type variants RotationFromMatrix, RotationFromQuaternion

expression rot(x, rot_order)

1.2.43 ScaleFromMatrix

description Gets scale from matrix

expression scale(x)

1.2.44 Select

description Toggles output

type variants SelectAngle, SelectCurve, SelectInt, SelectMatrix, SelectMesh, SelectQuaternion, SelectRotation, SelectSurface, SelectVector

expression select(x, y, state)

1.2.45 SelectArray

description Toggles array output

type variants SelectAngleArray, SelectIntArray, SelectMatrixArray, SelectVectorArray

expression selectarray(x, y, state)

1.2.46 SinAngle

description Computes sin of angle

expression sin(x)

1.2.47 SlerpQuaternion

description Computes slerp interpolation between two quaternions

expression slerp(x, y)

1.2.48 Smoothstep

description Computes smoothstep interpolation of value within [0.0, 1.0] range

expression smoothstep(x)

1.2.49 Subtract

description Computes the difference between two values

type variants SubtractAngle, SubtractInt, SubtractVector

expression x - y

1.2.50 Sum

description Computes the the sum of values

type variants SumAngle, SumInt, SumVector

expression sum([x, y, . . .])

1.2.51 TanAngle

description Computes tangent of angle

expression tan(x)

1.2.52 TranslationFromMatrix

description Get translation from matrix

expression translation(x)

1.2.53 TwistFrom*

description Computes twist around axis from matrix or rotation

type variants TwistFromMatrix, TwistFromRotaiton

expression twist(x, axis, rot_order)

1.2.54 VectorLength

description Computes length of vector

expression length(x)

1.2.55 VectorLengthSquared

description Computes squared length of vector

expression lengthsquared(x)

1.2.56 WeightedAverage

description Computes the weighted average value

type variants WeightedAverageAngle, WeightedAverageInt, WeightedAverageMatrix, WeightedAverageQuaternion, WeightedAverageRotation, WeightedAverageVector

1.2.57 XorBool

description Gets logical *xor* of two values

type variants XorInt

expression x ^ b

CHAPTER 2

Expression Language

2.1 Overview

Even simple math expressions often require relatively large node networks, which are tedious to create by hand. While this process can be scripted, the code is likewise tedious to write and makes it difficult to see the logic at a glance.

To help alleviate these issues, Maya Math Nodes plugin provide a simple expression language that can be used to describe a series of mathematical operations inline, which can then be interpreted to generate a math node network for you. For example:

```
# project vector to plane
eval_expression('node.t - (vec(0, 1, 0) * dot(node.t, vec(0, 1, 0)))', 'projectToPlane
↪')
```

2.2 Data Types

The language supports the following data types:

numeric float and int types are supported, ex: `-1, 0, 1.0`

boolean boolean **true** and **false** values are supported and can cast to POD numeric types

string string literals are used to reference Maya attributes, ex: `node.attribute[0]`, note that there are no quotation marks around the string literals!

complex complex types such as vector, matrix, rotation, and quaternion are specified by using cast functions, ex: `vec(0, 1, 0)`

geometry a small subset of functions also supports geometry types such as mesh, nurbsCurve, and nurbsSurface

2.3 Operators

The language supports a limited set of arithmetic and logical operators: `+, -, *, /, %, &, |, ^, !`

2.4 Conditionals

The language supports the following relational operators: `==, !=, >, <, >=, <=`

These are used in combination with ternary conditional expression: `a == b ? true : false`

2.5 Functions

The language supports calling functions with arguments. These functions map directly to the node operators available in the plugin.

For example `Absolute` node is made available through the `abs()` function call. Please see the *Node Reference* for the mapping between node type and function name.

The function arguments correspond with node attributes. For example the `Clamp` node has two input attributes, therefore the `clamp(arg1, arg2)` function will take two arguments.

Likewise, array arguments are also supported with the following syntax: `minelement([1, 2, 3])`.

Output array arguments can also be index using the `[]` operator.

2.5.1 Cast Functions

Several functions that output complex data types can take constant values as input.

mat `mat(1, 0, 0, 0, 0, 1, 0, 0, 0, 0, 1, 0, 0, 0, 0, 1)` can be used to specify constant matrix value, `mat()` also maps to several math nodes and can take other arguments, ex: `mat(node.rotate, 0)`

rot `rot(0, 1, 0)` can be used to specify constant rotation value, `rot()` also maps to several math nodes and can take other arguments, ex: `rot(node.matrix, 0)`

quat `quat(0, 0, 0, 1)` can be used to specify constant quaternion value, `quat()` also maps to several math nodes and can take other arguments, ex: `quat(node.rotation, 0)`

vec `vec(1, 0, 0)` can be used to specify a constant vector value

> **Warning:**
>
> Currently, some nodes do not have expression bindings!
> See *Node Reference* section for details.

Note: Function calls require at least one argument to be specified!

2.6 Evaluation Order

Expressions are evaluated left to right with the following operator precedence, listed from lowest to highest:

Operator	Description
<, <=, >, >=, !=, ==, ?, :	Comparisons and ternary
&, |, ^, !	Logical operators
+, -	Addition and subtraction
*, /, %	Multiplication, division, remainder
func()	Function call
(...)	Grouping

2.7 Type Resolution

The operators and functions are mapped to specific Maya nodes shipped with the plugin, and because the node library is strongly typed the parser needs to make a determination about types using the following rules:

- for operators, the left operand is used to determine primary type
- for conditional expressions, the true value is used to determine primary selector type
- for functions, the first argument is used to determine primary type
- if operand or argument is literal numeric type then casting to another numeric type is allowed

2.8 Name Generator

The expression evaluator will create Maya nodes procedurally and therefore needs a mechanism to generate unique names consistently.

This is achieved with the `NameGenerator` class. To customize this behavior you can create your own implementation, with the only requirement that it implements `get_name(str: node_type) -> str` method.

2.9 Evaluator

The public API for this module consist of a single function:

```
eval_expression(str: expression, str: base_node_name='', NameGenerator:
name_generator=None) -> str
```

The return value is the path to the output attribute of the last node in the generated node network that will have the result value computed for the expression. This value can then be passed to subsequent expressions to chain them together.

2.10 Examples

```
from maya_math_nodes import eval_expression

# get twist value for roll joint
eval_expression('twist(ctrl.worldMatrix[0]) * 0.5', 'roll')

# get toe pivot value for foot roll
eval_expression('ctrl.roll > ctrl.break ? ctrl.roll - ctrl.break : 0', 'toeroll')

# compute some pole vector with offset
eval_expression('cross(axis(ctrl.matrix, 0), vec(0, 1, 0)) * 2', 'pole')
```

Maya Math Nodes is a plugin for Autodesk Maya that provides a set of atomic nodes to perform various common math operations. The purpose of these nodes is to streamline the creation of complex and highly performant rigging systems.

To see the list of nodes made available by the plugin, please refer to the *Node Reference* section.

Additionally, this plugin provides a simple expression language that can be used to describe a series of mathematical operations inline, which can then be interpreted to generate a math node network for you, see *Expression Language* section for details.

Note: At this time there are no distributable binaries available for download. However, it is fairly easy to build it directly from the source code.
