
Wrench Documentation

Release 2.0.0-beta

Dominic Scheirlinck and Contributors

Aug 15, 2017

Contents

1	Introduction	3
1.1	php-websocket	3
2	Installing Wrench	5
2.1	composer	5
3	Getting Started	7
3.1	Starting a Server	7
4	Performance	9
5	API Documentation	11
5.1	Wrench\Application	11
5.1.1	Wrench\Application\Application	11
5.1.2	Wrench\Application\EchoApplication	11
5.2	Wrench\BasicServer	12
5.3	Wrench\Client	14
5.4	Wrench\Connection	16
5.5	Wrench\ConnectionManager	19
5.6	Wrench\Exception	21
5.6.1	Wrench\Exception\BadRequestException	21
5.6.2	Wrench\Exception\CloseException	22
5.6.3	Wrench\Exception\ConnectionException	22
5.6.4	Wrench\Exception\Exception	23
5.6.5	Wrench\Exception\FrameException	24
5.6.6	Wrench\Exception\HandshakeException	24
5.6.7	Wrench\Exception\InvalidOriginException	25
5.6.8	Wrench\Exception\PayloadException	26
5.6.9	Wrench\Exception\RateLimiterException	27
5.6.10	Wrench\Exception\SocketException	27
5.7	Wrench\Frame	28
5.7.1	Wrench\Frame\Frame	28
5.7.2	Wrench\Frame\HybiFrame	30
5.8	Wrench\Listener	32
5.8.1	Wrench\Listener\HandshakeRequestListener	32
5.8.2	Wrench\Listener\Listener	33
5.8.3	Wrench\Listener\OriginPolicy	33

5.8.4	Wrench\Listener\RateLimiter	33
5.9	Wrench\Payload	35
5.9.1	Wrench\Payload\HybiPayload	35
5.9.2	Wrench\Payload\Payload	37
5.10	Wrench\Protocol	38
5.10.1	Wrench\Protocol\Hybi10Protocol	38
5.10.2	Wrench\Protocol\HybiProtocol	42
5.10.3	Wrench\Protocol\Protocol	46
5.10.4	Wrench\Protocol\Rfc6455Protocol	51
5.11	Wrench\Resource	55
5.12	Wrench\Server	55
5.13	Wrench\Socket	57
5.13.1	Wrench\Socket\ClientSocket	57
5.13.2	Wrench\Socket\ServerClientSocket	60
5.13.3	Wrench\Socket\ServerSocket	62
5.13.4	Wrench\Socket\Socket	64
5.13.5	Wrench\Socket\UriSocket	66
5.14	Wrench\Util	69
5.14.1	Wrench\Util\Configurable	69
5.14.2	Wrench\Util\Ssl	69
6	Authors	71

Wrench is a WebSockets library for PHP 7.1

Wrench is a simple websocket server and client package for PHP 7.1

php-websocket

Wrench was previously known as php-websocket. Why the name change? See [Frequently Asked Questions about the PHP License](#). Also, the namespace WebSocket is too generic; it denotes a common functionality, and may already be in use by application code. The BC break of a new [major version](#) was a good time to introduce this move to best practices.

Installing Wrench

The library is PSR-4 compatible, with a vendor name of **Wrench**.

composer

Wrench is available on Packagist as [wrench/wrench](#).

Here's what it looks like in your `composer.json`

```
{
    ...
    "require": {
        "wrench/wrench": "~3.0"
    }
}
```


Starting a Server

The first thing you'll want to do to serve WebSockets from PHP is start a WebSockets server. Wrench provides a simple Server class that implements the most recent version of the WebSockets protocol. Subclassing the Server class is encouraged: see `WebSocketBasicServer` for an example.

When you're ready for your server to start responding to requests, call `$server->run()`:

```
use Wrench\BasicServer;

$server = new BasicServer('ws://localhost:8000', array(
    'allowed_origins' => array(
        'mysite.com',
        'mysite.dev.localdomain'
    )
));

// Logging is via PSR3
$logger = new Monolog\Logger('name');
$server->setLogger($logger);

// Register your applications here
$server->registerApplication('echo', new \Wrench\Examples\EchoApplication());
$server->registerApplication('chat', new \My\ChatApplication());

$server->run();
```


CHAPTER 4

Performance

Wrench uses a single-process server, without threads, and blocks while processing data from any client. This means it has little hope of scaling in production.

You might like to use some middleware between your PHP application code and WebSocket clients in production. For example, you might use something like [RabbitMQ's STOMP + WebSockets Plugin](#). In any case, if you're hoping to serve large numbers of clients, you should probably look into one of the evented IO based servers.

Wrench\Application

Wrench\Application\Application

class **Application**

Wrench Server Application

onData (*\$payload*, *\$connection*)

Handle data received from a client

Parameters

- **\$payload** (*Payload*) – A payload object, that supports `__toString()`
- **\$connection** (*Connection*) –

Wrench\Application\EchoApplication

class **EchoApplication**

Example application for Wrench: echo server

onData (*\$data*, *\$client*)

Parameters

- **\$data** –
- **\$client** –

Wrench\BasicServer

class **BasicServer**

constant **EVENT_SOCKET_CONNECT**

Events

property **rateLimiter**

protected

property **originPolicy**

protected

property **uri**

protected string

The URI of the server

property **options**

protected array

Options

property **logger**

protected Closure

A logging callback

The default callback simply prints to stdout. You can pass your own logger in the options array. It should take a string message and string priority as parameters.

property **listeners**

protected array<string

Event listeners

Add listeners using the `addListener()` method.

property **connectionManager**

protected ConnectionManager

Connection manager

property **applications**

protected array<string

Applications

property **protocol**

protected Protocol

___**construct** (*\$uri*, *\$options = array()*)

Constructor

Parameters

- **\$uri** (*string*) –
- **\$options** (*array*) –

configure (*\$options*)

Parameters

- **\$options** –

configureRateLimiter ()

configureOriginPolicy ()
Configures the origin policy

addAllowedOrigin (*\$origin*)
Adds an allowed origin

Parameters

- **\$origin** (*array*) –

configureLogger ()
Configures the logger

Returns void

configureConnectionManager ()
Configures the connection manager

Returns void

getConnectionManager ()
Gets the connection manager

Returns WrenchConnectionManager

getUri ()

Returns string

setLogger (*\$logger*)
Sets a logger

Parameters

- **\$logger** (*Closure*) –

Returns void

run ()
Main server loop

Returns void This method does not return!

log (*\$message*, *\$priority = 'info'*)
Logs a message to the server log

The default logger simply prints the message to stdout. You can provide a logging closure. This is useful, for instance, if you've daemonized and closed STDOUT.

Parameters

- **\$message** (*string*) – Message to display.
- **\$priority** –

Returns void

notify (*\$event*, *\$arguments = array()*)
Notifies listeners of an event

Parameters

- **\$event** (*string*) –
- **\$arguments** (*array*) – Event arguments

Returns void

addListener (*\$event*, *\$callback*)

Adds a listener

Provide an event (see the `Server::EVENT_*` constants) and a callback closure. Some arguments may be provided to your callback, such as the connection that caused the event.

Parameters

- **\$event** (*string*) –
- **\$callback** (*Closure*) –

Returns void

getApplication (*\$key*)

Returns a server application.

Parameters

- **\$key** (*string*) – Name of application.

Returns Application The application object.

registerApplication (*\$key*, *\$application*)

Adds a new application object to the application storage.

Parameters

- **\$key** (*string*) – Name of application.
- **\$application** (*object*) – The application object

Returns void

configureProtocol ()

Configures the protocol option

Wrench\Client

class Client

Client class

Represents a Wrench client

constant MAX_HANDSHAKE_RESPONSE

property uri

protected

property origin

protected

property socket

protected

property headers

protected array

Request headers

property protocol

protected Protocol

Protocol instance

property options

protected array

Options

property connected

protected boolean

Whether the client is connected

__construct (*\$uri*, *\$origin*, *\$options = array()*)

Constructor

Parameters

- **\$uri** (*string*) –
- **\$origin** (*string*) – The origin to include in the handshake (required in later versions of the protocol)
- **\$options** –

configure (*\$options*)

Configure options

Parameters

- **\$options** (*array*) –

Returns void**__destruct** ()

Destructor

addRequestHeader (*\$name*, *\$value*)

Adds a request header to be included in the initial handshake

For example, to include a Cookie header

Parameters

- **\$name** (*string*) –
- **\$value** (*string*) –

Returns void**sendData** (*\$data*, *\$type = 'text'*, *\$masked = true*)

Sends data to the socket

Parameters

- **\$data** (*string*) –
- **\$type** (*string*) – Payload type
- **\$masked** (*boolean*) –

Returns int bytes written**connect** ()

Connect to the Wrench server

Returns boolean Whether a new connection was made

isConnected ()

Whether the client is currently connected

Returns boolean

disconnect ()

Wrench\Connection

class Connection

Represents a client connection on the server side

i.e. the *Server* manages a bunch of 'Connection's

property manager

protected WrenchConnectionManager

The connection manager

property socket

protected Socket

Socket object

Wraps the client connection resource

property handshaked

protected boolean

Whether the connection has successfully handshaken

property application

protected Application

The application this connection belongs to

property ip

protected string

The IP address of the client

property port

protected int

The port of the client

property headers

protected array

The array of headers included with the original request (like Cookie for example). The headers specific to the web sockets handshaking have been stripped out.

property queryParams

protected array

The array of query parameters included in the original request. The array is in the format 'key' => 'value'.

property id

protected string|null

Connection ID

property payload

protected

The current payload

property options

protected array

property protocol

protected Protocol

__construct (*ConnectionManager \$manager, ServerClientSocket \$socket, \$options = array()*)

Constructor

Parameters

- **\$manager** (*ConnectionManager*) –
- **\$socket** (*ServerClientSocket*) –
- **\$options** (*array*) –

getConnectionManager ()

Gets the connection manager of this connection

Returns WrenchConnectionManager**configure** (*\$options*)**Parameters**

- **\$options** –

configureClientInformation ()**configureClientId** ()

Configures the client ID

We hash the client ID to prevent leakage of information if another client happens to get a hold of an ID. The secret *must* be lengthy, and must be kept secret for this to work: otherwise it's trivial to search the space of possible IP addresses/ports (well, if not trivial, at least very fast).

onData (*\$data*)

Data receiver

Called by the connection manager when the connection has received data

Parameters

- **\$data** (*string*) –

handshake (*\$data*)

Performs a websocket handshake

Parameters

- **\$data** (*string*) –

export (*\$data*)

Returns a string export of the given binary data

Parameters

- **\$data** (*string*) –

Returns string

handle (*\$data*)

Handle data received from the client

The data passed in may belong to several different frames across one or more protocols. It may not even contain a single complete frame. This method manages slotting the data into separate payload objects.

Parameters

- **\$data** (*string*) –

handlePayload (*Payload \$payload*)

Handle a complete payload received from the client

Parameters

- **\$payload** (*Payload*) –

send (*\$data*, *\$type = Protocol::TYPE_TEXT*)

Sends the payload to the connection

Parameters

- **\$data** –
- **\$type** (*string*) –

Returns boolean

process ()

Processes data on the socket

close (*\$code = Protocol::CLOSE_NORMAL*)

Closes the connection according to the WebSocket protocol

Parameters

- **\$code** –

Returns boolean

log (*\$message*, *\$priority = 'info'*)

Logs a message

Parameters

- **\$message** (*string*) –
- **\$priority** (*string*) –

getIp ()

Gets the IP address of the connection

Returns string Usually dotted quad notation

getPort ()

Gets the port of the connection

Returns int

getHeaders ()

Gets the non-web-sockets headers included with the original request

Returns array

getQueryParams ()

Gets the query parameters included with the original request

Returns array

getId()
Gets the connection ID
Returns string

getSocket()
Gets the socket object
Returns SocketServerClientSocket

getClientApplication()
Gets the client application
Returns Application

configureProtocol()
Configures the protocol option

Wrench\ConnectionManager

class **ConnectionManager**

property server
protected Server

property socket
protected Socket
Master socket

property connections
protected array<int
An array of client connections

property resources
protected array<int
An array of raw socket resources, corresponding to connections, roughly

property options
protected array

property protocol
protected Protocol

__construct (*Server \$server, \$options = array()*)
Constructor

Parameters

- **\$server** (*Server*) –
- **\$options** (*array*) –

count ()

configure (*\$options*)

Parameters

- **\$options** –

getApplicationForPath (*\$path*)

Gets the application associated with the given path

Parameters

- **\$path** (*string*) –

configureMasterSocket ()

Configures the main server socket

listen ()

Listens on the main socket

Returns void

getAllResources ()

Gets all resources

Returns array<int => resource)

getConnectionForClientSocket (*\$socket*)

Returns the Connection associated with the specified socket resource

Parameters

- **\$socket** (*resource*) –

Returns Connection

selectAndProcess ()

Select and process an array of resources

processMasterSocket ()

Process events on the master socket (*\$this->socket*)

Returns void

createConnection (*\$resource*)

Creates a connection from a socket resource

The create connection object is based on the options passed into the constructor ('connection_class', 'connection_options'). This connection instance and its associated socket resource are then stored in the manager.

Parameters

- **\$resource** (*resource*) – A socket resource

Returns Connection

processClientSocket (*\$socket*)

Process events on a client socket

Parameters

- **\$socket** (*resource*) –

resourceId (*\$resource*)

This server makes an explicit assumption: PHP resource types may be cast to an integer. Furthermore, we assume this is bijective. Both seem to be true in most circumstances, but may not be guaranteed.

This method (and *\$this->getResourceId()*) exist to make this assumption explicit.

This is needed on the connection manager as well as on resources

Parameters

- **\$resource** (*resource*) –

getUri ()
Gets the connection manager’s listening URI

Returns string

log (*\$message*, *\$priority* = ‘info’)
Logs a message

Parameters

- **\$message** (*string*) –
- **\$priority** (*string*) –

getServer ()

Returns WrenchServer

removeConnection (*Connection \$connection*)
Removes a connection

Parameters

- **\$connection** (*Connection*) –

configureProtocol ()
Configures the protocol option

Wrench\Exception

Wrench\Exception\BadRequestException

class `BadRequestException`

property `message`

protected

property `code`

protected

property `file`

protected

property `line`

protected

__construct (*\$message* = null, *\$code* = null, *\$previous* = null)

Parameters

- **\$message** –
- **\$code** –
- **\$previous** (*Exception*) –

__clone ()

getMessage ()

getCode ()

```
getFile ()
getLine ()
getTrace ()
getPrevious ()
getTraceAsString ()
__toString ()
```

Wrench\Exception\CloseException

class `CloseException`

Close connection exception

property message
protected

property code
protected

property file
protected

property line
protected

__construct (*\$message = null, \$code = null, \$previous = null*)

Parameters

- **\$message** –
- **\$code** –
- **\$previous** (`Exception`) –

```
__clone ()
getMessage ()
getCode ()
getFile ()
getLine ()
getTrace ()
getPrevious ()
getTraceAsString ()
__toString ()
```

Wrench\Exception\ConnectionException

class `ConnectionException`

property message
protected

property code
 protected

property file
 protected

property line
 protected

__clone ()

__construct (*\$message*, *\$code*, *\$previous*)

Parameters

- *\$message* –
- *\$code* –
- *\$previous* –

getMessage ()

getCode ()

getFile ()

getLine ()

getTrace ()

getPrevious ()

getTraceAsString ()

__toString ()

Wrench\Exception\Exception

class **Exception**

property message
 protected

property code
 protected

property file
 protected

property line
 protected

__clone ()

__construct (*\$message*, *\$code*, *\$previous*)

Parameters

- *\$message* –
- *\$code* –
- *\$previous* –

getMessage ()

```
getCode ()  
getFile ()  
getLine ()  
getTrace ()  
getPrevious ()  
getTraceAsString ()  
__toString ()
```

Wrench\Exception\FrameException

class **FrameException**

```
property message  
    protected  
property code  
    protected  
property file  
    protected  
property line  
    protected  
__clone ()  
__construct ($message, $code, $previous)
```

Parameters

- ***\$message*** –
- ***\$code*** –
- ***\$previous*** –

```
getMessage ()  
getCode ()  
getFile ()  
getLine ()  
getTrace ()  
getPrevious ()  
getTraceAsString ()  
__toString ()
```

Wrench\Exception\HandshakeException

class **HandshakeException**

property message

protected

property code

protected

property file

protected

property line

protected

__construct (*\$message = null, \$code = null, \$previous = null*)**Parameters**

- **\$message** –
- **\$code** –
- **\$previous** (*Exception*)–

__clone ()**getMessage** ()**getCode** ()**getFile** ()**getLine** ()**getTrace** ()**getPrevious** ()**getTraceAsString** ()**__toString** ()

Wrench\Exception\InvalidOriginException

class InvalidOriginException

Invalid origin exception

property message

protected

property code

protected

property file

protected

property line

protected

__construct (*\$message = null, \$code = null, \$previous = null*)**Parameters**

- **\$message** –
- **\$code** –
- **\$previous** (*Exception*)–

```
__clone ()
getMessage ()
getCode ()
getFile ()
getLine ()
getTrace ()
getPrevious ()
getTraceAsString ()
__toString ()
```

Wrench\Exception\PayloadException

class PayloadException

```
property message
    protected
property code
    protected
property file
    protected
property line
    protected
__clone ()
__construct ($message, $code, $previous)
```

Parameters

- *\$message* –
- *\$code* –
- *\$previous* –

```
getMessage ()
getCode ()
getFile ()
getLine ()
getTrace ()
getPrevious ()
getTraceAsString ()
__toString ()
```

Wrench\Exception\RateLimiterException

class `RateLimiterException`

property message

protected

property code

protected

property file

protected

property line

protected

__construct (*\$message = null, \$code = null, \$previous = null*)

Parameters

- **\$message** –
- **\$code** –
- **\$previous** (`Exception`) –

__clone ()

getMessage ()

getCode ()

getFile ()

getLine ()

getTrace ()

getPrevious ()

getTraceAsString ()

__toString ()

Wrench\Exception\SocketException

class `SocketException`

property message

protected

property code

protected

property file

protected

property line

protected

__clone ()

__construct (*\$message, \$code, \$previous*)

Parameters

- `$message` –
- `$code` –
- `$previous` –

`getMessage()`

`getCode()`

`getFile()`

`getLine()`

`getTrace()`

`getPrevious()`

`getTraceAsString()`

`__toString()`

Wrench\Frame

Wrench\Frame\Frame

class **Frame**

Represents a WebSocket frame

property length

protected int

The frame data length

property type

protected int

The type of this payload

property buffer

protected string

The buffer

May not be a complete payload, because this frame may still be receiving data. See

property payload

protected string

The enclosed frame payload

May not be a complete payload, because this frame might indicate a continuation frame. See `isFinal()` versus `isComplete()`

getLength()

Gets the length of the payload

Returns int

encode (*\$data*, *\$type = Protocol::TYPE_TEXT*, *\$masked = false*)

Resets the frame and encodes the given data into it

Parameters

- **\$data** (*string*) –
- **\$type** (*int*) –
- **\$masked** (*boolean*) –

Returns Frame**isFinal** ()

Whether the frame is the final one in a continuation

Returns boolean**getType** ()**Returns** int**decodeFramePayloadFromBuffer** ()

Decodes a frame payload from the buffer

Returns void**getExpectedBufferLength** ()

Gets the expected length of the buffer once all the data has been received

Returns int**isComplete** ()

Whether the frame is complete

Returns boolean**receiveData** (*\$data*)

Receives data into the frame

Parameters

- **\$data** –

getRemainingData ()

Gets the remaining number of bytes before this frame will be complete

Returns number**isWaitingForData** ()

Whether this frame is waiting for more data

Returns boolean**getFramePayload** ()

Gets the contents of the frame payload

The frame must be complete to call this method.

Returns string**getFrameBuffer** ()

Gets the contents of the frame buffer

This is the encoded value, received into the frame with receiveData().

Returns string binary**getBufferLength** ()

Gets the expected length of the frame payload

Returns int

Wrench\Frame\HybiFrame

class **HybiFrame**

property masked

protected boolean

Whether the payload is masked

property mask

protected string

Masking key

property offset_payload

protected int

Byte offsets

property offset_mask

protected

property length

protected int

The frame data length

property type

protected int

The type of this payload

property buffer

protected string

The buffer

May not be a complete payload, because this frame may still be receiving data. See

property payload

protected string

The enclosed frame payload

May not be a complete payload, because this frame might indicate a continuation frame. See `isFinal()` versus `isComplete()`

encode (*\$payload*, *\$type = Protocol::TYPE_TEXT*, *\$masked = false*)

Parameters

- *\$payload* –
- *\$type* –
- *\$masked* –

mask (*\$payload*)

Masks/Unmasks the frame

Parameters

- *\$payload* (*string*) –

Returns string

unmask (*\$payload*)

Masks a payload

Parameters

- **\$payload** (*string*) –

Returns string

receiveData (*\$data*)

Parameters

- **\$data** –

getMask ()

Gets the mask

Returns string

generateMask ()

Generates a suitable masking key

Returns string

isMasked ()

Whether the frame is masked

Returns boolean

getExpectedBufferLength ()

getPayloadOffset ()

Gets the offset of the payload in the frame

Returns int

getMaskOffset ()

Gets the offset in the frame to the masking bytes

Returns int

getLength ()

getInitialLength ()

Gets the initial length value, stored in the first length byte

This determines how the rest of the length value is parsed out of the frame.

Returns int

getLengthSize ()

Returns the byte size of the length part of the frame

Not including the initial 7 bit part

Returns int

getMaskSize ()

Returns the byte size of the mask part of the frame

Returns int

decodeFramePayloadFromBuffer ()

isFinal ()

getType ()

isComplete ()

Whether the frame is complete

Returns boolean

getRemainingData ()

Gets the remaining number of bytes before this frame will be complete

Returns number

isWaitingForData ()

Whether this frame is waiting for more data

Returns boolean

getFramePayload ()

Gets the contents of the frame payload

The frame must be complete to call this method.

Returns string

getFrameBuffer ()

Gets the contents of the frame buffer

This is the encoded value, received into the frame with `receiveData()`.

Returns string binary

getBufferLength ()

Gets the expected length of the frame payload

Returns int

Wrench\Listener

Wrench\Listener\HandshakeRequestListener

class HandshakeRequestListener

onHandshakeRequest (*Connection \$connection, \$path, \$origin, \$key, \$extensions*)

Handshake request listener

Parameters

- **\$connection** (*Connection*) –
- **\$path** (*string*) –
- **\$origin** (*string*) –
- **\$key** (*string*) –
- **\$extensions** (*array*) –

Wrench\Listener\Listener

class `Listener`

`listen` (*Server* `$server`)

Parameters

- `$server` (*Server*) –

Wrench\Listener\OriginPolicy

class `OriginPolicy`

property `allowed`

protected

`__construct` (*\$allowed*)

Parameters

- `$allowed` –

`onHandshakeRequest` (*Connection* `$connection`, *\$path*, *\$origin*, *\$key*, *\$extensions*)

Handshake request listener

Closes the connection on handshake from an origin that isn't allowed

Parameters

- `$connection` (*Connection*) –
- `$path` (*string*) –
- `$origin` (*string*) –
- `$key` (*string*) –
- `$extensions` (*array*) –

`isAllowed` (*\$origin*)

Whether the specified origin is allowed under this policy

Parameters

- `$origin` (*string*) –

Returns boolean

`listen` (*Server* `$server`)

Parameters

- `$server` (*Server*) –

Wrench\Listener\RateLimiter

class `RateLimiter`

property server

protected Server

The server being limited

property ips

protected array<int>

Connection counts per IP address

property requests

protected array<array<int>>

Request tokens per IP address

property options

protected array

property protocol

protected Protocol

— **construct** (*\$options = array()*)

Constructor

Parameters

- **\$options** (*array*) –

configure (*\$options*)

Parameters

- **\$options** (*array*) –

listen (*Server \$server*)

Parameters

- **\$server** (*Server*) –

onSocketConnect (*\$socket, \$connection*)

Event listener

Parameters

- **\$socket** (*resource*) –
- **\$connection** (*Connection*) –

onSocketDisconnect (*\$socket, \$connection*)

Event listener

Parameters

- **\$socket** (*resource*) –
- **\$connection** (*Connection*) –

onClientData (*\$socket, \$connection*)

Event listener

Parameters

- **\$socket** (*resource*) –
- **\$connection** (*Connection*) –

checkConnections (*\$connection*)

Idempotent

Parameters

- **\$connection** (*Connection*) –

checkConnectionsPerIp (*\$connection*)

NOT idempotent, call once per connection

Parameters

- **\$connection** (*Connection*) –

releaseConnection (*\$connection*)

NOT idempotent, call once per disconnection

Parameters

- **\$connection** (*Connection*) –

checkRequestsPerMinute (*\$connection*)

NOT idempotent, call once per data

Parameters

- **\$connection** (*Connection*) –

limit (*\$connection*, *\$limit*)

Limits the given connection

Parameters

- **\$connection** (*Connection*) –
- **\$limit** (*string*) – Reason

log (*\$message*, *\$priority* = 'info')

Logger

Parameters

- **\$message** (*string*) –
- **\$priority** (*string*) –

configureProtocol ()

Configures the protocol option

Wrench\Payload

Wrench\Payload\HybiPayload

class HybiPayload

Gets a HyBi payload

property frames

protected array<Frame>

A payload may consist of one or more frames

getFrame ()

getCurrentFrame ()

Gets the current frame for the payload

Returns mixed

getReceivingFrame ()

Gets the frame into which data should be received

Returns Frame

isComplete ()

Whether the payload is complete

Returns boolean

encode (*\$data*, *\$type = Protocol::TYPE_TEXT*, *\$masked = false*)

Encodes a payload

Parameters

- *\$data* (*string*) –
- *\$type* (*int*) –
- *\$masked* (*boolean*) –

Returns Payload

getRemainingData ()

Gets the number of remaining bytes before this payload will be complete

May return 0 (no more bytes required) or null (unknown number of bytes required).

Returns number|NULL

isWaitingForData ()

Whether this payload is waiting for more data

Returns boolean

sendToSocket (*Socket \$socket*)

Parameters

- *\$socket* (*Socket*) –

Returns boolean

receiveData (*\$data*)

Receive raw data into the payload

Parameters

- *\$data* (*string*) –

Returns void

getPayload ()

Returns string

__toString ()

Returns string

getType ()

Gets the type of the payload

The type of a payload is taken from its first frame

Returns int

Wrench\Payload\Payload

class **Payload**

Payload class

Represents a WebSocket protocol payload, which may be made up of multiple frames.

property frames

protected array<Frame>

A payload may consist of one or more frames

getCurrentFrame ()

Gets the current frame for the payload

Returns mixed

getReceivingFrame ()

Gets the frame into which data should be received

Returns Frame

getFrame ()

Get a frame object

Returns Frame

isComplete ()

Whether the payload is complete

Returns boolean

encode (\$data, \$type = Protocol::TYPE_TEXT, \$masked = false)

Encodes a payload

Parameters

- **\$data** (*string*) –
- **\$type** (*int*) –
- **\$masked** (*boolean*) –

Returns Payload

getRemainingData ()

Gets the number of remaining bytes before this payload will be complete

May return 0 (no more bytes required) or null (unknown number of bytes required).

Returns number|NULL

isWaitingForData ()

Whether this payload is waiting for more data

Returns boolean

sendToSocket (Socket \$socket)

Parameters

- **\$socket** (*Socket*) –

Returns boolean

receiveData (*\$data*)

Receive raw data into the payload

Parameters

- **\$data** (*string*) –

Returns void

getPayload ()

Returns string

__toString ()

Returns string

getType ()

Gets the type of the payload

The type of a payload is taken from its first frame

Returns int

Wrench\Protocol

Wrench\Protocol\Hybi10Protocol

class Hybi10Protocol

<http://tools.ietf.org/html/draft-ietf-hybi-thewebsocketprotocol-10>

constant SCHEME_WEBSOCKET

Relevant schemes

constant HEADER_HOST

HTTP headers

constant HTTP_SWITCHING_PROTOCOLS

HTTP error statuses

constant CLOSE_NORMAL

Close statuses

constant TYPE_CONTINUATION

Frame types

%x0 denotes a continuation frame %x1 denotes a text frame %x2 denotes a binary frame %x3-7 are reserved for further non-control frames %x8 denotes a connection close %x9 denotes a ping %xA denotes a pong %xB-F are reserved for further control frames

constant MAGIC_GUID

Magic GUID

Used in the WebSocket accept header

constant UPGRADE_VALUE

The request MUST contain an |Upgrade| header field whose value MUST include the “websocket” keyword.

constant CONNECTION_VALUE

The request **MUST** contain a **!Connection!** header field whose value **MUST** include the “Upgrade” token.

constant REQUEST_LINE_FORMAT

Request line format

constant REQUEST_LINE_REGEX

Request line regex

Used for parsing requested path

constant RESPONSE_LINE_FORMAT

Response line format

constant HEADER_LINE_FORMAT

Header line format

property schemes

protected array<string>

Valid schemes

property closeReasons

array<int>

Close status codes

property frameTypes

array<string>

Frame types

property httpResponses

array<int>

HTTP errors

getVersion ()

acceptsVersion (\$version)

This is our most recent protocol class

Parameters

- **\$version** –

getPayload ()

generateKey ()

Generates a key suitable for use in the protocol

This base implementation returns a 16-byte (128 bit) random key as a binary string.

Returns string

getRequestHandshake (\$uri, \$key, \$origin, \$headers = array())

Gets request handshake string

The leading line from the client follows the Request-Line format. The leading line from the server follows the Status-Line format. The Request-Line and Status-Line productions are defined in [RFC2616].

An unordered set of header fields comes after the leading line in both cases. The meaning of these header fields is specified in Section 4 of this document. Additional header fields may also be present, such as cookies [RFC6265]. The format and parsing of headers is as defined in [RFC2616].

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. ws://example.org:8000/chat
- **\$key** (*string*) – 16 byte binary string key
- **\$origin** (*string*) – Origin of the request
- **\$headers** –

Returns string

getResponseHandshake (*\$key*, *\$headers = array()*)

Gets a handshake response body

Parameters

- **\$key** (*string*) –
- **\$headers** (*array*) –

getResponseError (*\$e*, *\$headers = array()*)

Gets a response to an error in the handshake

Parameters

- **\$e** (*int* | *Exception*) – Exception or HTTP error
- **\$headers** (*array*) –

getHttpResponse (*\$status*, *\$headers = array()*)

Gets an HTTP response

Parameters

- **\$status** (*int*) –
- **\$headers** (*array*) –

validateResponseHandshake (*\$response*, *\$key*)

Parameters

- **\$response** (*unknown_type*) –
- **\$key** (*unknown_type*) –

Returns boolean

getEncodedHash (*\$key*)

Gets an encoded hash for a key

Parameters

- **\$key** (*string*) –

Returns string

validateRequestHandshake (*\$request*)

Validates a request handshake

Parameters

- **\$request** (*string*) –

getCloseFrame (*\$e*)

Gets a suitable WebSocket close frame

Parameters

- **\$e** (*Exception* | *int*) –

validateUri (*\$uri*)

Validates a WebSocket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, int \$port, string \$path)**validateSocketUri** (*\$uri*)

Validates a socket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, string \$port)**validateOriginUri** (*\$origin*)

Validates an origin URI

Parameters

- **\$origin** (*string*) –

Returns string**validateRequestLine** (*\$line*)

Validates a request line

Parameters

- **\$line** (*string*) –

getAcceptValue (*\$encoded_key*)

Gets the expected accept value for a handshake response

Note that the protocol calls for the base64 encoded value to be hashed, not the original 16 byte random key.

Parameters

- **\$encoded_key** –

getHeaders (*\$response*, *\$request_line = null*)

Gets the headers from a full response

Parameters

- **\$response** (*string*) –
- **\$request_line** –

Returns array()**getRequestHeaders** (*\$response*)

Gets request headers

Parameters

- **\$response** (*string*) –

Returns array<string, array<string>> The request line, and an array of headers**validateScheme** (*\$scheme*)

Validates a scheme

Parameters

- **\$scheme** (*string*) –

Returns string Underlying scheme

getDefaultRequestHeaders (*\$host*, *\$key*, *\$origin*)

Gets the default request headers

Parameters

- **\$host** (*string*) –
- **\$key** (*string*) –
- **\$origin** (*string*) –

Returns multitype:unknown string NULL

getSuccessResponseHeaders (*\$key*)

Gets the default response headers

Parameters

- **\$key** (*string*) –

getPort (*\$scheme*)

Gets the default port for a scheme

By default, the WebSocket Protocol uses port 80 for regular WebSocket connections and port 443 for WebSocket connections tunneled over Transport Layer Security

Parameters

- **\$scheme** –

Returns int

Wrench\Protocol\HybiProtocol

class **HybiProtocol**

constant SCHEME_WEBSOCKET

Relevant schemes

constant HEADER_HOST

HTTP headers

constant HTTP_SWITCHING_PROTOCOLS

HTTP error statuses

constant CLOSE_NORMAL

Close statuses

constant TYPE_CONTINUATION

Frame types

%x0 denotes a continuation frame %x1 denotes a text frame %x2 denotes a binary frame %x3-7 are reserved for further non-control frames %x8 denotes a connection close %x9 denotes a ping %xA denotes a pong %xB-F are reserved for further control frames

constant MAGIC_GUID

Magic GUID

Used in the WebSocket accept header

constant UPGRADE_VALUE

The request **MUST** contain an **Upgrade** header field whose value **MUST** include the “websocket” keyword.

constant CONNECTION_VALUE

The request **MUST** contain a **Connection** header field whose value **MUST** include the “Upgrade” token.

constant REQUEST_LINE_FORMAT

Request line format

constant REQUEST_LINE_REGEX

Request line regex

Used for parsing requested path

constant RESPONSE_LINE_FORMAT

Response line format

constant HEADER_LINE_FORMAT

Header line format

property schemes

protected array<string>

Valid schemes

property closeReasons

array<int

Close status codes

property frameTypes

array<string

Frame types

property httpResponses

array<int

HTTP errors

getPayload()**getVersion()**

Gets a version number

acceptsVersion(\$version)

Subclasses should implement this method and return a boolean to the given version string, as to whether they would like to accept requests from user agents that specify that version.

Parameters

- **\$version** –

Returns boolean

generateKey()

Generates a key suitable for use in the protocol

This base implementation returns a 16-byte (128 bit) random key as a binary string.

Returns string

getRequestHandshake (*\$uri*, *\$key*, *\$origin*, *\$headers = array()*)

Gets request handshake string

The leading line from the client follows the Request-Line format. The leading line from the server follows the Status-Line format. The Request-Line and Status-Line productions are defined in [RFC2616].

An unordered set of header fields comes after the leading line in both cases. The meaning of these header fields is specified in Section 4 of this document. Additional header fields may also be present, such as cookies [RFC6265]. The format and parsing of headers is as defined in [RFC2616].

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. `ws://example.org:8000/chat`
- **\$key** (*string*) – 16 byte binary string key
- **\$origin** (*string*) – Origin of the request
- **\$headers** –

Returns string

getResponseHandshake (*\$key*, *\$headers = array()*)

Gets a handshake response body

Parameters

- **\$key** (*string*) –
- **\$headers** (*array*) –

getResponseError (*\$e*, *\$headers = array()*)

Gets a response to an error in the handshake

Parameters

- **\$e** (*int* | *Exception*) – Exception or HTTP error
- **\$headers** (*array*) –

getHttpResponse (*\$status*, *\$headers = array()*)

Gets an HTTP response

Parameters

- **\$status** (*int*) –
- **\$headers** (*array*) –

validateResponseHandshake (*\$response*, *\$key*)

Parameters

- **\$response** (*unknown_type*) –
- **\$key** (*unknown_type*) –

Returns boolean

getEncodedHash (*\$key*)

Gets an encoded hash for a key

Parameters

- **\$key** (*string*) –

Returns string

validateRequestHandshake (*\$request*)

Validates a request handshake

Parameters

- **\$request** (*string*) –

getCloseFrame (*\$e*)

Gets a suitable WebSocket close frame

Parameters

- **\$e** (*Exception|int*) –

validateUri (*\$uri*)

Validates a WebSocket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, int \$port, string \$path)

validateSocketUri (*\$uri*)

Validates a socket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, string \$port)

validateOriginUri (*\$origin*)

Validates an origin URI

Parameters

- **\$origin** (*string*) –

Returns string

validateRequestLine (*\$line*)

Validates a request line

Parameters

- **\$line** (*string*) –

getAcceptValue (*\$encoded_key*)

Gets the expected accept value for a handshake response

Note that the protocol calls for the base64 encoded value to be hashed, not the original 16 byte random key.

Parameters

- **\$encoded_key** –

getHeaders (*\$response, \$request_line = null*)

Gets the headers from a full response

Parameters

- **\$response** (*string*) –
- **\$request_line** –

Returns array()

getRequestHeaders (*\$response*)

Gets request headers

Parameters

- **\$response** (*string*) –

Returns array<string, array<string>> The request line, and an array of headers

validateScheme (*\$scheme*)

Validates a scheme

Parameters

- **\$scheme** (*string*) –

Returns string Underlying scheme

getDefaultRequestHeaders (*\$host, \$key, \$origin*)

Gets the default request headers

Parameters

- **\$host** (*string*) –
- **\$key** (*string*) –
- **\$origin** (*string*) –

Returns multitype:unknown string NULL

getSuccessResponseHeaders (*\$key*)

Gets the default response headers

Parameters

- **\$key** (*string*) –

getPort (*\$scheme*)

Gets the default port for a scheme

By default, the WebSocket Protocol uses port 80 for regular WebSocket connections and port 443 for WebSocket connections tunneled over Transport Layer Security

Parameters

- **\$scheme** –

Returns int

Wrench\Protocol\Protocol

class Protocol

Definitions and implementation helpers for the Wrenchs protocol

Based on RFC 6455: <http://tools.ietf.org/html/rfc6455>

constant SCHEME_WEBSOCKET

Relevant schemes

constant HEADER_HOST

HTTP headers

constant HTTP_SWITCHING_PROTOCOLS

HTTP error statuses

constant CLOSE_NORMAL

Close statuses

constant TYPE_CONTINUATION

Frame types

%x0 denotes a continuation frame %x1 denotes a text frame %x2 denotes a binary frame %x3-7 are reserved for further non-control frames %x8 denotes a connection close %x9 denotes a ping %xA denotes a pong %xB-F are reserved for further control frames

constant MAGIC_GUID

Magic GUID

Used in the WebSocket accept header

constant UPGRADE_VALUE

The request **MUST** contain an **Upgrade** header field whose value **MUST** include the “websocket” keyword.

constant CONNECTION_VALUE

The request **MUST** contain a **Connection** header field whose value **MUST** include the “Upgrade” token.

constant REQUEST_LINE_FORMAT

Request line format

constant REQUEST_LINE_REGEX

Request line regex

Used for parsing requested path

constant RESPONSE_LINE_FORMAT

Response line format

constant HEADER_LINE_FORMAT

Header line format

property schemes

protected array<string>

Valid schemes

property closeReasons

array<int>

Close status codes

property frameTypes

array<string>

Frame types

property httpResponses

array<int>

HTTP errors

getVersion ()

Gets a version number

acceptsVersion (\$version)

Subclasses should implement this method and return a boolean to the given version string, as to whether they would like to accept requests from user agents that specify that version.

Parameters

- **\$version** –

Returns boolean

getPayload()

Gets a payload instance, suitable for use in decoding/encoding protocol frames

Returns Payload

generateKey()

Generates a key suitable for use in the protocol

This base implementation returns a 16-byte (128 bit) random key as a binary string.

Returns string

getRequestHandshake(\$uri, \$key, \$origin, \$headers = array())

Gets request handshake string

The leading line from the client follows the Request-Line format. The leading line from the server follows the Status-Line format. The Request-Line and Status-Line productions are defined in [RFC2616].

An unordered set of header fields comes after the leading line in both cases. The meaning of these header fields is specified in Section 4 of this document. Additional header fields may also be present, such as cookies [RFC6265]. The format and parsing of headers is as defined in [RFC2616].

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. ws://example.org:8000/chat
- **\$key** (*string*) – 16 byte binary string key
- **\$origin** (*string*) – Origin of the request
- **\$headers** –

Returns string

getResponseHandshake(\$key, \$headers = array())

Gets a handshake response body

Parameters

- **\$key** (*string*) –
- **\$headers** (*array*) –

getResponseError(\$e, \$headers = array())

Gets a response to an error in the handshake

Parameters

- **\$e** (*int* | *Exception*) – Exception or HTTP error
- **\$headers** (*array*) –

getHttpResponse(\$status, \$headers = array())

Gets an HTTP response

Parameters

- **\$status** (*int*) –
- **\$headers** (*array*) –

validateResponseHandshake(\$response, \$key)

Parameters

- **\$response** (*unknown_type*) –
- **\$key** (*unknown_type*) –

Returns boolean**getEncodedHash** (*\$key*)

Gets an encoded hash for a key

Parameters

- **\$key** (*string*) –

Returns string**validateRequestHandshake** (*\$request*)

Validates a request handshake

Parameters

- **\$request** (*string*) –

getCloseFrame (*\$e*)

Gets a suitable WebSocket close frame

Parameters

- **\$e** (*Exception|int*) –

validateUri (*\$uri*)

Validates a WebSocket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, int \$port, string \$path)**validateSocketUri** (*\$uri*)

Validates a socket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, string \$port)**validateOriginUri** (*\$origin*)

Validates an origin URI

Parameters

- **\$origin** (*string*) –

Returns string**validateRequestLine** (*\$line*)

Validates a request line

Parameters

- **\$line** (*string*) –

getAcceptValue (*\$encoded_key*)

Gets the expected accept value for a handshake response

Note that the protocol calls for the base64 encoded value to be hashed, not the original 16 byte random key.

Parameters

- **\$encoded_key** –

getHeaders (*\$response*, *\$request_line = null*)

Gets the headers from a full response

Parameters

- **\$response** (*string*) –
- **\$request_line** –

Returns array()

getRequestHeaders (*\$response*)

Gets request headers

Parameters

- **\$response** (*string*) –

Returns array<string, array<string>> The request line, and an array of headers

validateScheme (*\$scheme*)

Validates a scheme

Parameters

- **\$scheme** (*string*) –

Returns string Underlying scheme

getDefaultRequestHeaders (*\$host*, *\$key*, *\$origin*)

Gets the default request headers

Parameters

- **\$host** (*string*) –
- **\$key** (*string*) –
- **\$origin** (*string*) –

Returns multitype:unknown string NULL

getSuccessResponseHeaders (*\$key*)

Gets the default response headers

Parameters

- **\$key** (*string*) –

getPort (*\$scheme*)

Gets the default port for a scheme

By default, the WebSocket Protocol uses port 80 for regular WebSocket connections and port 443 for WebSocket connections tunneled over Transport Layer Security

Parameters

- **\$scheme** –

Returns int

Wrench\Protocol\Rfc6455Protocol

class Rfc6455Protocol

This is the version of websockets used by Chrome versions 17 through 19.

constant SCHEME_WEBSOCKET

Relevant schemes

constant HEADER_HOST

HTTP headers

constant HTTP_SWITCHING_PROTOCOLS

HTTP error statuses

constant CLOSE_NORMAL

Close statuses

constant TYPE_CONTINUATION

Frame types

%x0 denotes a continuation frame %x1 denotes a text frame %x2 denotes a binary frame %x3-7 are reserved for further non-control frames %x8 denotes a connection close %x9 denotes a ping %xA denotes a pong %xB-F are reserved for further control frames

constant MAGIC_GUID

Magic GUID

Used in the WebSocket accept header

constant UPGRADE_VALUE

The request **MUST** contain an **Upgrade** header field whose value **MUST** include the “websocket” keyword.

constant CONNECTION_VALUE

The request **MUST** contain a **Connection** header field whose value **MUST** include the “Upgrade” token.

constant REQUEST_LINE_FORMAT

Request line format

constant REQUEST_LINE_REGEX

Request line regex

Used for parsing requested path

constant RESPONSE_LINE_FORMAT

Response line format

constant HEADER_LINE_FORMAT

Header line format

property schemes

protected array<string>

Valid schemes

property closeReasons

array<int>

Close status codes

property frameTypes

array<string

Frame types

property httpResponses

array<int

HTTP errors

getVersion ()

acceptsVersion (\$version)

This is our most recent protocol class

Parameters

- **\$version** –

getPayload ()

generateKey ()

Generates a key suitable for use in the protocol

This base implementation returns a 16-byte (128 bit) random key as a binary string.

Returns string

getRequestHandshake (\$uri, \$key, \$origin, \$headers = array())

Gets request handshake string

The leading line from the client follows the Request-Line format. The leading line from the server follows the Status-Line format. The Request-Line and Status-Line productions are defined in [RFC2616].

An unordered set of header fields comes after the leading line in both cases. The meaning of these header fields is specified in Section 4 of this document. Additional header fields may also be present, such as cookies [RFC6265]. The format and parsing of headers is as defined in [RFC2616].

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. ws://example.org:8000/chat
- **\$key** (*string*) – 16 byte binary string key
- **\$origin** (*string*) – Origin of the request
- **\$headers** –

Returns string

getResponseHandshake (\$key, \$headers = array())

Gets a handshake response body

Parameters

- **\$key** (*string*) –
- **\$headers** (*array*) –

getResponseError (\$e, \$headers = array())

Gets a response to an error in the handshake

Parameters

- **\$e** (*int | Exception*) – Exception or HTTP error
- **\$headers** (*array*) –

getHttpResponse (*\$status*, *\$headers = array()*)

Gets an HTTP response

Parameters

- **\$status** (*int*) –
- **\$headers** (*array*) –

validateResponseHandshake (*\$response*, *\$key*)

Parameters

- **\$response** (*unknown_type*) –
- **\$key** (*unknown_type*) –

Returns boolean

getEncodedHash (*\$key*)

Gets an encoded hash for a key

Parameters

- **\$key** (*string*) –

Returns string

validateRequestHandshake (*\$request*)

Validates a request handshake

Parameters

- **\$request** (*string*) –

getCloseFrame (*\$e*)

Gets a suitable WebSocket close frame

Parameters

- **\$e** (*Exception|int*) –

validateUri (*\$uri*)

Validates a WebSocket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, int \$port, string \$path)

validateSocketUri (*\$uri*)

Validates a socket URI

Parameters

- **\$uri** (*string*) –

Returns array(string \$scheme, string \$host, string \$port)

validateOriginUri (*\$origin*)

Validates an origin URI

Parameters

- **\$origin** (*string*) –

Returns string

validateRequestLine (*\$line*)

Validates a request line

Parameters

- **\$line** (*string*) –

getAcceptValue (*\$encoded_key*)

Gets the expected accept value for a handshake response

Note that the protocol calls for the base64 encoded value to be hashed, not the original 16 byte random key.

Parameters

- **\$encoded_key** –

getHeaders (*\$response*, *\$request_line = null*)

Gets the headers from a full response

Parameters

- **\$response** (*string*) –
- **\$request_line** –

Returns array()

getRequestHeaders (*\$response*)

Gets request headers

Parameters

- **\$response** (*string*) –

Returns array<string, array<string>> The request line, and an array of headers

validateScheme (*\$scheme*)

Validates a scheme

Parameters

- **\$scheme** (*string*) –

Returns string Underlying scheme

getDefaultRequestHeaders (*\$host*, *\$key*, *\$origin*)

Gets the default request headers

Parameters

- **\$host** (*string*) –
- **\$key** (*string*) –
- **\$origin** (*string*) –

Returns multitype:unknown string NULL

getSuccessResponseHeaders (*\$key*)

Gets the default response headers

Parameters

- **\$key** (*string*) –

getPort (*\$scheme*)

Gets the default port for a scheme

By default, the WebSocket Protocol uses port 80 for regular WebSocket connections and port 443 for WebSocket connections tunneled over Transport Layer Security

Parameters

- *\$scheme* –

Returns int

Wrench\Resource

class Resource

Resource interface

getResourceId ()

getResource ()

Wrench\Server

class Server

WebSocket server

The server extends socket, which provides the master socket resource. This resource is listened to, and an array of clients managed.

constant EVENT_SOCKET_CONNECT

Events

property uri

protected string

The URI of the server

property options

protected array

Options

property logger

protected Closure

A logging callback

The default callback simply prints to stdout. You can pass your own logger in the options array. It should take a string message and string priority as parameters.

property listeners

protected array<string

Event listeners

Add listeners using the addListener() method.

property connectionManager

protected ConnectionManager

Connection manager

property applications

protected array<string>

Applications

property protocol

protected Protocol

__construct (*\$uri*, *\$options* = *array()*)

Constructor

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. ws://localhost:8000/, path will be ignored
- **\$options** (*array*) – (optional) See configure

configure (*\$options*)

Configure options

Options include - *socket_class* => The socket class to use, defaults to ServerSocket - *socket_options* => An array of socket options - *logger* => Closure(*\$message*, *\$priority* = 'info'), used for logging

Parameters

- **\$options** (*array*) –

Returns void

configureLogger ()

Configures the logger

Returns void

configureConnectionManager ()

Configures the connection manager

Returns void

getConnectionManager ()

Gets the connection manager

Returns WrenchConnectionManager

getUri ()

Returns string

setLogger (*\$logger*)

Sets a logger

Parameters

- **\$logger** (*Closure*) –

Returns void

run ()

Main server loop

Returns void This method does not return!

log (*\$message*, *\$priority* = 'info')

Logs a message to the server log

The default logger simply prints the message to stdout. You can provide a logging closure. This is useful, for instance, if you've daemonized and closed STDOUT.

Parameters

- **\$message** (*string*) – Message to display.
- **\$priority** –

Returns void

notify (*\$event*, *\$arguments = array()*)
Notifies listeners of an event

Parameters

- **\$event** (*string*) –
- **\$arguments** (*array*) – Event arguments

Returns void

addListener (*\$event*, *\$callback*)
Adds a listener

Provide an event (see the `Server::EVENT_*` constants) and a callback closure. Some arguments may be provided to your callback, such as the connection the caused the event.

Parameters

- **\$event** (*string*) –
- **\$callback** (*Closure*) –

Returns void

getApplication (*\$key*)
Returns a server application.

Parameters

- **\$key** (*string*) – Name of application.

Returns Application The application object.

registerApplication (*\$key*, *\$application*)
Adds a new application object to the application storage.

Parameters

- **\$key** (*string*) – Name of application.
- **\$application** (*object*) – The application object

Returns void

configureProtocol ()
Configures the protocol option

Wrench\Socket

Wrench\Socket\ClientSocket

class `ClientSocket`

Options:

- `timeout_connect => int, seconds, default 2`

constant `TIMEOUT_CONNECT`

Default connection timeout

constant `TIMEOUT_SOCKET`

Default timeout for socket operations (reads, writes)

constant `DEFAULT_RECEIVE_LENGTH`

constant `NAME_PART_IP`

Socket name parts

property `scheme`

protected

property `host`

protected

property `port`

protected

property `socket`

protected resource

property `context`

protected

Stream context

property `connected`

protected boolean

Whether the socket is connected to a server

Note, the connection may not be ready to use, but the socket is connected at least. See `$handshaked`, and other properties in subclasses.

property `firstRead`

protected boolean

Whether the current read is the first one to the socket

property `name`

protected string

The socket name according to `stream_socket_get_name`

property `options`

protected array

property `protocol`

protected Protocol

configure (*\$options*)

Parameters

- *\$options* –

connect ()

Connects to the given socket

reconnect ()

getSocketStreamContextOptions ()

getSslStreamContextOptions ()

__construct (*\$uri*, *\$options = array()*)
URI Socket constructor

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. `ws://example.org:8000/chat`
- **\$options** –

getUri ()
Gets the canonical/normalized URI for this socket

Returns string

getName ()

getHost ()
Gets the host name

getPort ()

getStreamContext (*\$listen = false*)
Gets a stream context

Parameters

- **\$listen** –

getNamePart (*\$name*, *\$part*)
Gets part of the name of the socket

PHP seems to return IPV6 address/port combos like this: `:::1:1234`, where `:::1` is the address and `1234` the port. So, the `part` number here is either the last `:` delimited section (the port) or all the other sections (the whole initial part, the address).

Parameters

- **\$name** (*string*) – (from `$this->getName()` usually)
- **\$part** –

Returns string

getIp ()
Gets the IP address of the socket

Returns string

getLastError ()
Get the last error that occurred on the socket

Returns intlstring

isConnected ()
Whether the socket is currently connected

Returns boolean

disconnect ()
Disconnect the socket

Returns void

getResource ()

getResourceId ()

send (*\$data*)

Parameters

- **\$data** (*unknown_type*) –

Returns boolean|int The number of bytes sent or false on error

receive (*\$length = self::DEFAULT_RECEIVE_LENGTH*)

Recieve data from the socket

Parameters

- **\$length** (*int*) –

Returns string

configureProtocol ()

Configures the protocol option

Wrench\Socket\ServerClientSocket

class **ServerClientSocket**

constant TIMEOUT_SOCKET

Default timeout for socket operations (reads, writes)

constant DEFAULT_RECEIVE_LENGTH

constant NAME_PART_IP

Socket name parts

property socket

protected resource

property context

protected

Stream context

property connected

protected boolean

Whether the socket is connected to a server

Note, the connection may not be ready to use, but the socket is connected at least. See \$handshaked, and other properties in subclasses.

property firstRead

protected boolean

Whether the current read is the first one to the socket

property name

protected string

The socket name according to stream_socket_get_name

property options

protected array

property protocol

protected Protocol

__construct (*\$accepted_socket*, *\$options = array()*)

Constructor

A server client socket is accepted from a listening socket, so there's no need to call `->connect()` or whatnot.

Parameters

- **\$accepted_socket** (*resource*) –
- **\$options** (*array*) –

configure (*\$options*)

Configure options

Options include - `timeout_connect => int, seconds, default 2` - `timeout_socket => int, seconds, default 5`

Parameters

- **\$options** (*array*) –

Returns void

getName ()

Gets the name of the socket

getNamePart (*\$name*, *\$part*)

Gets part of the name of the socket

PHP seems to return IPV6 address/port combos like this: `::1:1234`, where `::1` is the address and `1234` the port. So, the part number here is either the last `:` delimited section (the port) or all the other sections (the whole initial part, the address).

Parameters

- **\$name** (*string*) – (from `$this->getName()` usually)
- **\$part** –

Returns string

getIp ()

Gets the IP address of the socket

Returns string

getPort ()

Gets the port of the socket

Returns int

getLastError ()

Get the last error that occurred on the socket

Returns intlstring

isConnected ()

Whether the socket is currently connected

Returns boolean

disconnect ()

Disconnect the socket

Returns void

getResource ()

getResourceId ()

send (*\$data*)

Parameters

- **\$data** (*unknown_type*) –

Returns boolean|int The number of bytes sent or false on error

receive (*\$length = self::DEFAULT_RECEIVE_LENGTH*)

Receive data from the socket

Parameters

- **\$length** (*int*) –

Returns string

configureProtocol ()

Configures the protocol option

Wrench\Socket\ServerSocket

class ServerSocket

Server socket

Used for a server's "master" socket that binds to the configured interface and listens

constant TIMEOUT_SOCKET

Default timeout for socket operations (reads, writes)

constant DEFAULT_RECEIVE_LENGTH

constant NAME_PART_IP

Socket name parts

property listening

protected boolean

Whether the socket is listening

property scheme

protected

property host

protected

property port

protected

property socket

protected resource

property context

protected

Stream context

property connected

protected boolean

Whether the socket is connected to a server

Note, the connection may not be ready to use, but the socket is connected at least. See \$handshaked, and other properties in subclasses.

property firstRead

protected boolean

Whether the current read is the first one to the socket

property name

protected string

The socket name according to `stream_socket_get_name`**property options**

protected array

property protocol

protected Protocol

configure (*\$options*)**Parameters**

- **\$options** –

listen ()

Listens

accept ()

Accepts a new connection on the socket

Returns resource**getSocketStreamContextOptions** ()**getSslStreamContextOptions** ()**__construct** (*\$uri*, *\$options = array()*)

URI Socket constructor

Parameters

- **\$uri** (*string*) – WebSocket URI, e.g. `ws://example.org:8000/chat`
- **\$options** –

getUri ()

Gets the canonical/normalized URI for this socket

Returns string**getName** ()**getHost** ()

Gets the host name

getPort ()**getStreamContext** (*\$listen = false*)

Gets a stream context

Parameters

- **\$listen** –

getNamePart (*\$name*, *\$part*)

Gets part of the name of the socket

PHP seems to return IPV6 address/port combos like this: `::1:1234`, where `::1` is the address and `1234` the port. So, the part number here is either the last `:` delimited section (the port) or all the other sections (the whole initial part, the address).

Parameters

- **\$name** (*string*) – (from `$this->getName()` usually)
- **\$part** –

Returns string

getIp ()

Gets the IP address of the socket

Returns string

getLastError ()

Get the last error that occurred on the socket

Returns int|string

isConnected ()

Whether the socket is currently connected

Returns boolean

disconnect ()

Disconnect the socket

Returns void

getResource ()

getResourceId ()

send (\$data)

Parameters

- **\$data** (*unknown_type*) –

Returns boolean|int The number of bytes sent or false on error

receive (\$length = self::DEFAULT_RECEIVE_LENGTH)

Receive data from the socket

Parameters

- **\$length** (*int*) –

Returns string

configureProtocol ()

Configures the protocol option

Wrench\Socket\Socket

class **Socket**

Socket class

Implements low level logic for connecting, serving, reading to, and writing from WebSocket connections using PHP's streams.

Unlike in previous versions of this library, a `Socket` instance now represents a single underlying socket resource. It's designed to be used by aggregation, rather than inheritance.

constant TIMEOUT_SOCKET

Default timeout for socket operations (reads, writes)

constant DEFAULT_RECEIVE_LENGTH**constant NAME_PART_IP**

Socket name parts

property socket

protected resource

property context

protected

Stream context

property connected

protected boolean

Whether the socket is connected to a server

Note, the connection may not be ready to use, but the socket is connected at least. See `$handshaked`, and other properties in subclasses.

property firstRead

protected boolean

Whether the current read is the first one to the socket

property name

protected string

The socket name according to `stream_socket_get_name`

property options

protected array

property protocol

protected Protocol

configure (*\$options*)

Configure options

Options include - `timeout_connect => int, seconds, default 2` - `timeout_socket => int, seconds, default 5`

Parameters

- **\$options** (*array*) –

Returns void

getName ()

Gets the name of the socket

getNamePart (*\$name*, *\$part*)

Gets part of the name of the socket

PHP seems to return IPV6 address/port combos like this: `:::1:1234`, where `:::1` is the address and `1234` the port. So, the part number here is either the last `:` delimited section (the port) or all the other sections (the whole initial part, the address).

Parameters

- **\$name** (*string*) – (from `$this->getName()` usually)
- **\$part** –

Returns string

getIp ()

Gets the IP address of the socket

Returns string

getPort ()

Gets the port of the socket

Returns int

getLastError ()

Get the last error that occurred on the socket

Returns int|string

isConnected ()

Whether the socket is currently connected

Returns boolean

disconnect ()

Disconnect the socket

Returns void

getResource ()

getResourceId ()

send (*\$data*)

Parameters

- **\$data** (*unknown_type*) –

Returns boolean|int The number of bytes sent or false on error

receive (*\$length = self::DEFAULT_RECEIVE_LENGTH*)

Receive data from the socket

Parameters

- **\$length** (*int*) –

Returns string

__construct (*\$options = array()*)

Configurable constructor

Parameters

- **\$options** –

configureProtocol ()

Configures the protocol option

Wrench\Socket\UriSocket

class UriSocket

constant **TIMEOUT_SOCKET**

Default timeout for socket operations (reads, writes)

constant `DEFAULT_RECEIVE_LENGTH`

constant `NAME_PART_IP`

Socket name parts

property `scheme`

protected

property `host`

protected

property `port`

protected

property `socket`

protected resource

property `context`

protected

Stream context

property `connected`

protected boolean

Whether the socket is connected to a server

Note, the connection may not be ready to use, but the socket is connected at least. See `$handshaked`, and other properties in subclasses.

property `firstRead`

protected boolean

Whether the current read is the first one to the socket

property `name`

protected string

The socket name according to `stream_socket_get_name`

property `options`

protected array

property `protocol`

protected Protocol

__construct (*\$uri*, *\$options* = *array()*)

URI Socket constructor

Parameters

- *\$uri* (*string*) – WebSocket URI, e.g. `ws://example.org:8000/chat`
- *\$options* –

getUri ()

Gets the canonical/normalized URI for this socket

Returns string

getName ()

getHost ()

Gets the host name

getPort ()

getStreamContext (*\$listen = false*)

Gets a stream context

Parameters

- **\$listen** –

getSocketStreamContextOptions ()

Returns an array of socket stream context options

See <http://php.net/manual/en/context.socket.php>

Returns array

getSslStreamContextOptions ()

Returns an array of ssl stream context options

See <http://php.net/manual/en/context.ssl.php>

Returns array

configure (*\$options*)

Configure options

Options include - `timeout_connect => int, seconds, default 2` - `timeout_socket => int, seconds, default 5`

Parameters

- **\$options** (*array*) –

Returns void

getNamePart (*\$name, \$part*)

Gets part of the name of the socket

PHP seems to return IPV6 address/port combos like this: `:::1:1234`, where `:::1` is the address and `1234` the port. So, the `part` number here is either the last `:` delimited section (the port) or all the other sections (the whole initial part, the address).

Parameters

- **\$name** (*string*) – (from `$this->getName()` usually)
- **\$part** –

Returns string

getIp ()

Gets the IP address of the socket

Returns string

getLastError ()

Get the last error that occurred on the socket

Returns intlstring

isConnected ()

Whether the socket is currently connected

Returns boolean

disconnect ()

Disconnect the socket

Returns void

getResource ()

getResourceId()

send(\$data)

Parameters

- **\$data** (*unknown_type*) –

Returns boolean|int The number of bytes sent or false on error

receive(\$length = self::DEFAULT_RECEIVE_LENGTH)

Recieve data from the socket

Parameters

- **\$length** (*int*) –

Returns string

configureProtocol()

Configures the protocol option

Wrench\Util

Wrench\Util\Configurable

class Configurable

Configurable base class

property options

protected array

property protocol

protected Protocol

__construct(\$options = array())

Configurable constructor

Parameters

- **\$options** –

configure(\$options)

Configures the options

Parameters

- **\$options** (*array*) –

configureProtocol()

Configures the protocol option

Wrench\Util\Ssl

class Ssl

generatePemFile(\$pem_file, \$pem_passphrase, \$country_name, \$state_or_province_name, \$locality_name, \$organization_name, \$organizational_unit_name, \$common_name, \$email_address)

Generates a new PEM File given the informations

Parameters

- **\$pem_file** (*string*) – the path of the PEM file to create
- **\$pem_passphrase** (*string*) – the passphrase to protect the PEM file or if you don't want to use a passphrase
- **\$country_name** (*string*) – the country code of the new PEM file. e.g.: EN
- **\$state_or_province_name** (*string*) – the state or province name of the new PEM file
- **\$locality_name** (*string*) – the name of the locality
- **\$organization_name** –
- **\$organizational_unit_name** –
- **\$common_name** –
- **\$email_address** (*string*) – the email address

CHAPTER 6

Authors

The original maintainer and author was [@nicokaiser](#). Plentiful improvements were contributed by [@lemmingzshadow](#) and [@mzhack](#). Parts of the Socket class were written by Moritz Wutz. The server is licensed under the WTFPL, a free software compatible license.

Symbols

__clone() (BadRequestException method), **21**
 __clone() (CloseException method), **22**
 __clone() (ConnectionException method), **23**
 __clone() (Exception method), **23**
 __clone() (FrameException method), **24**
 __clone() (HandshakeException method), **25**
 __clone() (InvalidOriginException method), **25**
 __clone() (PayloadException method), **26**
 __clone() (RateLimiterException method), **27**
 __clone() (SocketException method), **27**
 __construct() (BadRequestException method), **21**
 __construct() (BasicServer method), **12**
 __construct() (Client method), **15**
 __construct() (ClientSocket method), **58**
 __construct() (CloseException method), **22**
 __construct() (Configurable method), **69**
 __construct() (Connection method), **17**
 __construct() (ConnectionException method), **23**
 __construct() (ConnectionManager method), **19**
 __construct() (Exception method), **23**
 __construct() (FrameException method), **24**
 __construct() (HandshakeException method), **25**
 __construct() (InvalidOriginException method), **25**
 __construct() (OriginPolicy method), **33**
 __construct() (PayloadException method), **26**
 __construct() (RateLimiter method), **34**
 __construct() (RateLimiterException method), **27**
 __construct() (Server method), **56**
 __construct() (ServerClientSocket method), **60**
 __construct() (ServerSocket method), **63**
 __construct() (Socket method), **66**
 __construct() (SocketException method), **27**
 __construct() (UriSocket method), **67**
 __destruct() (Client method), **15**
 __toString() (BadRequestException method), **22**
 __toString() (CloseException method), **22**
 __toString() (ConnectionException method), **23**
 __toString() (Exception method), **24**

__toString() (FrameException method), **24**
 __toString() (HandshakeException method), **25**
 __toString() (HybiPayload method), **36**
 __toString() (InvalidOriginException method), **26**
 __toString() (Payload method), **38**
 __toString() (PayloadException method), **26**
 __toString() (RateLimiterException method), **27**
 __toString() (SocketException method), **28**

A

accept() (ServerSocket method), **63**
 acceptsVersion() (Hybi10Protocol method), **39**
 acceptsVersion() (HybiProtocol method), **43**
 acceptsVersion() (Protocol method), **47**
 acceptsVersion() (Rfc6455Protocol method), **52**
 addAllowedOrigin() (BasicServer method), **13**
 addListener() (BasicServer method), **14**
 addListener() (Server method), **57**
 addRequestHeader() (Client method), **15**
 allowed (OriginPolicy property), **33**
 Application (class), **11**
 application (Connection property), **16**
 applications (BasicServer property), **12**
 applications (Server property), **56**

B

BadRequestException (class), **21**
 BasicServer (class), **12**
 BasicServer::EVENT_SOCKET_CONNECT (class constant), **12**
 buffer (Frame property), **28**
 buffer (HybiFrame property), **30**

C

checkConnections() (RateLimiter method), **34**
 checkConnectionsPerIp() (RateLimiter method), **35**
 checkRequestsPerMinute() (RateLimiter method), **35**
 Client (class), **14**
 Client::MAX_HANDSHAKE_RESPONSE (class constant), **14**

ClientSocket (class), [57](#)
ClientSocket::DEFAULT_RECEIVE_LENGTH (class constant), [58](#)
ClientSocket::NAME_PART_IP (class constant), [58](#)
ClientSocket::TIMEOUT_CONNECT (class constant), [57](#)
ClientSocket::TIMEOUT_SOCKET (class constant), [58](#)
close() (Connection method), [18](#)
CloseException (class), [22](#)
closeReasons (Hybi10Protocol property), [39](#)
closeReasons (HybiProtocol property), [43](#)
closeReasons (Protocol property), [47](#)
closeReasons (Rfc6455Protocol property), [51](#)
code (BadRequestException property), [21](#)
code (CloseException property), [22](#)
code (ConnectionException property), [22](#)
code (Exception property), [23](#)
code (FrameException property), [24](#)
code (HandshakeException property), [25](#)
code (InvalidOriginException property), [25](#)
code (PayloadException property), [26](#)
code (RateLimiterException property), [27](#)
code (SocketException property), [27](#)
Configurable (class), [69](#)
configure() (BasicServer method), [12](#)
configure() (Client method), [15](#)
configure() (ClientSocket method), [58](#)
configure() (Configurable method), [69](#)
configure() (Connection method), [17](#)
configure() (ConnectionManager method), [19](#)
configure() (RateLimiter method), [34](#)
configure() (Server method), [56](#)
configure() (ServerClientSocket method), [61](#)
configure() (ServerSocket method), [63](#)
configure() (Socket method), [65](#)
configure() (UriSocket method), [68](#)
configureClientId() (Connection method), [17](#)
configureClientInformation() (Connection method), [17](#)
configureConnectionManager() (BasicServer method), [13](#)
configureConnectionManager() (Server method), [56](#)
configureLogger() (BasicServer method), [13](#)
configureLogger() (Server method), [56](#)
configureMasterSocket() (ConnectionManager method), [20](#)
configureOriginPolicy() (BasicServer method), [13](#)
configureProtocol() (BasicServer method), [14](#)
configureProtocol() (ClientSocket method), [60](#)
configureProtocol() (Configurable method), [69](#)
configureProtocol() (Connection method), [19](#)
configureProtocol() (ConnectionManager method), [21](#)
configureProtocol() (RateLimiter method), [35](#)
configureProtocol() (Server method), [57](#)
configureProtocol() (ServerClientSocket method), [62](#)
configureProtocol() (ServerSocket method), [64](#)
configureProtocol() (Socket method), [66](#)
configureProtocol() (UriSocket method), [67](#)
Connection (class), [16](#)
ConnectionException (class), [22](#)
connectionManager (BasicServer property), [12](#)
ConnectionManager (class), [19](#)
connectionManager (Server property), [55](#)
connections (ConnectionManager property), [19](#)
context (ClientSocket property), [58](#)
context (ServerClientSocket property), [60](#)
context (ServerSocket property), [62](#)
context (Socket property), [65](#)
context (UriSocket property), [67](#)
count() (ConnectionManager method), [19](#)
createConnection() (ConnectionManager method), [20](#)

D

decodeFramePayloadFromBuffer() (Frame method), [29](#)
decodeFramePayloadFromBuffer() (HybiFrame method), [31](#)
disconnect() (Client method), [16](#)
disconnect() (ClientSocket method), [59](#)
disconnect() (ServerClientSocket method), [61](#)
disconnect() (ServerSocket method), [64](#)
disconnect() (Socket method), [66](#)
disconnect() (UriSocket method), [68](#)

E

EchoApplication (class), [11](#)
encode() (Frame method), [28](#)
encode() (HybiFrame method), [30](#)
encode() (HybiPayload method), [36](#)
encode() (Payload method), [37](#)
Exception (class), [23](#)
export() (Connection method), [17](#)

F

file (BadRequestException property), [21](#)
file (CloseException property), [22](#)
file (ConnectionException property), [23](#)
file (Exception property), [23](#)
file (FrameException property), [24](#)
file (HandshakeException property), [25](#)
file (InvalidOriginException property), [25](#)
file (PayloadException property), [26](#)

file (RateLimiterException property), [27](#)
 file (SocketException property), [27](#)
 firstRead (ClientSocket property), [58](#)
 firstRead (ServerClientSocket property), [60](#)
 firstRead (ServerSocket property), [62](#)
 firstRead (Socket property), [65](#)
 firstRead (UriSocket property), [67](#)
 Frame (class), [28](#)
 FrameException (class), [24](#)
 frames (HybiPayload property), [35](#)
 frames (Payload property), [37](#)
 frameTypes (Hybi10Protocol property), [39](#)
 frameTypes (HybiProtocol property), [43](#)
 frameTypes (Protocol property), [47](#)
 frameTypes (Rfc6455Protocol property), [51](#)

G

generateKey() (Hybi10Protocol method), [39](#)
 generateKey() (HybiProtocol method), [43](#)
 generateKey() (Protocol method), [48](#)
 generateKey() (Rfc6455Protocol method), [52](#)
 generateMask() (HybiFrame method), [31](#)
 generatePemFile() (Ssl method), [69](#)
 getAcceptValue() (Hybi10Protocol method), [41](#)
 getAcceptValue() (HybiProtocol method), [45](#)
 getAcceptValue() (Protocol method), [49](#)
 getAcceptValue() (Rfc6455Protocol method), [54](#)
 getAllResources() (ConnectionManager method), [20](#)
 getApplication() (BasicServer method), [14](#)
 getApplication() (Server method), [57](#)
 getApplicationForPath() (ConnectionManager method),
[19](#)
 getBufferLength() (Frame method), [29](#)
 getBufferLength() (HybiFrame method), [32](#)
 getClientApplication() (Connection method), [19](#)
 getCloseFrame() (Hybi10Protocol method), [40](#)
 getCloseFrame() (HybiProtocol method), [45](#)
 getCloseFrame() (Protocol method), [49](#)
 getCloseFrame() (Rfc6455Protocol method), [53](#)
 getCode() (BadRequestException method), [21](#)
 getCode() (CloseException method), [22](#)
 getCode() (ConnectionException method), [23](#)
 getCode() (Exception method), [24](#)
 getCode() (FrameException method), [24](#)
 getCode() (HandshakeException method), [25](#)
 getCode() (InvalidOriginException method), [26](#)
 getCode() (PayloadException method), [26](#)
 getCode() (RateLimiterException method), [27](#)
 getCode() (SocketException method), [28](#)
 getConnectionForClientSocket() (ConnectionManager
 method), [20](#)
 getConnectionManager() (BasicServer method), [13](#)
 getConnectionManager() (Connection method), [17](#)
 getConnectionManager() (Server method), [56](#)

getCurrentFrame() (HybiPayload method), [35](#)
 getCurrentFrame() (Payload method), [37](#)
 getDefaultRequestHeaders() (Hybi10Protocol method),
[42](#)
 getDefaultRequestHeaders() (HybiProtocol method), [46](#)
 getDefaultRequestHeaders() (Protocol method), [50](#)
 getDefaultRequestHeaders() (Rfc6455Protocol method),
[54](#)
 getEncodedHash() (Hybi10Protocol method), [40](#)
 getEncodedHash() (HybiProtocol method), [44](#)
 getEncodedHash() (Protocol method), [49](#)
 getEncodedHash() (Rfc6455Protocol method), [53](#)
 getExpectedBufferLength() (Frame method), [29](#)
 getExpectedBufferLength() (HybiFrame method), [31](#)
 getFile() (BadRequestException method), [21](#)
 getFile() (CloseException method), [22](#)
 getFile() (ConnectionException method), [23](#)
 getFile() (Exception method), [24](#)
 getFile() (FrameException method), [24](#)
 getFile() (HandshakeException method), [25](#)
 getFile() (InvalidOriginException method), [26](#)
 getFile() (PayloadException method), [26](#)
 getFile() (RateLimiterException method), [27](#)
 getFile() (SocketException method), [28](#)
 getFrame() (HybiPayload method), [35](#)
 getFrame() (Payload method), [37](#)
 getFrameBuffer() (Frame method), [29](#)
 getFrameBuffer() (HybiFrame method), [32](#)
 getFramePayload() (Frame method), [29](#)
 getFramePayload() (HybiFrame method), [32](#)
 getHeaders() (Connection method), [18](#)
 getHeaders() (Hybi10Protocol method), [41](#)
 getHeaders() (HybiProtocol method), [45](#)
 getHeaders() (Protocol method), [50](#)
 getHeaders() (Rfc6455Protocol method), [54](#)
 getHost() (ClientSocket method), [59](#)
 getHost() (ServerSocket method), [63](#)
 getHost() (UriSocket method), [67](#)
 getHttpResponse() (Hybi10Protocol method), [40](#)
 getHttpResponse() (HybiProtocol method), [44](#)
 getHttpResponse() (Protocol method), [48](#)
 getHttpResponse() (Rfc6455Protocol method), [52](#)
 getId() (Connection method), [18](#)
 getInitialLength() (HybiFrame method), [31](#)
 getIp() (ClientSocket method), [59](#)
 getIp() (Connection method), [18](#)
 getIp() (ServerClientSocket method), [61](#)
 getIp() (ServerSocket method), [64](#)
 getIp() (Socket method), [66](#)
 getIp() (UriSocket method), [68](#)
 getLastError() (ClientSocket method), [59](#)
 getLastError() (ServerClientSocket method), [61](#)
 getLastError() (ServerSocket method), [64](#)
 getLastError() (Socket method), [66](#)

`getLastError()` (UriSocket method), [68](#)
`getLength()` (Frame method), [28](#)
`getLength()` (HybiFrame method), [31](#)
`getLengthSize()` (HybiFrame method), [31](#)
`getLine()` (BadRequestException method), [22](#)
`getLine()` (CloseException method), [22](#)
`getLine()` (ConnectionException method), [23](#)
`getLine()` (Exception method), [24](#)
`getLine()` (FrameException method), [24](#)
`getLine()` (HandshakeException method), [25](#)
`getLine()` (InvalidOriginException method), [26](#)
`getLine()` (PayloadException method), [26](#)
`getLine()` (RateLimiterException method), [27](#)
`getLine()` (SocketException method), [28](#)
`getMask()` (HybiFrame method), [31](#)
`getMaskOffset()` (HybiFrame method), [31](#)
`getMaskSize()` (HybiFrame method), [31](#)
`getMessage()` (BadRequestException method), [21](#)
`getMessage()` (CloseException method), [22](#)
`getMessage()` (ConnectionException method), [23](#)
`getMessage()` (Exception method), [23](#)
`getMessage()` (FrameException method), [24](#)
`getMessage()` (HandshakeException method), [25](#)
`getMessage()` (InvalidOriginException method), [26](#)
`getMessage()` (PayloadException method), [26](#)
`getMessage()` (RateLimiterException method), [27](#)
`getMessage()` (SocketException method), [28](#)
`getName()` (ClientSocket method), [59](#)
`getName()` (ServerClientSocket method), [61](#)
`getName()` (ServerSocket method), [63](#)
`getName()` (Socket method), [65](#)
`getName()` (UriSocket method), [67](#)
`getNamePart()` (ClientSocket method), [59](#)
`getNamePart()` (ServerClientSocket method), [61](#)
`getNamePart()` (ServerSocket method), [63](#)
`getNamePart()` (Socket method), [65](#)
`getNamePart()` (UriSocket method), [68](#)
`getPayload()` (Hybi10Protocol method), [39](#)
`getPayload()` (HybiPayload method), [36](#)
`getPayload()` (HybiProtocol method), [43](#)
`getPayload()` (Payload method), [38](#)
`getPayload()` (Protocol method), [48](#)
`getPayload()` (Rfc6455Protocol method), [52](#)
`getPayloadOffset()` (HybiFrame method), [31](#)
`getPort()` (ClientSocket method), [59](#)
`getPort()` (Connection method), [18](#)
`getPort()` (Hybi10Protocol method), [42](#)
`getPort()` (HybiProtocol method), [46](#)
`getPort()` (Protocol method), [50](#)
`getPort()` (Rfc6455Protocol method), [54](#)
`getPort()` (ServerClientSocket method), [61](#)
`getPort()` (ServerSocket method), [63](#)
`getPort()` (Socket method), [66](#)
`getPort()` (UriSocket method), [67](#)
`getPrevious()` (BadRequestException method), [22](#)
`getPrevious()` (CloseException method), [22](#)
`getPrevious()` (ConnectionException method), [23](#)
`getPrevious()` (Exception method), [24](#)
`getPrevious()` (FrameException method), [24](#)
`getPrevious()` (HandshakeException method), [25](#)
`getPrevious()` (InvalidOriginException method), [26](#)
`getPrevious()` (PayloadException method), [26](#)
`getPrevious()` (RateLimiterException method), [27](#)
`getPrevious()` (SocketException method), [28](#)
`getQueryParams()` (Connection method), [18](#)
`getReceivingFrame()` (HybiPayload method), [36](#)
`getReceivingFrame()` (Payload method), [37](#)
`getRemainingData()` (Frame method), [29](#)
`getRemainingData()` (HybiFrame method), [32](#)
`getRemainingData()` (HybiPayload method), [36](#)
`getRemainingData()` (Payload method), [37](#)
`getRequestHandshake()` (Hybi10Protocol method), [39](#)
`getRequestHandshake()` (HybiProtocol method), [43](#)
`getRequestHandshake()` (Protocol method), [48](#)
`getRequestHandshake()` (Rfc6455Protocol method), [52](#)
`getRequestHeaders()` (Hybi10Protocol method), [41](#)
`getRequestHeaders()` (HybiProtocol method), [45](#)
`getRequestHeaders()` (Protocol method), [50](#)
`getRequestHeaders()` (Rfc6455Protocol method), [54](#)
`getResource()` (ClientSocket method), [59](#)
`getResource()` (Resource method), [55](#)
`getResource()` (ServerClientSocket method), [61](#)
`getResource()` (ServerSocket method), [64](#)
`getResource()` (Socket method), [66](#)
`getResource()` (UriSocket method), [68](#)
`getResourceId()` (ClientSocket method), [59](#)
`getResourceId()` (Resource method), [55](#)
`getResourceId()` (ServerClientSocket method), [61](#)
`getResourceId()` (ServerSocket method), [64](#)
`getResourceId()` (Socket method), [66](#)
`getResourceId()` (UriSocket method), [68](#)
`getResponseError()` (Hybi10Protocol method), [40](#)
`getResponseError()` (HybiProtocol method), [44](#)
`getResponseError()` (Protocol method), [48](#)
`getResponseError()` (Rfc6455Protocol method), [52](#)
`getResponseHandshake()` (Hybi10Protocol method), [40](#)
`getResponseHandshake()` (HybiProtocol method), [44](#)
`getResponseHandshake()` (Protocol method), [48](#)
`getResponseHandshake()` (Rfc6455Protocol method), [52](#)
`getServer()` (ConnectionManager method), [21](#)
`getSocket()` (Connection method), [19](#)
`getSocketStreamContextOptions()` (ClientSocket method), [58](#)
`getSocketStreamContextOptions()` (ServerSocket method), [63](#)
`getSocketStreamContextOptions()` (UriSocket method), [68](#)
`getSslStreamContextOptions()` (ClientSocket method), [58](#)

- getSslStreamContextOptions() (ServerSocket method), [63](#)
 - getSslStreamContextOptions() (UriSocket method), [68](#)
 - getStreamContext() (ClientSocket method), [59](#)
 - getStreamContext() (ServerSocket method), [63](#)
 - getStreamContext() (UriSocket method), [67](#)
 - getSuccessResponseHeaders() (Hybi10Protocol method), [42](#)
 - getSuccessResponseHeaders() (HybiProtocol method), [46](#)
 - getSuccessResponseHeaders() (Protocol method), [50](#)
 - getSuccessResponseHeaders() (Rfc6455Protocol method), [54](#)
 - getTrace() (BadRequestException method), [22](#)
 - getTrace() (CloseException method), [22](#)
 - getTrace() (ConnectionException method), [23](#)
 - getTrace() (Exception method), [24](#)
 - getTrace() (FrameException method), [24](#)
 - getTrace() (HandshakeException method), [25](#)
 - getTrace() (InvalidOriginException method), [26](#)
 - getTrace() (PayloadException method), [26](#)
 - getTrace() (RateLimiterException method), [27](#)
 - getTrace() (SocketException method), [28](#)
 - getTraceAsString() (BadRequestException method), [22](#)
 - getTraceAsString() (CloseException method), [22](#)
 - getTraceAsString() (ConnectionException method), [23](#)
 - getTraceAsString() (Exception method), [24](#)
 - getTraceAsString() (FrameException method), [24](#)
 - getTraceAsString() (HandshakeException method), [25](#)
 - getTraceAsString() (InvalidOriginException method), [26](#)
 - getTraceAsString() (PayloadException method), [26](#)
 - getTraceAsString() (RateLimiterException method), [27](#)
 - getTraceAsString() (SocketException method), [28](#)
 - getType() (Frame method), [29](#)
 - getType() (HybiFrame method), [31](#)
 - getType() (HybiPayload method), [36](#)
 - getType() (Payload method), [38](#)
 - getUri() (BasicServer method), [13](#)
 - getUri() (ClientSocket method), [59](#)
 - getUri() (ConnectionManager method), [21](#)
 - getUri() (Server method), [56](#)
 - getUri() (ServerSocket method), [63](#)
 - getUri() (UriSocket method), [67](#)
 - getVersion() (Hybi10Protocol method), [39](#)
 - getVersion() (HybiProtocol method), [43](#)
 - getVersion() (Protocol method), [47](#)
 - getVersion() (Rfc6455Protocol method), [52](#)
- ## H
- handle() (Connection method), [17](#)
 - handlePayload() (Connection method), [18](#)
 - handshake() (Connection method), [17](#)
 - handshaked (Connection property), [16](#)
 - HandshakeException (class), [24](#)
 - HandshakeRequestListener (class), [32](#)
 - headers (Client property), [14](#)
 - headers (Connection property), [16](#)
 - host (ClientSocket property), [58](#)
 - host (ServerSocket property), [62](#)
 - host (UriSocket property), [67](#)
 - httpResponses (Hybi10Protocol property), [39](#)
 - httpResponses (HybiProtocol property), [43](#)
 - httpResponses (Protocol property), [47](#)
 - httpResponses (Rfc6455Protocol property), [52](#)
 - Hybi10Protocol (class), [38](#)
 - Hybi10Protocol::CLOSE_NORMAL (class constant), [38](#)
 - Hybi10Protocol::CONNECTION_VALUE (class constant), [38](#)
 - Hybi10Protocol::HEADER_HOST (class constant), [38](#)
 - Hybi10Protocol::HEADER_LINE_FORMAT (class constant), [39](#)
 - Hybi10Protocol::HTTP_SWITCHING_PROTOCOLS (class constant), [38](#)
 - Hybi10Protocol::MAGIC_GUID (class constant), [38](#)
 - Hybi10Protocol::REQUEST_LINE_FORMAT (class constant), [39](#)
 - Hybi10Protocol::REQUEST_LINE_REGEX (class constant), [39](#)
 - Hybi10Protocol::RESPONSE_LINE_FORMAT (class constant), [39](#)
 - Hybi10Protocol::SCHEME_WEBSOCKET (class constant), [38](#)
 - Hybi10Protocol::TYPE_CONTINUATION (class constant), [38](#)
 - Hybi10Protocol::UPGRADE_VALUE (class constant), [38](#)
 - HybiFrame (class), [30](#)
 - HybiPayload (class), [35](#)
 - HybiProtocol (class), [42](#)
 - HybiProtocol::CLOSE_NORMAL (class constant), [42](#)
 - HybiProtocol::CONNECTION_VALUE (class constant), [43](#)
 - HybiProtocol::HEADER_HOST (class constant), [42](#)
 - HybiProtocol::HEADER_LINE_FORMAT (class constant), [43](#)
 - HybiProtocol::HTTP_SWITCHING_PROTOCOLS (class constant), [42](#)
 - HybiProtocol::MAGIC_GUID (class constant), [42](#)
 - HybiProtocol::REQUEST_LINE_FORMAT (class constant), [43](#)
 - HybiProtocol::REQUEST_LINE_REGEX (class constant), [43](#)
 - HybiProtocol::RESPONSE_LINE_FORMAT (class constant), [43](#)
 - HybiProtocol::SCHEME_WEBSOCKET (class constant), [42](#)
 - HybiProtocol::TYPE_CONTINUATION (class constant), [42](#)

HybiProtocol::UPGRADE_VALUE (class constant), [42](#)

I

id (Connection property), [16](#)
InvalidOriginException (class), [25](#)
ip (Connection property), [16](#)
ips (RateLimiter property), [34](#)
isAllowed() (OriginPolicy method), [33](#)
isComplete() (Frame method), [29](#)
isComplete() (HybiFrame method), [32](#)
isComplete() (HybiPayload method), [36](#)
isComplete() (Payload method), [37](#)
isConnected() (Client method), [16](#)
isConnected() (ClientSocket method), [59](#)
isConnected() (ServerClientSocket method), [61](#)
isConnected() (ServerSocket method), [64](#)
isConnected() (Socket method), [66](#)
isConnected() (UriSocket method), [68](#)
isFinal() (Frame method), [29](#)
isFinal() (HybiFrame method), [31](#)
isMasked() (HybiFrame method), [31](#)
isWaitingForData() (Frame method), [29](#)
isWaitingForData() (HybiFrame method), [32](#)
isWaitingForData() (HybiPayload method), [36](#)
isWaitingForData() (Payload method), [37](#)

L

length (Frame property), [28](#)
length (HybiFrame property), [30](#)
limit() (RateLimiter method), [35](#)
line (BadRequestException property), [21](#)
line (CloseException property), [22](#)
line (ConnectionException property), [23](#)
line (Exception property), [23](#)
line (FrameException property), [24](#)
line (HandshakeException property), [25](#)
line (InvalidOriginException property), [25](#)
line (PayloadException property), [26](#)
line (RateLimiterException property), [27](#)
line (SocketException property), [27](#)
listen() (ConnectionManager method), [20](#)
listen() (Listener method), [33](#)
listen() (OriginPolicy method), [33](#)
listen() (RateLimiter method), [34](#)
listen() (ServerSocket method), [63](#)
Listener (class), [33](#)
listeners (BasicServer property), [12](#)
listeners (Server property), [55](#)
listening (ServerSocket property), [62](#)
log() (BasicServer method), [13](#)
log() (Connection method), [18](#)
log() (ConnectionManager method), [21](#)
log() (RateLimiter method), [35](#)
log() (Server method), [56](#)

logger (BasicServer property), [12](#)
logger (Server property), [55](#)

M

manager (Connection property), [16](#)
mask (HybiFrame property), [30](#)
mask() (HybiFrame method), [30](#)
masked (HybiFrame property), [30](#)
message (BadRequestException property), [21](#)
message (CloseException property), [22](#)
message (ConnectionException property), [22](#)
message (Exception property), [23](#)
message (FrameException property), [24](#)
message (HandshakeException property), [24](#)
message (InvalidOriginException property), [25](#)
message (PayloadException property), [26](#)
message (RateLimiterException property), [27](#)
message (SocketException property), [27](#)

N

name (ClientSocket property), [58](#)
name (ServerClientSocket property), [60](#)
name (ServerSocket property), [63](#)
name (Socket property), [65](#)
name (UriSocket property), [67](#)
notify() (BasicServer method), [13](#)
notify() (Server method), [57](#)

O

offset_mask (HybiFrame property), [30](#)
offset_payload (HybiFrame property), [30](#)
onClientData() (RateLimiter method), [34](#)
onData() (Application method), [11](#)
onData() (Connection method), [17](#)
onData() (EchoApplication method), [11](#)
onHandshakeRequest() (HandshakeRequestListener method), [32](#)
onHandshakeRequest() (OriginPolicy method), [33](#)
onSocketConnect() (RateLimiter method), [34](#)
onSocketDisconnect() (RateLimiter method), [34](#)
options (BasicServer property), [12](#)
options (Client property), [15](#)
options (ClientSocket property), [58](#)
options (Configurable property), [69](#)
options (Connection property), [17](#)
options (ConnectionManager property), [19](#)
options (RateLimiter property), [34](#)
options (Server property), [55](#)
options (ServerClientSocket property), [60](#)
options (ServerSocket property), [63](#)
options (Socket property), [65](#)
options (UriSocket property), [67](#)
origin (Client property), [14](#)
originPolicy (BasicServer property), [12](#)

OriginPolicy (class), [33](#)

P

Payload (class), [37](#)

payload (Connection property), [16](#)

payload (Frame property), [28](#)

payload (HybiFrame property), [30](#)

PayloadException (class), [26](#)

port (ClientSocket property), [58](#)

port (Connection property), [16](#)

port (ServerSocket property), [62](#)

port (UriSocket property), [67](#)

process() (Connection method), [18](#)

processClientSocket() (ConnectionManager method), [20](#)

processMasterSocket() (ConnectionManager method), [20](#)

protocol (BasicServer property), [12](#)

Protocol (class), [46](#)

protocol (Client property), [14](#)

protocol (ClientSocket property), [58](#)

protocol (Configurable property), [69](#)

protocol (Connection property), [17](#)

protocol (ConnectionManager property), [19](#)

protocol (RateLimiter property), [34](#)

protocol (Server property), [56](#)

protocol (ServerClientSocket property), [60](#)

protocol (ServerSocket property), [63](#)

protocol (Socket property), [65](#)

protocol (UriSocket property), [67](#)

Protocol::CLOSE_NORMAL (class constant), [46](#)

Protocol::CONNECTION_VALUE (class constant), [47](#)

Protocol::HEADER_HOST (class constant), [46](#)

Protocol::HEADER_LINE_FORMAT (class constant), [47](#)

Protocol::HTTP_SWITCHING_PROTOCOLS (class constant), [46](#)

Protocol::MAGIC_GUID (class constant), [47](#)

Protocol::REQUEST_LINE_FORMAT (class constant), [47](#)

Protocol::REQUEST_LINE_REGEX (class constant), [47](#)

Protocol::RESPONSE_LINE_FORMAT (class constant), [47](#)

Protocol::SCHEME_WEBSOCKET (class constant), [46](#)

Protocol::TYPE_CONTINUATION (class constant), [47](#)

Protocol::UPGRADE_VALUE (class constant), [47](#)

Q

queryParams (Connection property), [16](#)

R

rateLimiter (BasicServer property), [12](#)

RateLimiter (class), [33](#)

RateLimiterException (class), [27](#)

receive() (ClientSocket method), [60](#)

receive() (ServerClientSocket method), [62](#)

receive() (ServerSocket method), [64](#)

receive() (Socket method), [66](#)

receive() (UriSocket method), [69](#)

receiveData() (Frame method), [29](#)

receiveData() (HybiFrame method), [31](#)

receiveData() (HybiPayload method), [36](#)

receiveData() (Payload method), [37](#)

reconnect() (ClientSocket method), [58](#)

registerApplication() (BasicServer method), [14](#)

registerApplication() (Server method), [57](#)

releaseConnection() (RateLimiter method), [35](#)

removeConnection() (ConnectionManager method), [21](#)

requests (RateLimiter property), [34](#)

Resource (class), [55](#)

resourceId() (ConnectionManager method), [20](#)

resources (ConnectionManager property), [19](#)

Rfc6455Protocol (class), [51](#)

Rfc6455Protocol::CLOSE_NORMAL (class constant), [51](#)

Rfc6455Protocol::CONNECTION_VALUE (class constant), [51](#)

Rfc6455Protocol::HEADER_HOST (class constant), [51](#)

Rfc6455Protocol::HEADER_LINE_FORMAT (class constant), [51](#)

Rfc6455Protocol::HTTP_SWITCHING_PROTOCOLS (class constant), [51](#)

Rfc6455Protocol::MAGIC_GUID (class constant), [51](#)

Rfc6455Protocol::REQUEST_LINE_FORMAT (class constant), [51](#)

Rfc6455Protocol::REQUEST_LINE_REGEX (class constant), [51](#)

Rfc6455Protocol::RESPONSE_LINE_FORMAT (class constant), [51](#)

Rfc6455Protocol::SCHEME_WEBSOCKET (class constant), [51](#)

Rfc6455Protocol::TYPE_CONTINUATION (class constant), [51](#)

Rfc6455Protocol::UPGRADE_VALUE (class constant), [51](#)

run() (BasicServer method), [13](#)

run() (Server method), [56](#)

S

scheme (ClientSocket property), [58](#)

scheme (ServerSocket property), [62](#)

scheme (UriSocket property), [67](#)

schemes (Hybi10Protocol property), [39](#)

schemes (HybiProtocol property), [43](#)

schemes (Protocol property), [47](#)

schemes (Rfc6455Protocol property), [51](#)

selectAndProcess() (ConnectionManager method), [20](#)

send() (ClientSocket method), [59](#)

send() (Connection method), [18](#)

send() (ServerClientSocket method), [61](#)

send() (ServerSocket method), [64](#)
send() (Socket method), [66](#)
send() (UriSocket method), [69](#)
sendData() (Client method), [15](#)
sendToSocket() (HybiPayload method), [36](#)
sendToSocket() (Payload method), [37](#)
Server (class), [55](#)
server (ConnectionManager property), [19](#)
server (RateLimiter property), [33](#)
Server::EVENT_SOCKET_CONNECT (class constant), [55](#)
ServerClientSocket (class), [60](#)
ServerClientSocket::DEFAULT_RECEIVE_LENGTH (class constant), [60](#)
ServerClientSocket::NAME_PART_IP (class constant), [60](#)
ServerClientSocket::TIMEOUT_SOCKET (class constant), [60](#)
ServerSocket (class), [62](#)
ServerSocket::DEFAULT_RECEIVE_LENGTH (class constant), [62](#)
ServerSocket::NAME_PART_IP (class constant), [62](#)
ServerSocket::TIMEOUT_SOCKET (class constant), [62](#)
setLogger() (BasicServer method), [13](#)
setLogger() (Server method), [56](#)
Socket (class), [64](#)
socket (Client property), [14](#)
socket (ClientSocket property), [58](#)
socket (Connection property), [16](#)
socket (ConnectionManager property), [19](#)
socket (ServerClientSocket property), [60](#)
socket (ServerSocket property), [62](#)
socket (Socket property), [65](#)
socket (UriSocket property), [67](#)
Socket::DEFAULT_RECEIVE_LENGTH (class constant), [65](#)
Socket::NAME_PART_IP (class constant), [65](#)
Socket::TIMEOUT_SOCKET (class constant), [64](#)
SocketException (class), [27](#)
Ssl (class), [69](#)

T

type (Frame property), [28](#)
type (HybiFrame property), [30](#)

U

unmask() (HybiFrame method), [31](#)
uri (BasicServer property), [12](#)
uri (Client property), [14](#)
uri (Server property), [55](#)
UriSocket (class), [66](#)
UriSocket::DEFAULT_RECEIVE_LENGTH (class constant), [66](#)
UriSocket::NAME_PART_IP (class constant), [67](#)

UriSocket::TIMEOUT_SOCKET (class constant), [66](#)

V

validateOriginUri() (Hybi10Protocol method), [41](#)
validateOriginUri() (HybiProtocol method), [45](#)
validateOriginUri() (Protocol method), [49](#)
validateOriginUri() (Rfc6455Protocol method), [53](#)
validateRequestHandshake() (Hybi10Protocol method), [40](#)
validateRequestHandshake() (HybiProtocol method), [44](#)
validateRequestHandshake() (Protocol method), [49](#)
validateRequestHandshake() (Rfc6455Protocol method), [53](#)
validateRequestLine() (Hybi10Protocol method), [41](#)
validateRequestLine() (HybiProtocol method), [45](#)
validateRequestLine() (Protocol method), [49](#)
validateRequestLine() (Rfc6455Protocol method), [53](#)
validateResponseHandshake() (Hybi10Protocol method), [40](#)
validateResponseHandshake() (HybiProtocol method), [44](#)
validateResponseHandshake() (Protocol method), [48](#)
validateResponseHandshake() (Rfc6455Protocol method), [53](#)
validateScheme() (Hybi10Protocol method), [41](#)
validateScheme() (HybiProtocol method), [46](#)
validateScheme() (Protocol method), [50](#)
validateScheme() (Rfc6455Protocol method), [54](#)
validateSocketUri() (Hybi10Protocol method), [41](#)
validateSocketUri() (HybiProtocol method), [45](#)
validateSocketUri() (Protocol method), [49](#)
validateSocketUri() (Rfc6455Protocol method), [53](#)
validateUri() (Hybi10Protocol method), [40](#)
validateUri() (HybiProtocol method), [45](#)
validateUri() (Protocol method), [49](#)
validateUri() (Rfc6455Protocol method), [53](#)